



SECS/GEM Interface Option for Fluidmove for Windows®

**FmXP Version 5.3
FmNT Version 4.9.3**

User Guide

P/N 7223396 Rev A

Notice

This is an Asymtek publication which is protected by copyright. Original copyright date 2009. No part of this document may be photocopied, reproduced, or translated to another language without the prior written consent of Asymtek. The information contained in this publication is subject to change without notice.

Manuals on the Internet

For the convenience of Asymtek customers and field service representatives, copies of this manual can be downloaded from http://www.asymtek.com/support/manuals_request.htm.

Contact Us

Asymtek welcomes requests for information, comments, and inquiries about its products. General information about Asymtek can be found on the Internet at www.asymtek.com.

| | |
|---|--|
|  | |
| Headquarters | 2762 Loker Avenue West Carlsbad, CA 92010-6603 USA |
| Toll Free: | 1-800-ASYMTEK (1-800-279-6835) |
| Tel: | +1-760-431-1919 |
| Fax: | +1-760-431-2678 |
| E-mail: | info@asymtek.com |
| Website: | www.asymtek.com |
| Technical Support | |
| USA: | 1-800-ASYMTEK (1-800-279-6835) |
| Other regions: | www.asymtek.com/support.htm |

Trademarks

Asymtek[®] and Fluidmove[®] are registered trademarks of Asymtek.

Microsoft[®], Windows[®], Windows NT[®], and Windows XP[®] are registered trademarks of Microsoft Corporation.

Table of Contents

| | | |
|----------|---|------------|
| 1 | Introduction..... | 1-1 |
| 1.1 | Overview..... | 1-1 |
| 1.2 | Terminology..... | 1-1 |
| 1.3 | SECS/GEM – Fluidmove Compatibility | 1-3 |
| 1.4 | SECS Standard | 1-3 |
| 1.4.1 | SECS-I Clarifications | 1-3 |
| 1.4.2 | Physical Connection | 1-4 |
| 1.4.3 | SECS-I Blocks Transmitted..... | 1-4 |
| 1.4.4 | Interleaved Blocks | 1-5 |
| 1.4.5 | Simultaneous Transactions | 1-5 |
| 1.5 | SECS-II Clarifications..... | 1-5 |
| 1.5.1 | Data Format Types..... | 1-5 |
| 1.5.2 | Data Item Length Bytes | 1-5 |
| 1.5.3 | ASCII Data..... | 1-5 |
| 1.5.4 | Multi-Block Messages | 1-5 |
| 1.5.5 | Function Zero | 1-6 |
| 1.6 | GEM Standard..... | 1-6 |
| 1.7 | GEM Compliance | 1-6 |
| 1.8 | SEMI E10 Standard..... | 1-8 |
| 1.9 | SECS I / SECS II Parameters | 1-8 |
| 1.9.1 | SECS-I Parameters..... | 1-8 |
| 1.9.2 | SECS-II Parameters..... | 1-8 |
| 1.9.3 | GEM Configuration | 1-9 |
| 1.10 | State Diagrams..... | 1-10 |
| 1.11 | Machine Operation and the GEM Interface | 1-11 |
| 1.11.1 | Connecting to the Host..... | 1-11 |
| 1.11.2 | Device Identification | 1-11 |
| 1.11.3 | Clock | 1-11 |
| 1.11.4 | Loss of Communications Link: Spooling | 1-12 |
| 1.11.5 | Communications Error Messages | 1-12 |
| 1.11.6 | Normal Communications..... | 1-12 |
| 1.11.7 | SECS/GEM Setup Dialog Box in Fluidmove | 1-14 |
| 1.11.8 | Fluidmove Run Window Interface | 1-19 |
| 2 | Message Summary | 2-1 |
| 2.1 | Overview..... | 2-1 |
| 2.2 | Host-to-Equipment Messages | 2-1 |
| 2.3 | Equipment-to-Host Messages | 2-3 |

| | | |
|----------|--|------------|
| 3 | Operating Characteristics | 3-1 |
| 3.1 | Overview..... | 3-1 |
| 3.2 | Communications States | 3-1 |
| 3.2.1 | Communications Finite State Description | 3-1 |
| 3.2.2 | Power Up..... | 3-4 |
| 3.2.3 | Related Variables | 3-4 |
| 3.2.4 | Compatibility | 3-4 |
| 3.3 | Control States..... | 3-5 |
| 3.3.1 | Control Finite State Description..... | 3-6 |
| 3.3.2 | Power Up..... | 3-9 |
| 3.3.3 | Related Variables | 3-9 |
| 3.3.4 | Related Events | 3-9 |
| 3.4 | Process States | 3-10 |
| 3.4.1 | E10 State..... | 3-10 |
| 3.4.2 | Equipment Process States | 3-12 |
| 3.4.3 | Related Variables | 3-14 |
| 3.4.4 | Related Collection Events | 3-14 |
| 3.5 | Data Collection | 3-15 |
| 3.5.1 | Variables..... | 3-15 |
| 3.5.2 | Are You There | 3-15 |
| 3.5.3 | Host Requests Status..... | 3-15 |
| 3.5.4 | Setting Equipment Constants | 3-15 |
| 3.5.5 | Event Reports..... | 3-16 |
| 3.5.6 | Time Driven Trace..... | 3-16 |
| 3.5.7 | Limits Monitoring | 3-16 |
| 3.5.8 | Limits State Transitions | 3-19 |
| 3.5.9 | Disk Files..... | 3-20 |
| 3.5.10 | Related Variables | 3-20 |
| 3.5.11 | Related Events | 3-20 |
| 3.6 | Alarm Management..... | 3-21 |
| 3.6.1 | Alarm States..... | 3-21 |
| 3.6.2 | Reporting..... | 3-21 |
| 3.6.3 | Enable/Disable | 3-21 |
| 3.6.4 | Host Requests Alarm Status | 3-21 |
| 3.6.5 | Compatibility | 3-22 |
| 3.6.6 | Related Variables | 3-22 |
| 3.6.7 | Related Collection Events | 3-22 |
| 3.7 | Process Program Management | 3-23 |
| 3.7.1 | Equipment Management of Process Programs | 3-23 |
| 3.7.2 | Host Management of Process Programs | 3-23 |
| 3.7.3 | Related Variables | 3-24 |
| 3.7.4 | Related Events | 3-24 |
| 3.8 | Remote Commands | 3-25 |
| 3.8.1 | S2F41 Commands | 3-25 |
| 3.8.2 | Related Variables | 3-28 |
| 3.8.3 | Related Events | 3-28 |
| 3.9 | Material Movement..... | 3-29 |
| 3.9.1 | Related Variables | 3-29 |
| 3.9.2 | Related Collection Events | 3-29 |

| | | |
|----------|---|------------|
| 3.10 | Equipment Terminal Services | 3-30 |
| 3.11 | Error Messages | 3-31 |
| 3.12 | Clock | 3-31 |
| 3.12.1 | Related Variables | 3-31 |
| 3.13 | Spooling..... | 3-32 |
| 3.13.1 | A Word of Caution..... | 3-32 |
| 3.13.2 | Spooling Sequence | 3-32 |
| 3.13.3 | Spool States | 3-36 |
| 3.13.4 | Related Variables | 3-37 |
| 3.13.5 | Related Events | 3-37 |
| 4 | SECS Message Detail | 4-1 |
| 4.1 | SML Notation..... | 4-1 |
| 4.1.1 | Data Item Format | 4-1 |
| 4.1.2 | Message Format | 4-3 |
| 4.2 | SECS Messages | 4-4 |
| 4.2.1 | S1F1 - Are You There | 4-4 |
| 4.2.2 | S1F2 - On Line Data (Equipment to Host) | 4-4 |
| 4.2.3 | S1F2 - On Line Data (Host to Equipment) | 4-4 |
| 4.2.4 | S1F3 - Selected Status Request..... | 4-5 |
| 4.2.5 | S1F4 - Selected Status Data..... | 4-5 |
| 4.2.6 | S1F11 - Status Variable Namelist Request..... | 4-6 |
| 4.2.7 | S1F12 - Status Variable Namelist Reply | 4-6 |
| 4.2.8 | S1F13 - Connect Request..... | 4-7 |
| 4.2.9 | S1F14 - Connect Request Acknowledge | 4-7 |
| 4.2.10 | S1F15 - Request Off-Line | 4-8 |
| 4.2.11 | S1F16 - Off-Line Acknowledge | 4-8 |
| 4.2.12 | S1F17 - Request On-Line | 4-8 |
| 4.2.13 | S1F18 - On-Line Acknowledge | 4-8 |
| 4.2.14 | S1F65 - Connect Request..... | 4-9 |
| 4.2.15 | S1F66 - Connect Request Acknowledge | 4-10 |
| 4.2.16 | S2F13 - Equipment Constant Request..... | 4-11 |
| 4.2.17 | S2F14 - Equipment Constant Data | 4-11 |
| 4.2.18 | S2F15 - New Equipment Constant Send | 4-12 |
| 4.2.19 | S2F16 - Equipment Constant Send Acknowledge | 4-12 |
| 4.2.20 | S2F17 - Date and Time Request..... | 4-13 |
| 4.2.21 | S2F18 - Date and Time Data | 4-13 |
| 4.2.22 | S2F23 - Trace Initialize Send | 4-14 |
| 4.2.23 | S2F24 - Trace Initialize Acknowledge | 4-15 |
| 4.2.24 | S2F25 - Diagnostic Loopback Request..... | 4-15 |
| 4.2.25 | S2F26 - Diagnostic Loopback Data..... | 4-16 |
| 4.2.26 | S2F27 - Initiate Process Request..... | 4-16 |
| 4.2.27 | S2F28 - Initiate Process Acknowledge..... | 4-16 |
| 4.2.28 | S2F29 - Equipment Constant Namelist Request | 4-17 |
| 4.2.29 | S2F30 - Equipment Constant Namelist Reply..... | 4-17 |
| 4.2.30 | S2F31 - Date and Time Send..... | 4-18 |
| 4.2.31 | S2F32 - Date and Time Acknowledge..... | 4-18 |
| 4.2.32 | S2F33 - Define Report | 4-18 |
| 4.2.33 | S2F34 - Define Report Acknowledge | 4-19 |
| 4.2.34 | S2F35 - Link Event Report | 4-20 |
| 4.2.35 | S2F36 - Link Event Report Acknowledge..... | 4-21 |
| 4.2.36 | S2F37 - Enable/Disable Event Report..... | 4-21 |
| 4.2.37 | S2F38 - Enable/Disable Event Report Acknowledge | 4-22 |
| 4.2.38 | S2F39 - Multi-Block Inquire | 4-22 |
| 4.2.39 | S2F40 - Multi-Block Grant | 4-22 |

| | | |
|--------|--|------|
| 4.2.40 | S2F41 - Remote Command with Parameters | 4-23 |
| 4.2.41 | S2F42 - Remote Command Acknowledge | 4-24 |
| 4.2.42 | S2F43 - Reset Spooling Streams and Functions | 4-25 |
| 4.2.43 | S2F44 - Reset Spooling Acknowledge | 4-26 |
| 4.2.44 | S2F45 - Define Variable Limits Attributes | 4-27 |
| 4.2.45 | S2F46 - Variable Limit Attribute Acknowledge | 4-29 |
| 4.2.46 | S2F47 - Variable Limit Attribute Request | 4-31 |
| 4.2.47 | S2F48 - Variable Limit Attributes Send | 4-31 |
| 4.2.48 | S5F1 - Alarm Report | 4-33 |
| 4.2.49 | S5F2 - Alarm Acknowledge | 4-33 |
| 4.2.50 | S5F3 - Enable/Disable Alarm Send | 4-34 |
| 4.2.51 | S5F4 - Enable/Disable Alarm Acknowledge | 4-34 |
| 4.2.52 | S5F5 - List Alarms Request | 4-35 |
| 4.2.53 | S5F6 - List Alarm Data | 4-35 |
| 4.2.54 | S5F7 - List Enabled Alarms Request | 4-36 |
| 4.2.55 | S5F8 - List Enabled Alarm Data | 4-36 |
| 4.2.56 | S5F71 - Alarm Report Block Send | 4-37 |
| 4.2.57 | S5F72 - Alarm Report Block Acknowledge | 4-38 |
| 4.2.58 | S5F73 - Alarm Report Block Acknowledge | 4-38 |
| 4.2.59 | S5F74 - Alarm Notification Acknowledge | 4-38 |
| 4.2.60 | S6F1 - Trace Data Send | 4-39 |
| 4.2.61 | S6F2 - Trace Data Acknowledge | 4-40 |
| 4.2.62 | S6F3 - Annotated Event Report | 4-40 |
| 4.2.63 | S6F4 - Annotated Event Report Acknowledge | 4-41 |
| 4.2.64 | S6F5 - Multi-Block Data Send Inquire | 4-41 |
| 4.2.65 | S6F6 - Multi-Block Grant | 4-42 |
| 4.2.66 | S6F9 - Event Report | 4-42 |
| 4.2.67 | S6F10 - Event Report Acknowledge | 4-43 |
| 4.2.68 | S6F11 - Event Report Send | 4-43 |
| 4.2.69 | S6F12 - Event Report Acknowledge | 4-44 |
| 4.2.70 | S6F13 - Annotated Event Report Send | 4-45 |
| 4.2.71 | S6F14 - Annotated Event Report Acknowledge | 4-46 |
| 4.2.72 | S6F15 - Event Report Request | 4-46 |
| 4.2.73 | S6F16 - Event Report Data | 4-47 |
| 4.2.74 | S6F17 - Annotated Event Report Request | 4-48 |
| 4.2.75 | S6F18 - Annotated Event Report Data | 4-48 |
| 4.2.76 | S6F19 - Request Report Request | 4-49 |
| 4.2.77 | S6F20 - Request Report Data | 4-49 |
| 4.2.78 | S6F21 - Request Annotated Report Request | 4-49 |
| 4.2.79 | S6F22 - Request Annotated Report Data | 4-50 |
| 4.2.80 | S6F23 - Request Spooled Data | 4-50 |
| 4.2.81 | S6F24 - Request Spooled Data Acknowledge | 4-51 |
| 4.2.82 | S7F1 - Process Program Load Inquire | 4-51 |
| 4.2.83 | S7F2 - Process Program Load Grant | 4-52 |
| 4.2.84 | S7F3 - Process Program Send | 4-52 |
| 4.2.85 | S7F4 - Process Program Acknowledge | 4-53 |
| 4.2.86 | S7F5 - Process Program Request | 4-53 |
| 4.2.87 | S7F6 - Process Program Data | 4-54 |
| 4.2.88 | S7F17 - Process Program Delete | 4-54 |
| 4.2.89 | S7F18 - Process Program Delete Acknowledge | 4-55 |
| 4.2.90 | S7F19 - Process Program Directory Request | 4-55 |
| 4.2.91 | S7F20 - Process Program Directory | 4-55 |
| 4.2.92 | S9F1 - Unrecognized Device ID | 4-55 |
| 4.2.93 | S9F3 - Unrecognized Stream | 4-56 |
| 4.2.94 | S9F5 - Unrecognized Function | 4-56 |
| 4.2.95 | S9F7 Invalid Data | 4-56 |
| 4.2.96 | S9F9 Transaction Timer Timeout | 4-56 |
| 4.2.97 | S9F11 - Data Too Long | 4-56 |
| 4.2.98 | S10F1 - Terminal Request | 4-56 |

| | | |
|----------|---|------------|
| 4.2.99 | S10F2 - Terminal Request Acknowledge..... | 4-57 |
| 4.2.100 | S10F3 - Terminal Display, Single..... | 4-57 |
| 4.2.101 | S10F4 - Terminal Display Single Acknowledge | 4-57 |
| 4.2.102 | S10F5 - Terminal Display, Multiblock..... | 4-58 |
| 4.2.103 | S10F6 - Terminal Display Multiblock Acknowledge | 4-58 |
| 4.2.104 | S10F9 - Broadcast | 4-59 |
| 4.2.105 | S10F10 - Broadcast Acknowledge | 4-59 |
| 5 | SECS Scenarios | 5-1 |
| 5.1 | Equipment Communications | 5-1 |
| 5.1.1 | Equipment Establishes Communications..... | 5-1 |
| 5.1.2 | Host Establishes Communications..... | 5-1 |
| 5.1.3 | Simultaneous Establish Communications | 5-2 |
| 5.1.4 | Losing Connection, Re-Connecting..... | 5-2 |
| 5.1.5 | Heartbeat..... | 5-2 |
| 5.2 | Data Collection | 5-3 |
| 5.2.1 | Host Initializes Event Reporting..... | 5-3 |
| 5.2.2 | Equipment Reports Event | 5-4 |
| 5.2.3 | Equipment Reports Annotated Event | 5-4 |
| 5.2.4 | Host Initiates Trace | 5-5 |
| 5.2.5 | Host Terminates Trace..... | 5-5 |
| 5.2.6 | Host Requests Status..... | 5-5 |
| 5.2.7 | Host Defines Limits | 5-6 |
| 5.2.8 | Host Queries Defined Limits..... | 5-6 |
| 5.2.9 | Host Requests Report by CEID..... | 5-6 |
| 5.2.10 | Host Requests Annotated Report by CEID | 5-6 |
| 5.2.11 | Host Requests Report by RPTID | 5-7 |
| 5.2.12 | Host Requests Annotated Report by RPTID | 5-7 |
| 5.2.13 | Are You There | 5-7 |
| 5.2.14 | Host Reads Equipment Constants | 5-7 |
| 5.2.15 | Host Sets Equipment Constants | 5-7 |
| 5.3 | Alarms | 5-8 |
| 5.3.1 | Equipment Reports Alarm | 5-8 |
| 5.3.2 | Host Enables/Disables Alarms | 5-8 |
| 5.3.3 | Host Requests Alarms..... | 5-8 |
| 5.3.4 | Alarm Report (GEM, Ver 3.1 Compatibility) | 5-9 |
| 5.3.5 | Alarm Report (GEM, Ver 1.7 Compatibility) | 5-9 |
| 5.4 | Control State..... | 5-10 |
| 5.4.1 | Host Sends On-Line Command | 5-10 |
| 5.4.2 | Host Sends Off-Line Command | 5-10 |
| 5.4.3 | Host Sends Remote Command | 5-10 |
| 5.4.4 | Equipment Rejects Host Command | 5-11 |
| 5.4.5 | Go Remote, Operator-Initiated | 5-11 |
| 5.4.6 | Go Local, Operator-Initiated | 5-11 |
| 5.4.7 | Go Local, Host-Initiated | 5-12 |
| 5.4.8 | Operator Command, Successful | 5-12 |
| 5.5 | Process Program Management | 5-13 |
| 5.5.1 | Unformatted, Host-Initiated Download | 5-13 |
| 5.5.2 | Unformatted, Host-Initiated Upload | 5-13 |
| 5.5.3 | Unformatted, Equipment-Initiated Download..... | 5-13 |
| 5.5.4 | Unformatted, Equipment-Initiated Upload | 5-14 |
| 5.5.5 | Host Deletes Process Program | 5-14 |
| 5.5.6 | Host Requests Directory | 5-15 |
| 5.5.7 | Operator Changes Process Program Library | 5-15 |

| | | |
|---|--|------------|
| 5.6 | Equipment Terminal Communications | 5-16 |
| 5.6.1 | Host to Equipment, Single Line | 5-16 |
| 5.6.2 | Host to Equipment, Multi-Line | 5-16 |
| 5.6.3 | Equipment Sends Text to Host..... | 5-16 |
| 5.7 | SECS Error Messages | 5-17 |
| 5.7.1 | Unrecognized Device ID..... | 5-17 |
| 5.7.2 | Unrecognized Stream..... | 5-17 |
| 5.7.3 | Unrecognized Function..... | 5-17 |
| 5.7.4 | Illegal Data Format | 5-18 |
| 5.7.5 | Data Too Long..... | 5-18 |
| 5.8 | Clock | 5-19 |
| 5.8.1 | Host Sets Date and Time | 5-19 |
| 5.8.2 | Host Requests Date and Time | 5-19 |
| 5.8.3 | Equipment Requests Date and Time | 5-19 |
| 5.9 | Spooling..... | 5-20 |
| 5.9.1 | Host Enables Spooling of Messages..... | 5-20 |
| 5.9.2 | Messages Spooled and Transmitted..... | 5-21 |
| 5.9.3 | Host Purges Spool | 5-22 |
| 6 | Machine Variable Definitions..... | 6-1 |
| 6.1 | Status Variables | 6-1 |
| 6.2 | Data Variables | 6-4 |
| 6.3 | Equipment Constants | 6-8 |
| 7 | Host-to-Equipment Messages | 7-1 |
| 8 | Equipment-to-Host Messages | 8-1 |
| Appendix A All Variables | | A-1 |
| A.1 | Overview..... | A-1 |
| A.2 | Data Formats..... | A-1 |
| A.3 | Variables..... | A-1 |
| Appendix B Collection Events | | B-1 |
| B.1 | Overview..... | B-1 |
| B.2 | Collection Events..... | B-1 |
| Appendix C Alarms..... | | C-1 |
| C.1 | Overview..... | C-1 |
| C.2 | Alarm Format..... | C-1 |
| C.3 | Alarms | C-1 |
| Appendix D FmConfig.ini File Variables | | D-1 |
| D.1 | Overview..... | D-1 |
| D.2 | FmConfig.ini File Variables | D-1 |
| Appendix E SECS/GEM Remote Commands | | E-1 |
| E.1 | Overview..... | E-1 |
| E.2 | SECS/GEM Remote Commands | E-1 |

| | | |
|-------------------|--|------------|
| Appendix F | Variables Grouped by Fluidmove Activity | F-1 |
| F.1 | Overview | F-1 |
| F.2 | Setup Level Variables | F-4 |
| F.3 | Lot Level Variables | F-5 |
| F.4 | Carrier Level Variables and Equipment Constants | F-6 |
| F.5 | Configuration Parameter Download Rejection Variables | F-9 |
| F.6 | Configuration Change Notification | F-10 |
| | New Collection Events | F-10 |
| | New Data Variables | F-11 |
| F.7 | Recipe Change Notification | F-12 |
| F.8 | Program Instruction Variables | F-13 |
| | Program Modification Collection Events | F-13 |
| | Program Header Change Collection Events | F-15 |
| | Heater Parameter Change Collection Events | F-15 |
| | Heater File Data Variables | F-18 |
| | Fluid File Variables | F-20 |
| | Fluid File Data Variables | F-21 |
| F.9 | Local Machine Offsets (LMO) - Workpiece Origin | F-27 |
| F.10 | LMO Workpiece Align – Remote Command | F-29 |
| | LMO Workpiece Align HCACK Rejection Codes | F-29 |
| F.11 | LMO Height Sense | F-30 |
| F.12 | Dispense Head Linear Fluid Sensor Level Percent | F-31 |
| F.13 | Dispense Head Linear Fluid Level State | F-31 |
| F.14 | Limited Start Number of Runs | F-32 |
| F.15 | Remote Restart Application – Remote Command | F-33 |
| F.16 | Calibrated Process Jetting (CPJ) – Remote Command | F-34 |
| F.17 | Flow Rate Calibration – Remote Command | F-37 |
| F.18 | Dispense Weight Verification (DWV) – Remote Command | F-42 |
| F.19 | DJ9K Vacuum Assisted Prime – Remote Command | F-46 |
| F.20 | Run PSS File – Remote Command | F-49 |
| | Run PSS File Variables | F-50 |
| F.21 | Height Sense XY Offsets – Remote Command | F-52 |
| F.22 | Needle XY Offsets – Remote Command | F-55 |
| F.23 | Needle Z Offsets – Remote Command | F-59 |
| | Needle Z Offsets | F-59 |
| F.24 | Locate Service Station – Remote Command | F-62 |
| F.25 | Prime – Remote Command | F-65 |
| F.26 | Purge – Remote Command | F-68 |
| F.27 | Teach Scale – Remote Command | F-71 |
| F.28 | PP-Select – Remote Command | F-75 |
| F.29 | DJ Offset Calibration – Remote Command | F-77 |

| | | |
|------|---|-------|
| F.30 | Move Home – Remote Command..... | F-82 |
| F.31 | Move To Center – Remote Command | F-84 |
| F.32 | Move To Front – Remote Command..... | F-86 |
| F.33 | Load Board – Remote Command | F-88 |
| F.34 | Vacuum On/Off – Remote Command | F-91 |
| F.35 | Preliminary Needle To Camera Offsets – Remote Command | F-95 |
| F.36 | Control Dot Weight – Remote Command | F-98 |
| F.37 | Auto Setup – Remote commands | F-102 |
| | Locate Service Station..... | F-102 |
| | Needle Z Offsets | F-102 |
| | Teach Scale | F-103 |
| | DJ Offset Calibration | F-105 |
| | Flowrate (dot weight)..... | F-106 |
| F.38 | Abort – Remote Command | F-107 |
| F.39 | Local – Remote Command | F-108 |
| F.40 | Pause – Remote Command..... | F-109 |
| F.41 | Remote – Remote Command | F-110 |
| F.42 | Resume – Remote Command..... | F-111 |
| F.43 | Start – Remote Command | F-112 |
| F.44 | Stop – Remote Command..... | F-113 |
| F.45 | Auto Setup Variables..... | F-114 |
| F.46 | Controlled Process Heat (CpH) Air Flow Variables | F-115 |
| F.47 | Multiple Flow Rates | F-120 |
| F.48 | Carrier Sequence Number | F-124 |
| F.49 | Lane Number..... | F-125 |
| F.50 | Carrier Load/Unload Time Stamps..... | F-126 |
| F.51 | Lookup Camera (LUC) Model Teach/Find | F-127 |
| F.52 | Pressure Controlled CPJ (DWCA) Variables | F-128 |
| | Control Dot Weight – Remote Command | F-128 |
| | DJ9K Dot Weight Pressure Setup – Remote Command | F-128 |
| | FlowRateCalib - Remote Command (existing command)..... | F-131 |
| F.53 | Setup “Offset” Data | F-133 |
| F.54 | Image Capture..... | F-134 |
| F.55 | Additional Offset Variables | F-136 |
| F.56 | Prompted Setup, Flowrate and Purge Collection Events | F-137 |
| F.57 | DJ Cycle Count..... | F-138 |
| F.58 | Low Fluid Collection Events | F-138 |
| F.59 | Height Sense | F-138 |
| F.60 | Electronic Pressure | F-139 |
| F.61 | Scale Number..... | F-140 |

| | | |
|-----------------------|--|------------|
| F.62 | Program Fiducial ON/OFF Control | F-140 |
| | Pattern Fiducials | F-140 |
| | SECS/GEM Control | F-141 |
| | SECS/GEM Variables | F-143 |
| F.63 | Scale Overflow | F-146 |
| | Equipment Constants | F-146 |
| | Collection Events | F-148 |
| F.64 | Electronic Pressure LMO | F-150 |
| | Equipment Constants | F-150 |
| | Status Variables | F-151 |
| | Collection Events | F-151 |
| F.65 | Operator ID | F-152 |
| F.66 | Additional Configuration Parameter Variables | F-153 |
| Glossary | | G-1 |

Table of Figures

| | | |
|---------------|--|-------|
| Figure 1-1 | Terminal Message Notification (FmXP shown)..... | 1-14 |
| Figure 1-2 | SECS/GEM Setup Dialog Box – Control Tab (FmXP shown)..... | 1-15 |
| Figure 1-3 | SECS/GEM Setup Dialog Box – Terminal Tab (FmXP shown) | 1-16 |
| Figure 1-4 | SECS/GEM Setup Dialog Box – Setup Tab (FmXP shown)..... | 1-17 |
| Figure 1-5 | SECS/GEM Setup Dialog Box – Communication Tab (FmXP shown) | 1-18 |
| Figure 1-6 | SECS/GEM Setup Dialog Box – Version Tab (FmXP shown) | 1-18 |
| Figure 1-7 | Run Window – SECS/GEM Tab (FmXP shown)..... | 1-19 |
| Figure 3-1 | Communication Finite State Diagram | 3-1 |
| Figure 3-2 | Equipment Control State Diagram | 3-6 |
| Figure 3-3 | E10 State Diagram | 3-10 |
| Figure 3-4 | Equipment Process States..... | 3-12 |
| Figure 3-5 | Limits Events Signaling | 3-17 |
| Figure 3-6 | Limits State Diagram..... | 3-18 |
| Figure 3-7 | Spooling State Diagram | 3-33 |
| Figure F.29-1 | DJ Line Offset Calibration | F-79 |
| Figure F.47-1 | Fluid Manager – Enable Multiple Flow Rate Calibration | F-121 |
| Figure F.47-2 | Multiple Flow Rate Calibration..... | F-122 |
| Figure F.47-3 | Fluidmove Message – Flow Rate Results | F-123 |
| Figure F.62-1 | Create Pattern – Allow SECS/GEM Control of Fiducial Search | F-141 |
| Figure F.62-2 | Edit SECS/GEM Fid Control..... | F-142 |
| Figure F.62-3 | Multiple Flow Rate Calibration..... | F-142 |
| Figure F.62-4 | Editing Configuration Files | F-144 |
| Figure F.62-5 | Fluidmove – File Versioning Error Message | F-145 |

Table of Tables

| | | |
|------------|--|------|
| Table 1-1 | Definition of Terms | 1-1 |
| Table 1-2 | RS-232 Pins | 1-4 |
| Table 1-3 | GEM Compliance Statement..... | 1-7 |
| Table 1-4 | SECS Installation Parameters..... | 1-8 |
| Table 1-5 | GemRPTYPE | 1-9 |
| Table 1-6 | Compatibility Settings..... | 1-10 |
| Table 1-7 | Remote Run Commands | 1-13 |
| Table 2-1 | SECS Messages – Host-to-Equipment..... | 2-1 |
| Table 2-2 | Control State Values | 2-2 |
| Table 2-3 | SECS Messages – Equipment-to-Host..... | 2-3 |
| Table 3-1 | State Transitions | 3-2 |
| Table 3-2 | Communication State Values..... | 3-3 |
| Table 3-3 | Related Variables | 3-4 |
| Table 3-4 | Control States..... | 3-5 |
| Table 3-5 | Control State Transitions..... | 3-7 |
| Table 3-6 | Control State Values | 3-8 |
| Table 3-7 | Control State Variables | 3-9 |
| Table 3-8 | Control State CEIDS | 3-9 |
| Table 3-9 | E10 State Transitions..... | 3-11 |
| Table 3-10 | E10 State Values..... | 3-11 |
| Table 3-11 | Process State Transitions | 3-13 |
| Table 3-12 | Equipment Process State Values..... | 3-14 |
| Table 3-13 | Equipment Processing Variables | 3-14 |
| Table 3-14 | Limits State Transitions..... | 3-19 |
| Table 3-15 | Limits States..... | 3-19 |
| Table 3-16 | Data Collection / Setup Variables..... | 3-20 |
| Table 3-17 | Data Collection CEIDS | 3-20 |

| | | |
|------------|--|------|
| Table 3-18 | Alarm Management Variables | 3-22 |
| Table 3-19 | Process Program Management Variables | 3-24 |
| Table 3-20 | Process Program Management CEIDS | 3-24 |
| Table 3-21 | Remote Control Variable | 3-28 |
| Table 3-22 | Remote Control CEIDS | 3-28 |
| Table 3-23 | Clock Variables | 3-31 |
| Table 3-24 | Spooling State Transitions | 3-34 |
| Table 3-25 | Spooling Activity | 3-35 |
| Table 3-26 | Power On Spool Substates | 3-36 |
| Table 3-27 | Spooling Variables | 3-37 |
| Table 3-28 | Spooling CEIDS | 3-37 |
| Table 4-1 | Components of a SML Data Item | 4-1 |
| Table 4-2 | Components SML Notation | 4-3 |
| Table 4-3 | On-Line Acknowledge | 4-8 |
| Table 4-4 | EAC Values | 4-12 |
| Table 4-5 | Trace Initialize Acknowledge | 4-15 |
| Table 4-6 | CMDA Values | 4-16 |
| Table 4-7 | TIACK | 4-18 |
| Table 4-8 | DRACK Values | 4-19 |
| Table 4-9 | LRACK Values | 4-21 |
| Table 4-10 | ERACK Values | 4-22 |
| Table 4-11 | ERACK Values | 4-23 |
| Table 4-12 | HCACK Values | 4-24 |
| Table 4-13 | CPACK Values | 4-25 |
| Table 4-14 | RSPACK Values | 4-26 |
| Table 4-15 | STRACK Values | 4-27 |
| Table 4-16 | VLAACK Values | 4-29 |
| Table 4-17 | LVACK Values | 4-30 |
| Table 4-18 | VLACK Values | 4-30 |

| | | |
|------------|--|------|
| Table 4-19 | ALED Values | 4-34 |
| Table 4-20 | ACKC5 Values | 4-34 |
| Table 4-21 | Multi-Block Event Values..... | 4-42 |
| Table 4-22 | RSDC | 4-50 |
| Table 4-23 | RSDA Values | 4-51 |
| Table 4-24 | S7F2 PPGNT Values | 4-52 |
| Table 4-25 | S7F2 PPGNT Interpretations | 4-52 |
| Table 4-26 | S7F4 ACKC7 Values..... | 4-53 |
| Table 4-27 | S7F4 ACKC7 Interpretations..... | 4-53 |
| Table 4-28 | S7F18 ACKC7 Values..... | 4-55 |
| Table 4-29 | S10F1 TID Values..... | 4-56 |
| Table 4-30 | S10F2 ACKC10 Values..... | 4-57 |
| Table 4-31 | S10F3 TID Values..... | 4-57 |
| Table 4-32 | S10F4 ACKC10 Values..... | 4-57 |
| Table 4-33 | S10F5 TID Values..... | 4-58 |
| Table 4-34 | S10F6 ACKC10 Values..... | 4-58 |
| Table 4-35 | S10F10 ACKC10 Values..... | 4-59 |
| Table 5-1 | SECS Messages Equipment Establishes Communications | 5-1 |
| Table 5-2 | SECS Messages Host Establishes Communications | 5-1 |
| Table 5-3 | SECS Messages Simultaneous Establish Communications..... | 5-2 |
| Table 5-4 | SECS Messages Losing Connection, Re-Connecting | 5-2 |
| Table 5-5 | SECS Messages Heartbeat | 5-2 |
| Table 5-6 | SECS Messages Host Initializes Event Reporting | 5-3 |
| Table 5-7 | SECS Messages Equipment Reports Event | 5-4 |
| Table 5-8 | SECS Messages Equipment Reports Annotated Event..... | 5-4 |
| Table 5-9 | SECS Messages Host Initiates Trace | 5-5 |
| Table 5-10 | SECS Messages Host Terminates Trace | 5-5 |
| Table 5-11 | SECS Messages Host Requests Status | 5-5 |
| Table 5-12 | SECS Messages Host Defines Limits | 5-6 |

| | | |
|------------|---|------|
| Table 5-13 | SECS Messages Host Queries Defined Limits | 5-6 |
| Table 5-14 | SECS Messages Host Requests Report by CEID | 5-6 |
| Table 5-15 | SECS Messages Host Requests Annotated Report by CEID | 5-6 |
| Table 5-16 | SECS Messages Host Requests Report by RPTID | 5-7 |
| Table 5-17 | SECS Messages Host Requests Annotated Report by RPTID | 5-7 |
| Table 5-18 | SECS Messages Are You There..... | 5-7 |
| Table 5-19 | SECS Messages Host Reads Equipment Constants..... | 5-7 |
| Table 5-20 | SECS Messages Host Sets Equipment Constants | 5-7 |
| Table 5-21 | SECS Messages Equipment Reports Alarm..... | 5-8 |
| Table 5-22 | SECS Messages Host Enables/Disables Alarms..... | 5-8 |
| Table 5-23 | SECS Messages Host Requests Alarms | 5-8 |
| Table 5-24 | SECS Messages Alarm Report (GEM, Ver 3.1 Compatibility) | 5-9 |
| Table 5-25 | SECS Messages Alarm Report (GEM, Ver 1.7 Compatibility) | 5-9 |
| Table 5-26 | SECS Messages Host Sends On-Line Command | 5-10 |
| Table 5-27 | SECS Messages Host Sends Off-Line Command..... | 5-10 |
| Table 5-28 | SECS Messages Host Sends Remote Command | 5-10 |
| Table 5-29 | SECS Messages Equipment Rejects Host Command..... | 5-11 |
| Table 5-30 | SECS Messages Go Remote, Operator-Initiated..... | 5-11 |
| Table 5-31 | SECS Messages Go Local, Operator-Initiated..... | 5-11 |
| Table 5-32 | SECS Messages Go Local, Host-Initiated | 5-12 |
| Table 5-33 | SECS Messages Operator Command, Successful..... | 5-12 |
| Table 5-34 | SECS Messages Unformatted, Host-Initiated Download | 5-13 |
| Table 5-35 | SECS Messages Unformatted, Host-Initiated Upload..... | 5-13 |
| Table 5-36 | SECS Messages Unformatted, Equipment-Initiated Download | 5-13 |
| Table 5-37 | SECS Messages Unformatted, Equipment-Initiated Upload..... | 5-14 |
| Table 5-38 | SECS Messages Host Deletes Process Program | 5-14 |
| Table 5-39 | SECS Messages Host Requests Directory | 5-15 |
| Table 5-40 | SECS Messages Operator Changes Process Program Library | 5-15 |
| Table 5-41 | SECS Messages Host to Equipment, Single Line..... | 5-16 |

| | | |
|-------------|--|------|
| Table 5-42 | SECS Messages Host to Equipment, Multi-Line | 5-16 |
| Table 5-43 | SECS Messages Equipment Sends Text to Host | 5-16 |
| Table 5-44 | SECS Messages Unrecognized Device ID | 5-17 |
| Table 5-45 | SECS Messages Unrecognized Stream | 5-17 |
| Table 5-46 | SECS Messages Unrecognized Function | 5-17 |
| Table 5-47 | SECS Messages Illegal Data Format..... | 5-18 |
| Table 5-48 | SECS Messages Data Too Long | 5-18 |
| Table 5-49 | SECS Messages Host Sets Date and Time..... | 5-19 |
| Table 5-50 | SECS Messages Host Requests Date and Time..... | 5-19 |
| Table 5-51 | SECS Messages Equipment Requests Date and Time..... | 5-19 |
| Table 5-52 | SECS Messages Host Enables Spooling of Messages | 5-20 |
| Table 5-53 | SECS Messages Spooled and Transmitted..... | 5-21 |
| Table 5-54 | SECS Messages Host Purges Spool | 5-22 |
| Table 6-1 | Status Variables | 6-1 |
| Table 6-2 | Data Variables..... | 6-4 |
| Table 6-3 | Equipment Constants..... | 6-8 |
| Table 7-1 | Host-to-Equipment Messages..... | 7-1 |
| Table 8-1 | Equipment-to-Host Messages..... | 8-1 |
| Table C-1 | Alarms | C-1 |
| Table F.2-1 | Setup Level Variables | F-4 |
| Table F.3-1 | Lot Level Variables..... | F-5 |
| Table F.3-2 | Lot Level Variables – Related Collection Events..... | F-5 |
| Table F.4-1 | Carrier Level Variables..... | F-6 |
| Table F.4-2 | Carrier Level Variables – Related Collection Events..... | F-8 |
| Table F.5-1 | Configuration Parameter Download Rejection Variables | F-9 |
| Table F.5-2 | Configuration Parameter Download Rejection Variables – Related Collection Events.... | F-9 |
| Table F.6-1 | Configuration Change Notification - New Collection Events | F-10 |
| Table F.6-2 | Configuration Change Notification - New Data Variables | F-11 |
| Table F.7-1 | Recipe Change Notification – Related Report Variables | F-12 |

| | | |
|--------------|--|------|
| Table F.7-2 | Recipe Change Notification – Related Collection Events..... | F-12 |
| Table F.8-1 | Program Modification - Collection Events | F-13 |
| Table F.8-2 | Program Instruction Change Collection Events – Related Data Variables | F-14 |
| Table F.8-3 | Program Header Change - Collection Events | F-15 |
| Table F.8-4 | Heater Parameter Change - Collection Events | F-15 |
| Table F.8-5 | Heater File Parameter Change - Data Variables | F-17 |
| Table F.8-6 | Heater File - Data Variables | F-18 |
| Table F.8-7 | Fluid File Parameter Change – Collection Events | F-20 |
| Table F.8-8 | Fluid File Parameter Change – Data Variables..... | F-21 |
| Table F.8-9 | Fluid File - Data Variables | F-21 |
| Table F.9-1 | LMO Workpiece Origin - Collection Events..... | F-27 |
| Table F.9-2 | LMO Workpiece Origin – Data Variables | F-28 |
| Table F.10-1 | LMO Workpiece Align – Remote Command..... | F-29 |
| Table F.10-2 | LMO Workpiece Align – HCAK Rejection Codes | F-29 |
| Table F.11-1 | LMO Height Sense – Equipment Constants | F-30 |
| Table F.11-2 | LMO Height Sense - Collection Events | F-30 |
| Table F.12-1 | Dispense Head Linear Fluid Sensor Level Percent –Status Variables and Collection Events..... | F-31 |
| Table F.13-1 | Dispense Head Linear Fluid Sensor Level Percent – Status Variables and Collection Events..... | F-31 |
| Table F.14-1 | Limited Start Number of Runs – Equipment Constants | F-32 |
| Table F.15-1 | Remote Restart Application - Remote Commands..... | F-33 |
| Table F.16-1 | Calibrated Process Jetting (CPJ) - Remote Command | F-34 |
| Table F.16-2 | CPJ Check Remote Command – Related Variables, Equipment Constants and Collection Events..... | F-35 |
| Table F.16-3 | Calibrated Process Jetting - Check CPJ Results Status..... | F-35 |
| Table F.17-1 | Flow Rate Calibration – Remote Command – Collection Events..... | F-37 |
| Table F.17-2 | Flow Rate Calibration – Remote Command – Related Data Variables and Collection Events..... | F-38 |
| Table F.17-3 | Flow Rate Calibration Results Status..... | F-38 |
| Table F.18-1 | Dispense Weight Verification – Remote Command..... | F-42 |

| | | |
|--------------|--|------|
| Table F.18-2 | Dispense Weight Verification – Data Variables and Collection Events..... | F-43 |
| Table F.19-1 | DJ9K Vacuum Assisted Prime – Remote Command..... | F-46 |
| Table F.20-1 | Run PSS File – Remote Command | F-49 |
| Table F.20-2 | Run PSS File - Related Collection Events | F-50 |
| Table F.21-1 | Height Sense XY Offsets – Remote Command | F-52 |
| Table F.21-2 | Height Sense XY Offsets –Related Equipment Constants | F-52 |
| Table F.22-1 | Needle XY Offsets – Remote Command | F-55 |
| Table F.22-2 | Needle XY Offsets Variables..... | F-55 |
| Table F.23-1 | Needle Z Offsets – Remote Command..... | F-59 |
| Table F.23-2 | Needle Z Offsets – Equipment Constants..... | F-59 |
| Table F.24-1 | Locate Service Station – Remote Command..... | F-62 |
| Table F.24-2 | Locate Service Station - Equipment Constants and Collection Events..... | F-62 |
| Table F.25-1 | Prime – Remote Command | F-65 |
| Table F.25-2 | Prime Variables | F-65 |
| Table F.26-1 | Purge – Remote Command | F-68 |
| Table F.26-2 | Purge – Collection Events | F-68 |
| Table F.27-1 | Teach Scale – Remote Command..... | F-71 |
| Table F.27-2 | Teach Scale – Equipment Constants..... | F-71 |
| Table F.28-1 | PP-Select – Remote Command | F-75 |
| Table F.28-2 | PP-Select – Status Variables and Collection Events | F-75 |
| Table F.28-3 | PP-Select – Results | F-75 |
| Table F.29-1 | DJ Offset Calibration – Remote Command..... | F-77 |
| Table F.29-2 | DJ Offset Calibration – Equipment Constants | F-78 |
| Table F.30-1 | Move Home – Remote Command | F-82 |
| Table F.31-1 | Move to Center – Remote Command | F-84 |
| Table F.32-1 | Move to Front – Remote Command..... | F-86 |
| Table F.33-1 | Load Board – Remote Command | F-88 |
| Table F.34-1 | Vacuum On/Off – Remote Command..... | F-91 |
| Table F.35-1 | Preliminary Needle to Camera Offsets – Remote Command | F-95 |

| | | |
|--------------|--|-------|
| Table F.35-2 | Preliminary Needle to Camera Offsets – Equipment Constants | F-95 |
| Table F.36-1 | Control Dot Weight – Remote Command | F-98 |
| Table F.36-2 | Control Dot Weight – Collection Events | F-98 |
| Table F.38-1 | Abort - Remote Command | F-107 |
| Table F.39-1 | Local - Remote Command | F-108 |
| Table F.40-1 | Pause - Remote Command | F-109 |
| Table F.41-1 | Remote - Remote Command | F-110 |
| Table F.42-1 | Resume - Remote Command | F-111 |
| Table F.43-1 | Start - Remote Command | F-112 |
| Table F.44-1 | Stop - Remote Command | F-113 |
| Table F.45-1 | Auto Setup - Remote Command | F-114 |
| Table F.45-2 | Auto Setup – Collection Events | F-114 |
| Table F.46-1 | CPH Air Flow - Status Variables | F-115 |
| Table F.46-2 | CPH Air Flow - Related Configuration Variables | F-116 |
| Table F.46-3 | Heater/Air Flow States Status Variables | F-117 |
| Table F.47-1 | Multiple Flow Rates - Data Variables | F-120 |
| Table F.47-2 | Multiple Flow Rates - Collection Events | F-120 |
| Table F.48-1 | Carrier Sequence Number – Data Variables | F-124 |
| Table F.49-1 | Lane Number – Data Variables | F-125 |
| Table F.50-1 | Carrier Load/Unload Time Stamps – Data Variables | F-126 |
| Table F.51-1 | Lookup Camera Model Teach/Find – Collected Events | F-127 |
| Table F.51-2 | Lookup Camera Model Teach/Find – Related Data Variables | F-127 |
| Table F.52-1 | Dot Weight Pressure Setup – Rejection HCAACK | F-128 |
| Table F.52-2 | Dot Weight Pressure Setup – Data Variables | F-129 |
| Table F.52-3 | Dot Weight Pressure Setup – Related Collection Events | F-130 |
| Table F.52-4 | CPJ with Pressure Control – Data Variables | F-131 |
| Table F.52-5 | CPJ with Pressure Control – Related Collection Events | F-132 |
| Table F.53-1 | Setup Offset – Data Variables | F-133 |
| Table F.54-1 | Image Capture – Equipment Constants | F-134 |

| | | |
|--------------|--|-------|
| Table F.54-2 | Image Capture – Collection Events..... | F-134 |
| Table F.54-3 | Image Capture – Data Variables..... | F-135 |
| Table F.55-1 | Additional Offset Variables – Collection Events | F-136 |
| Table F.55-2 | Additional Offset Variables – Data Variables | F-136 |
| Table F.56-1 | Prompted Setup, Flowrate and Purge - Collection Events..... | F-137 |
| Table F.56-2 | Prompted Setup, Flowrate and Purge – New Data Variable..... | F-137 |
| Table F.57-1 | DJ Cycle Count - Equipment Constants..... | F-138 |
| Table F.58-1 | Low Fluid – Collection Events | F-138 |
| Table F.59-1 | Height Sense –Data Variables and Collection Events | F-138 |
| Table F.60-1 | Electronic Pressure –Data Variables and Collection Events..... | F-139 |
| Table F.61-1 | Scale Number – Data Variables..... | F-140 |
| Table F.62-1 | Program Fiducial ON/OFF Control – Equipment Constants | F-143 |
| Table F.63-1 | Scale Overflow – Equipment Constants..... | F-147 |
| Table F.63-2 | Scale Overflow – Collection Events | F-148 |
| Table F.64-1 | Electronic Pressure LMO - Equipment Constants | F-150 |
| Table F.64-2 | Electronic Pressure LMO – Status Variables | F-151 |
| Table F.64-3 | Electronic Pressure LMO – Collection Events | F-151 |
| Table F.64-4 | Electronic Pressure LMO – Data Variables..... | F-152 |
| Table F.65-1 | Operator ID – Status Variables | F-152 |
| Table F.66-1 | Additional Configuration Parameter Variables | F-153 |

1 Introduction

1.1 Overview

This manual describes the SECS/GEM interface used with Fluidmove for Windows XP (FmXP) version 5.3 and higher and Fluidmove for Windows NT (FmNT) version 4.93 and higher. The term “Fluidmove” as used in this manual refers to the applicable software (FmXP or FmNT) used on the Equipment.

This document is a modification of the GW Associates GES-1993 SECS/GEM Interface document and has been especially prepared to support Fluidmove. The content and structure of this document follows the original GES-1993 document. User information and GEM interface with Fluidmove were added. Fluidmove supports the GW Associates GEM subset of the SECS communication standard. Future references to the SECS/GEM interface will use only the GEM identification to acknowledge the specific approach used by Fluidmove.

The interface between Fluidmove and a Host computer is explained in detail. The interface conforms to the GEM standard. The GEM standard defines a standard implementation of the SECS-II communication interface for all semiconductor manufacturing equipment.

GW Associates (Software Model GEM-NT-100) is used to implement approximately 90% of SECS and GEM features, with Fluidmove implementing the remaining equipment-specific features.

1.2 Terminology

Abbreviations and terms used in this manual are defined in Table 1-1.

Table 1-1 Definition of Terms

| Term | Definition |
|-------------------------|---|
| Alarm | An alarm is related to any abnormal situation on the Equipment. GEM allows the Host to be notified when alarm conditions are detected and cleared. |
| ALID | Equipment Alarm ID. The identifier for a specific alarm condition. |
| CEID | Collection Event ID. The identifier for a specific collection event. |
| Collection Event | A collection event is a detectable occurrence significant to the Equipment that is considered to be significant to the Host. GEM allows the Host to be notified when a collection event occurs. This allows the Host to track the Equipment's activity. |
| Data Values | Also known as Discrete Data. Meant to be temporary or ephemeral statuses that disappear after an event is complete. Sometimes known as 'DVs' (Data Values), 'DVVALs' (Discrete Data Values). |
| Data Variable (DV) | Data variables may only be valid upon the occurrence of a particular collection event. The Host may gather data variable values from the GEM Equipment. |
| Equipment | An intelligent system which communicates with a Host and complies with the GEM standard. In this manual it refers to the dispensing system. |
| Equipment Constant (EC) | Equipment Constants are settable by the Host. The Host may gather Equipment constant values from the GEM Equipment. The Host may also set Equipment constant values on the GEM Equipment to control the Equipment's behavior. |

Table 1-1 Definition of Terms (continued)

| Term | Definition |
|---|---|
| Fluidmove | The Fluidmove® for Windows XP® (FmXP) or Fluidmove® for Windows NT® (FmNT) software application which controls GEM. |
| GCD | GWGEM Configuration Data (an ASCII file compiled for GWGEM). |
| GEM | Generic Equipment Model. The GEM (E30) standard defines the generic behavior of semiconductor Equipment as viewed through a communications link in terms of SECS-II messages communicated over that link. The GEM standard impacts Equipment control and Equipment-to-Host communications. |
| High-Speed SECS Message Services (HSMS) | <p>HSMS (E37) is a high-speed replacement and an alternative to SECS-I for applications where higher speed communication is needed or where simple point-to-point technology is insufficient.</p> <p>HSMS defines a communication interface via TCP/IP suitable for the exchange of (SECS-II) messages between computers in a semiconductor factory.</p> |
| Host | The computer which is connected to, and communicates with, the Equipment via the SECS interface. The GEM standard defines a set of messages the Host must use when interacting with the Equipment. The Equipment communicates with one Host, but the Host may communicate with multiple Equipment units. |
| HSMS-GS | High Speed Message Service-General Session. This standard defines TCP/IP network communication used by GEM for Host/Equipment communication. It is intended to be applied for complex systems containing multiple independently accessible subsystems and uses an extended state machine. |
| HSMS-SS | High Speed Message Service-Single Session. This standard defines TCP/IP network communication used by GEM for Host/Equipment communication. It replaces the SECS-I standard. |
| ID | Identifier or Identification. |
| Operator | The person who physically has access to the Equipment's material port(s) and control panel. This is the person who is operating the dispensing system. |
| PP | Process Program |
| Recipe | A file containing a set of instructions for the Equipment. |
| Report | A set of variables predefined by the Equipment or defined by the Host. The Host uses reports to gather status variable, data variable, and Equipment constant values. The Host may request a report explicitly or attach a set of reports to a collection event. |
| SECS | <p>SEMI Equipment Communications Standard.</p> <p>SECS I (E4): SEMI Equipment Communications Standard 1 Message Transfer. Defines RS-232 serial communication used by GEM for Host/Equipment communication.</p> <p>SECS II (E5): SEMI Equipment Communications Standard 2 Message Content. A standard for communications between intelligent Equipment and a Host. The standard defines the communication protocol interface (SECS-I) and the messages exchanged (SECS-II).</p> |
| Message | All GEM Equipment and Host communication is accomplished using SECS-II messages. Each unique SECS-II message is identified by its stream number (S) and function number (F). The SECS-II standard defines a large set of SECS-II messages determining each one's purpose, content, and usage. The GEM standard defines how to use a subset of these SECS-II messages yet allows other SECS-II messages to be used in addition to this subset. |

Table 1-1 Definition of Terms (continued)

| Term | Definition |
|----------------------|--|
| SEMI | Semiconductor Equipment and Materials International (SEMI) is a global trade association that represents the semiconductor and flat panel display equipment and materials industries. SEMI maintains and publishes standards that relate to Equipment automation and software. |
| Status Variable (SV) | Status Variable. Status variables may include any parameters that can be sampled in time such as temperature or quantity of a consumable. The Host may gather status variable values from the GEM Equipment. |
| UFPP | Unformatted Process Program |
| VID | Variable Identifier. A unique string representing the name of a variable. |

1.3 SECS/GEM – Fluidmove Compatibility

Compatibility between Fluidmove and SECS/GEM version is as follows:

- FmXP 5.3 requires SECS/GEM version 5.0.
- FmNT 4.9.3 requires SECS/GEM version 4.8.3.

1.4 SECS Standard

The SEMI Equipment Communication Standard (SECS) is published by Semiconductor Equipment and Materials International (SEMI). It defines a computer to computer communications interface between a unit of factory Equipment and a Host Computer.

This Equipment complies to the complete SECS-I standard (excluding the physical RS-232 hardware connection) and to the generic portions of the SECS-II standard. The Equipment implements an appropriate subset of the SECS-II standard messages and complies with the following versions of standards:

- E4-1991 (SECS-I)
- E5-1993 (SECS-II)



NOTES There were no changes to the SEMI E4 standard for 1993.

GWGEM Software is used to meet the SECS standard.

SECS default parameters will be used wherever possible; differences will be noted.

1.4.1 SECS-I Clarifications

The Equipment was designed to avoid using any of the unusual features of the SECS standard, so as to simplify the job of implementing Equipment support on the Host. This section clarifies the Equipment/Host SECS interface.

Fluidmove supports only Ethernet High Speed SECS Message Services (HSMS) in conjunction with communication drivers supplied by GW Associates.

Fluidmove does not support RS-232 interfaces.

1.4.2 Physical Connection

The GEM hardware interface must be a TCP/IP network card connection through a Ten-Base-T connector or BNC jack (SECS-II interface).



NOTE The following information is provided only as a reference for RS-232 connections (SECS-I interface) and is currently not implemented by Fluidmove:

- The RS-232 connector on the equipment deviates from the standard SECS-I DB25F connector.
- The Equipment provides a male 25-pin RS-232 “DB25M” connector on its back panel as the SECS port. Table 1-2 lists the pins used on the RS-232 connector.

Table 1-2 RS-232 Pins

| Pin No. | Description |
|---------|---|
| 1 | Shield. |
| 2 | TX Data (Equipment-to-Host). |
| 3 | RX Data (Host-to-Equipment). |
| 4 | Request to send (RTS). The Equipment raises this output signal when activating SECS. Not required by SECS standard, but you may find it useful for modem control. |
| 7 | Signal Ground. |
| 20 | Data Terminal Ready (DTR). The Equipment raises this output signal when activating SECS. This is not required by the SECS standard, but you may find it useful for modem control. |

Note: Optional SECS power pins 18 and 25 are not provided.

1.4.3 SECS-I Blocks Transmitted

The Equipment uses the following SECS-I conventions in the blocks it sends:

- The Device ID is present in every block, with the R-bit always set to “1”.
- The Block Number is always one (0x0001) for the first block of a message.
- For Primary messages, the System Bytes are generated unique for each message. For Secondary messages, the System Bytes are replicated from the received Primary message.
- SECS-I Blocks Received

Blocks received by the Equipment should be formatted as described above (except with the R-bit set to “0”), although the rules are more relaxed:

If a message consists of a single block, the Block Number may be zero (0x0000) or one (0x0001).

The Equipment is indifferent to the R-bit setting.

1.4.4 Interleaved Blocks

The Equipment never sends interleaved blocks to the Host. That is, the Equipment always sends all blocks of one message before sending the first block of the next message. This simplifies the job of the Host. However, the Equipment allows the Host to send interleaved blocks, if it so chooses.

1.4.5 Simultaneous Transactions

The Equipment may initiate several simultaneous outstanding SECS transactions. That is, the Equipment may send a secondary primary message before the Host has sent the Reply to a previous primary message. Mainly, this occurs when the Equipment reports Alarms and Events. The Host can reduce the number of outstanding transactions initiated by the Equipment by setting equipment constants appropriately so that the Equipment sends no W-Bit for Stream 5 (Alarm), Stream 6 (Event), and Stream 10 (Free Text) messages.

The Equipment allows the Host to initiate at least two (2) simultaneous outstanding transactions.

1.5 SECS-II Clarifications

The Equipment uses the following SECS-II conventions:

1.5.1 Data Format Types

Where the Standards permit a choice of data item types, the choice has been made as described in [*Section 4 - SECS Message Detail*](#).

For outgoing messages, the Equipment always sends Data Items of the exact format shown. For some incoming messages, the Equipment “forgives” minor Host errors. For example, the Equipment may accept a U1 Data Item where a U2 format was expected. We recommend the Host attempt to use the formats shown.

1.5.2 Data Item Length Bytes

For messages sent by the Equipment, the number of length bytes in Data Items is always the minimum required to contain the Data Item length.

For messages received from the Host, the number of length bytes in Data Items can be 1, 2, or 3, provided that the length parameter can accurately be specified.

1.5.3 ASCII Data

Unless otherwise specified, all ASCII data items must contain printable ASCII data—that is, characters in the range 0x20 to 0x7E.

1.5.4 Multi-Block Messages

Wherever the Host is supposed to send a single-block message, this Equipment will also accept multi-block format.

The maximum size for a single SECS message is approximately 1000 blocks (256,000 bytes).

1.5.5 Function Zero

The Equipment sends a Reply message using Function zero (F0) according to the requirements of the GEM Control State.

Wherever this Equipment expects a Reply message from the Host, the Host can send F0. The Equipment will instantly abort the outstanding transaction. The Equipment will not take any additional action.

1.6 GEM Standard

The SEMI Generic Equipment Model for Effective Factory Automation (GEM) is another document published by SEMI. The GEM standard defines some useful conventions for designing the communications interface on a unit of factory Equipment to improve operations with a Host Computer. The Equipment complies with SEMI E30-1993.

1.7 GEM Compliance

The following items and Table 1-3 clarify which GEM functions are implemented in this Equipment:

- The Equipment never sends S2F25 (Loopback Diagnostic) to the Host. It will send the appropriate S2F26 in response to an S2F25 from the Host.
- The Equipment never sends S9F13 (Conversation Timeout) to the Host. The Equipment can be defined as having an “infinite timeout” for conversations.
- The Equipment never sends S10F7 (Multi-Block Not Allowed) to the Host. It will accept incoming messages consisting of printable characters and a maximum size of 320 characters.
- The Equipment will accept, but does not require, the Inquire/Grant transaction (S2F39/S2F40, S6F5/S6F6, S7F1/S7F2) for incoming primary multi-block messages.
- GWGEM Software Model GEM-NT-100 is used by Fluidmove to meet the SECS standard.

Table 1-3 GEM Compliance Statement

| FUNDAMENTAL GEM REQUIREMENTS | IMPLEMENTED | COMPLIANT |
|--------------------------------------|---|---|
| State Models | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Equipment Processing States | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| S1F13/S1F14 Auto Connection Scenario | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Event Notification | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| On-line Identification | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Error Messages | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Control (Operator Initiated) | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Documentation | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| ADDITIONAL CAPABILITIES | IMPLEMENTED | COMPLIANT |
| Establish Communications | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Dynamic Event Report Configuration | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Variable Data Collection | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Trace Data Collection | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Status Data Collection | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Alarm Management | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Remote Control | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Equipment Constants | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Process Program Management | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Material Movement | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Equipment Terminal Services | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Clock | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Limits Monitoring | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Spooling | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |
| Control (Host Initiated) | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No | <input checked="" type="checkbox"/> Yes <input type="checkbox"/> No |

1.8 SEMI E10 Standard



NOTE Fluidmove does not upload the E10 states through the SECS/GEM interface.

SEMI E10 provides a guideline for the definition and measurement of Equipment reliability, availability, and maintainability (RAM). This document defines six basic Equipment States which define how Equipment time is categorized.

A status bar on the Equipment reflects the current E10 state. These Equipment states are as defined in SEMI E10-1992 (Section 3, 'Equipment States').

1.9 SECS I / SECS II Parameters

1.9.1 SECS-I Parameters

This section provides hardware settings that apply only to the RS-232 hardware interface.



NOTE Fluidmove currently does not support this interface.

Table 1-4 SECS Installation Parameters

| Parameter | Default | Description |
|-----------|----------|--|
| Device ID | 1 | Specified as a value from 0 to 32767 (15 bits). |
| Baud Rate | 9600 | Allowable speeds are 110, 150, 300, 600, 1200, 2400, 4800, 9600, and 19200 Baud. |
| T1 | 0.5 Sec | Inter-character Timeout. Range allowed is 0.1 to 10.0 seconds, at increments of 0.1 seconds. |
| T2 | 10.0 Sec | Protocol Timeout. Range allowed is 0.2 to 25.0 seconds, at increments of 0.1 seconds. |
| T3 | 45 Sec | Transaction Timeout. Range allowed is 1 to 120 seconds, at increments of 1 second. |
| T4 | 45 Sec | Inter-Block Timeout. Range allowed is 1 to 120 seconds, at increments of 1. |
| RTY | 3 | Transmit Failure Retry Limit. Range allowed is 0 to 31, at increments of 1. |
| DUPLIC | Off | Duplicate Block Detect. May be Enabled (On) or Disabled (Off). |

1.9.2 SECS-II Parameters

This section applies only to the Ethernet hardware interface defined in the SECS II standard.

There are no Operator adjustable parameters involved in configuring the SECS II interface.



The operating system of the Equipment computer must be made aware of the network connection or the SECS/GEM feature will not operate.

1.9.3 GEM Configuration

This Equipment is configurable for operation with most older Host computers which do not support the GEM message set, or support an older version of GEM.

1. Equipment constant “CONFIGALARMS” (VID 1) selects the message the Equipment will send for Alarm Reports. “ConfigAlarms” may be 0, 1, or 2, selection S5F1, S5F71, or S5F73, respectively.
2. Equipment constant “CONFIGCONNECT” (VID 2) selects the message the Equipment will send for Connect Request. “ConfigConnect” may be 0, 1, or 2, selecting S1F1, S1F65, or S1F13, respectively.
3. Equipment constant “CONFIGEVENTS” (VID 3) selects which message the Equipment will send for Event Reports. If “ConfigEvents” is 0, the Equipment will send S6F9 for normal (unannotated) Event Reports or S6F3 for annotated Event Reports. If “ConfigEvents” is 1, the Equipment will send S6F11 for normal Event Reports or S6F13 for annotated Event Reports.
4. Equipment constant “RPTYPE” (VID 17) selects whether the Equipment will send “normal” Event Reports (S6F9 or S6F11) or annotated Event Reports (S6F3 or S6F13).

RpType = “False”. Equipment will send “normal” Event Reports.

RpType = “True”. Equipment will send annotated Event Reports.

Table 1-5 GemRPTYPE

| | GemConfigEvents = 0 | GemConfigEvents = 1 |
|--------------------------|----------------------------|----------------------------|
| GemRPTYPE = FALSE | S6F9 | S6F11 |
| GemRPTYPE = TRUE | S6F3 | S6F13 |

5. For a non-GEM Host, build appropriate Report Definitions, Links, and Enables (S2F33, S2F35, S2F37) so that S6F9 or S6F3 Event Reports contain the desired data.
6. Equipment constant “WBITS5” (VID 19) selects whether Stream 5 primary message (S5F1, S5F71, and S5F73) sent by the Equipment will have the W-bit set to “0” or “1”.
7. Equipment constant “WBITS6” (VID 20) selects whether Stream 6 primary messages (S6F1, S6F3, S6F9, S6F11, and S6F13) sent by the Equipment will have the W-bit set to “0” or “1”.
8. Equipment constant “WBITS10” (VID 18) selects whether Stream 10 primary message S10F1 sent by the Equipment will have the W-bit set to “0” or “1”.
9. Equipment constant “CONFIGSPOOL” (VID 63) configures whether the Equipment will transition to “Spool Active” state when a RTY error occurs.

Table 1-6 shows the recommended settings for compatibility with various types of Hosts. Factory (Default) settings are shown in bold.

Table 1-6 Compatibility Settings

| Equipment Constant | E30-93 | GEM 3.1 | GEM 3.0 | GEM 2.0 | GEM 1.7 | Non-GEM |
|---------------------------|---------------|----------------|----------------|----------------|----------------|----------------|
| CONFIGALARMS | 0 | 2 | 2 | 2 | 1 | 0 |
| CONFIGCONNECT | 2 | 2 | 2 | 1 | 1 | 0 |
| CONFIGEVENTS | 1 | 1 | 1 | 1 | 1 | 0 |
| RPTYPE | False | False | False | False | False | False or True |
| WBITS5 | 1 | 1 or 0 | 1 or 0 | 1 or 0 | 1 or 0 | 1 or 0 |
| WBITS6 | 1 | 1 | 1 | 1 | 1 | 1 or 0 |
| WBITS10 | 1 | 1 or 0 | 1 or 0 | 1 or 0 | 1 or 0 | 0 |
| CONFIGSPOOL | 1 | 0 | 0 | 0 | 0 | 0 |

1.10 State Diagrams

This document uses several Finite State Machine diagrams to describe the current condition of the Equipment's SECS link, material handling mechanisms, and process cycle. Each Finite State Machine diagram includes a State Diagram and a complete description of the states and state transitions.

All Finite State Diagrams have been prepared in the format specified in the GEM standard. This notation is required as a fundamental part of GEM compliance and must be included in the Equipment SECS Interface Documentation. This notation is the "Statechart" notation developed by David Harel.

The following are the major characteristics of this notation as it is used in this document:

1. Each state is represented by a rectangle with rounded corners.
2. A collection of sub-states may be grouped into a super-state.
3. The entity described by the diagrams will be in one and only one of the sub-states at all times.
4. Variables representing the current state of an entity do not contain values for super-states, only the lowest sub-state is represented.
5. State transitions are represented by single-headed arrows.
6. Each state transition is a Collection Event, and it has a unique Collection Event ID (CEID).
7. An arrow directly from a super-state to another state describes a Collection Event that can occur while the entity is in any one of the sub-states contained in the super-state.

8. An arrow directly into a super-state to the H* (history) symbol describes a transition to the lowest sub-state which described the entity just before the transition out of the super-state.
9. An arrow directly into a super-state to the C (conditional) symbol describes a transition to a particular sub-state based on some other relevant data. The conditional data is not represented in the diagram but is described in the associated text.

1.11 Machine Operation and the GEM Interface

1.11.1 Connecting to the Host

Fluidmove loads the GEM communications driver immediately upon startup. Once connection to the driver is established, the device enters its default communication state as set by the Operator. This default state can be set via the SECS/GEM Setup dialog box in Fluidmove. The recommended selection is “Enabled”. If enabled, the Communications State Machine in the GEM driver sends the Establish Communications Request message (S1F13) every ESTABLISHCOMMUNICATIONSTIMER seconds until a reply is received from the Host. The Communication State changes to reflect this response.

Unlike other state machines, transitions in this state machine do not produce events or message reports to the Host.

In the Main Window of Fluidmove, the GEM Status control can be seen in the lower part of the screen in a status bar display format. The COMM section displays the GEM communication state of the program. The CTRL section displays the control state of the program. The SPOOL section displays the spooling state of the program. General GEM controls are available to the user by clicking on the SECS/GEM button from the main window.

The initial (default) control state is set through Fluidmove’s SECS/GEM Setup dialog box. “ONLINE/REMOTE” is recommended for this setting. This way, the Host has control of the machine once the application has started and communication has been established. Refer to [1.11.7 SECS/GEM Setup Dialog Box in Fluidmove](#) for further details.

Normally, communications are established without fault, and going to the GEM setup dialog would only be used by the Operator to manually go off line for maintenance reasons.

1.11.2 Device Identification

The Host periodically sends the Are You There message (S1F1) to the Equipment. If the communication link is operational the Equipment automatically responds with the acknowledgment message (S1F2) which contains Fluidmove model type (MDLN) and software revision number (SOFTREV). The Host may receive more detailed information by requesting the MachineID variable from the Equipment.

1.11.3 Clock

The Host updates the GEM TIME structure periodically using the Date and Time Send message (S2F31). Fluidmove will update its system clock to reflect the data presented by the Host. Current values of the system time are used extensively in event logging and will be required to synchronize with comparable events logged by the Host.

1.11.4 Loss of Communications Link: Spooling

Communications may be temporarily lost with the Host from time to time. GEM message responses and requests are automatically spooled to disk when this happens. When communications are restored the messages on the SPOOL file are automatically sent to the Host.

Spooling is enabled for Fluidmove. The Host may query the SPOOLSTSATE and CONTROLSTATE variables with the Selected Equipment Status Request message (S1F3) in order to establish the success of REMOTE operations. In addition, the Host will receive spooling update messages from Fluidmove.

The default spool state can be set through the Fluidmove SECS/GEM Setup dialog box.

1.11.5 Communications Error Messages

Occasionally messages are garbled between Fluidmove and the Host. Garbled message device IDs and streams result in Fluidmove replying to the Host with S9F1 and S9F3 messages. Further distortion of the message results in the device ignoring the message which causes the Host to resend the message. See [4.2.92 S9F1 – Unrecognized Device ID](#) and [4.2.93 S9F3 – Unrecognized Stream](#) for details of the message exchange.

1.11.6 Normal Communications

1.11.6.1 Alarm Notification

Alarms are reports of errors (caused by the program or the operator) or events which may result in production or Equipment damage or events which may cause a safety hazard to workers. When an alarm state occurs, Fluidmove initiates an alarm notification (message S5F1) to the Host. The Process State transfers into the Alarm-Paused state and the Equipment stops dispensing and retracts the dispenser apparatus from the board.

The Operator will need to correct the alarm condition and guide the machine through the Paused state to the Idle State.

The Host may poll the Equipment to receive lists of enabled or existing alarms. When the Host sends a List Alarm Data message (S5F6) the Equipment replies with a list of the current active alarms. The Host may receive a list of the currently enabled alarms with the List Enabled Alarms Request (S5F7).

1.11.6.2 Remote Control Operations

Both the Host and the Operator are allowed to request runtime control of Fluidmove from each other. When the control state is Local, only the Operator has the ability to command Fluidmove, and Host run commands are rejected. Conversely, when the Host has control of Fluidmove, the Operator is limited to requesting Fluidmove status displays and Help screens. The Operator can stop, abort, or pause the process from the Run Window. Host will receive an event if the Operator presses any of the buttons from the Run Window. Refer to [Appendix B](#) for the list of these events.

Both the Host and the Operator may request that control be turned over to the requester. Each change in the control state machine generates a notification event to the Host.

Remote run commands are described in Table 1-7.

Table 1-7 Remote Run Commands

| Command | Description |
|---------|---|
| START | This command is successful when the Control State is OnLine - REMOTE , the board is in the Dispensing position, the machine is configured for a run, and the process program has been selected. This event begins the continuous processing of substrate trays. Processing can be interrupted by STOP, PAUSE, and ABORT commands. The Operator can also initiate PAUSE and STOP commands from the Run Window. |
| STOP | This command is successful when the Control State is OnLine - REMOTE, and the Process State is Running. It causes a halt in dispensing following completion of the current substrate cycle. The Process State changes to IDLE when this command is delivered and the process program is terminated. Further processing of the substrate tray is not possible after completing this command. |
| PAUSE | This command is successful when the Control State is OnLine - REMOTE and the Process State is Running. It causes a halt in dispensing following completion of the current instruction. The board and the process program are retained without change. The Process State changes to PAUSED. Diagnostics and status checks may be performed at this time. The substrate processing may be continued in the Running State by delivering the RESUME command. |
| RESUME | This command is successful when the Control State is OnLine - REMOTE, and the Process State is PAUSED. Processing of the substrate tray continues exactly from the PAUSED point and the current process program executes from the beginning of the next unprocessed instruction. |
| LOCAL | This command is successful if the current Control State is OnLine -REMOTE, otherwise it is ignored. The Host may request local operation for an Operator to perform maintenance or inspection of the machine. The Host may request a return to operation under its command by delivering the REMOTE command. |
| REMOTE | This command is successful if the current Control State is OnLine - LOCAL, the Process State is IDLE and the configuration allows remote operation. Return to the REMOTE state following an ALARM or ABORT command without proper Operator inspection and delivery of a Proceed event may return the machine to the same error state which initially caused the machine to leave the REMOTE state. |
| ABORT | This command is successful if the current Control State is OnLine - REMOTE, the Process State is Running, and the configuration allows remote operation. This command indicates an error status which prevents further dispensing operation until the error is corrected. Dispensing is immediately stopped and the current process program is terminated. Operator intervention and maintenance is generally required in order to resume operation past this point |

1.11.6.3 Material Movement

Fluidmove declares two material movement events. The event notifications to the Host are: Dispensing and DispensingDone.

Movement of the board into the ready position for dispensing invokes the Dispensing event. Transfer of the board out of the ready position after dispensing invokes the DispensingDone event.

1.11.6.4 Terminal Message Notification

After a terminal message has been received from the Host, the GEM status bar at the bottom of the Fluidmove Run Window will start blinking. See Figure 1-1. GEM status bar displays the current communication, control, and spooling state. If the user has selected the beeping option (through the SECS/GEM Setup dialog box) a half-second interval beep is also provided to catch the user's attention.

During run-time, the GEM status bar is displayed. The Run Window's SECS/GEM tab is responsible for displaying the incoming terminal message. See Figure 1-7 for all screen features.





Figure 1-1 Terminal Message Notification (FmXP shown)


1.11.7 SECS/GEM Setup Dialog Box in Fluidmove

The SECS/GEM Setup dialog box can be accessed by pressing the SECS/GEM button in the Fluidmove Main Window. The dialog box contains tabs with buttons and drop-down menus for control and setup of GEM features. These tabs are described in Figure 1-2 through Figure 1-7.




| Item | Name | Description |
|------|-----------------|---|
| 1 | Control | <p><u>On-Line Local:</u> The Operator has control of the system. The system will reject most Host commands. The Host can monitor operations, but cannot control processing. In this state, the system will not accept a REMOTE command from the Host.</p> <p><u>On-Line Remote:</u> The Host has control of the system. The Operator may issue a Pause, Stop, or Abort command.</p> <p><u>Off-Line:</u> Puts the system Off-Line.</p> |
| 2 | Get Date & Time | Requests current date and time from the Host. |
| 3 | Status Box | Displays the current communication state, control state, and spooling state. |
| 4 | Spooling | <p><u>Disable:</u> Neither messages nor commands will be spooled and re-sent if the communications link between the Host and the dispensing system is temporarily disrupted.</p> <p><u>Enable:</u> Messages and commands will be spooled and re-sent if the communications link between the Host and the dispensing system is temporarily disrupted.</p> |
| 5 | Communication | <p><u>Disable:</u> The SECS/GEM link with the Host is disconnected.</p> <p><u>Enable:</u> The SECS/GEM link with the Host is established and communication can take place.</p> |

Figure 1-2 SECS/GEM Setup Dialog Box – Control Tab (FmXP shown)




| Item | Name | Description |
|------|------------------|--|
| 1 | Incoming Message | Messages from the Host are displayed in this box. |
| 2 | Acknowledge | Press to acknowledge receipt of the incoming message from the Host. |
| 3 | Outgoing Message | Enter messages to the Host in this box. |
| 4 | Send | Press to send the message in the Outgoing Message box. |
| 5 | Status Box | Displays the current communication state, control state, and spooling state. |

Figure 1-3 SECS/GEM Setup Dialog Box – Terminal Tab (FmXP shown)



| Item | Name | Description |
|------|--|--|
| 1 | Establish Communication Timeout | The user-configurable equipment constant that defines the delay, in seconds, between attempts to send S1F13. This value is used to initialize the CommDelay timer. |
| 2 | Default Communication State | Allows the user define the default communication state upon Fluidmove's startup. The valid choices are: <u>ENABLED</u> : Fluidmove will attempt to establish communication link upon startup. <u>DISABLED</u> : Fluidmove will not attempt to establish communication link upon startup. Recommended: ENABLED |
| 3 | Default Control State | Allows the user define the default control state upon Fluidmove's startup. The valid choices are: OFFLINE/ATTEMPT ONLINE, OFFLINE/EQUIPMENT OFFLINE, OFFLINE/HOST OFFLINE, ONLINE/LOCAL, ONLINE/REMOTE Refer to 5.4 Control State for descriptions. Recommended: ONLINE/REMOTE |
| 4 | If On-line Attempt Fails Go To | Allows the user to select what to do if attempting to go on-line fails for any reason. The valid choices are: OFFLINE/HOST OFFLINE, OFFLINE/EQUIPMENT OFFLINE Refer to 5.4 Control State for descriptions. Recommended: OFFLINE/HOST OFFLINE |
| 5 | Beep Until Incoming Message Acknowledged | If selected, Fluidmove will beep twice a second to notify the user of arrival an incoming terminal message from the Host. The GEM status bar blinks at the same rate to catch user's attention regardless of this option being selected or not. The user should then go to the Terminal tab to view and acknowledge the message. |
| 6 | Status Box | Displays the current communication state, control state, and spooling state. |

Figure 1-4 SECS/GEM Setup Dialog Box – Setup Tab (FmXP shown)



| Item | Name | Description |
|------|------------|--|
| 1 | Device ID | Displays the unique identifier for the Equipment. |
| 2 | Status Box | Displays the current communication state, control state, and spooling state. |

Figure 1-5 SECS/GEM Setup Dialog Box – Communication Tab (FmXP shown)





Figure 1-6 SECS/GEM Setup Dialog Box – Version Tab (FmXP shown)

1.11.8 Fluidmove Run Window Interface

The Fluidmove Run Window includes a SECS/GEM tab that shows communication status and allows messages to be sent between the Host and the Operator. This tab is described in Figure 1-7.



| Item | Name | Description |
|------|----------------------------------|--|
| 1 | Incoming Message | Messages from the Host are displayed in this box. |
| 2 | Acknowledge | Click to acknowledge receipt of the incoming message from the Host. |
| 3 | Outgoing Message | Enter messages to the Host in this box. |
| 4 | Send | Click to send the message in the Outgoing Message box to the Host. |
| 5 | Status Box | Displays the current communication state, control state, and spooling state. |
| 6 | GEM Status Bar | <u>COMM</u> : Displays the GEM communication state of the program. <u>CTRL</u> : Displays the control state of the program. <u>SPOOL</u> : Displays the spooling state of the program. |
| 7 | SECS/GEM Communication Indicator | A green button is present when the communication link is established. Otherwise, the button is not displayed. |

Figure 1-7 Run Window – SECS/GEM Tab (FmXP shown)

2 Message Summary

2.1 Overview

This section covers the primary SECS messages sent and received between the Host and the Equipment.

2.2 Host-to-Equipment Messages

Table 2-1 describes primary SECS messages sent by the Host, and the associated reply messages from the Equipment.

The **CState** column indicates the control state the Equipment must be in to accept the message. The current value of the Equipment Control State can be found in variable CONTROLSTATE (VID 28). Possible control state values for this column are listed in [Table 2-2](#).

Unlawful messages sent to the Equipment while Control State is Off-Line (1, 2, or 3) will be replied to with a SnF0 message. Thus, the Host will see only values of 4 or 5 for CONTROLSTATE.

Refer to [Table 7-1](#) for further message detail.

In the **Notes** column, those messages marked with “E” are extensions beyond GEM. Those messages marked with “N” are provided for non-GEM or older GEM compatibility.

Table 2-1 SECS Messages – Host-to-Equipment

| Primary | Reply | CState | Description | Notes |
|---------|-------|--------|-------------------------------------|-------|
| S1F1 | S1F2 | 4,5 | Are You There | |
| S1F3 | S1F4 | 4,5 | Selected Status | |
| S1F11 | S1F12 | 4,5 | Status Variable Namelist Request | |
| S1F13 | S1F14 | All | Connect Request | |
| S1F15 | S1F16 | 4,5 | Request Off-Line | |
| S1F17 | S1F18 | 1,2,3 | Request On-Line | |
| S1F65 | S1F66 | All | Connect Request | N |
| S2F13 | S2F14 | 4,5 | Equipment Constant Request | |
| S2F15 | S2F16 | 4,5 | New Equipment Constant Send | |
| S2F17 | S2F18 | 4,5 | Date and Time Request | |
| S2F21 | S2F22 | 5 | Remote Command | N |
| S2F23 | S2F24 | 4,5 | Trace Initialize | |
| S2F25 | S2F26 | 4,5 | Loopback Diagnostic | E |
| S2F27 | S2F28 | 5 | Initiate Processing Request | N |
| S2F29 | S2F30 | 4,5 | Equipment Constant Namelist Request | E |
| S2F31 | S2F32 | 4,5 | Date and Time Send | |
| S2F33 | S2F34 | 4,5 | Define Report | |

Table 2-1 SECS Messages – Host-to-Equipment (continued)

| Primary | Reply | CState | Description | Notes |
|---------|--------|--------|--------------------------------------|-------|
| S2F35 | S2F36 | 4,5 | Link Event Report | |
| S2F37 | S2F38 | 4,5 | Enable/Disable Event Report | |
| S2F39 | S2F40 | 4,5 | Multi-Block Inquire/Grant | |
| S2F41 | S2F42 | 5 | Remote Command with Parameters | |
| S2F43 | S2F44 | 4,5 | Reset Spooling Streams and Functions | |
| S2F45 | S2F46 | 4,5 | Define Variable Limits Attributes | |
| S2F47 | S2F48 | 4,5 | Variable Limit Attribute Request | |
| S5F3 | S5F4 | 4,5 | Enable/Disable Alarm | |
| S5F5 | S5F6 | 4,5 | List Alarms | |
| S5F7 | S5F8 | 4,5 | List Enabled Alarms | E |
| S6F15 | S6F16 | 4,5 | Request Event Report | |
| S6F17 | S6F18 | 4,5 | Request Annotated Event Report | E |
| S6F19 | S6F20 | 4,5 | Request Report | |
| S6F21 | S6F22 | 4,5 | Request Annotated Report | E |
| S6F23 | S6F24 | 4,5 | Request Spooled Data | |
| S7F1 | S7F2 | 4,5 | Process Program Inquire/Grant | |
| S7F3 | S7F4 | 4,5 | Unformatted Process Program Send | |
| S7F5 | S7F6 | 4,5 | Unformatted Process Program Request | |
| S7F17 | S7F18 | 4,5 | Process Program Delete | |
| S7F19 | S7F20 | 4,5 | Process Program Directory | |
| S10F3 | S10F4 | 4,5 | Terminal Display, Single | |
| S10F5 | S10F6 | 4,5 | Terminal Display, Multiple | |
| S10F9 | S10F10 | 4,5 | Broadcast | E |

Table 2-2 Control State Values

| Value | State |
|-------|-----------------------------|
| 1 | Off-Line/Equipment Off-Line |
| 2 | Off-Line/Attempt On-Line |
| 3 | Off-Line/Host Off-Line |
| 4 | On-Line/Local |
| 5 | On-Line/Remote |

2.3 Equipment-to-Host Messages

Table 2-3 describes primary SECS messages sent by the Equipment, and the associated reply messages from the Host.

Refer to [Table 8-1](#) for further details.

In the **Notes** column, those messages marked with “N” are provided for non-GEM or older GEM compatibility.

Table 2-3 SECS Messages – Equipment-to-Host

| Primary | Reply | Description | Notes |
|----------|-------|-------------------------------------|-------|
| -- (any) | SnF0 | Primary rejected while Off-Line | |
| S1F1 | S1F2 | Are You There | |
| S1F13 | S1F14 | Connect Request | |
| S1F65 | S1F66 | Connect Request | N |
| S2F17 | S2F18 | Date and Time Request | |
| S5F1 | S5F2 | Alarm Report | N |
| S5F71 | S5F72 | Alarm Report Block Send | |
| S5F73 | S7F74 | Alarm Notification Send | |
| S6F1 | S6F2 | Trace Data Send | |
| S6F3 | S6F4 | Annotated Event Report Send | N |
| S6F5 | S6F6 | Multi-Block Data Send Inquire/Grant | |
| S6F9 | S6F10 | Event Report Send | N |
| S6F11 | S6F12 | Event Report Send | |
| S6F13 | S6F14 | Annotated Event Report Send | N |
| S7F1 | S7F2 | Process Program Inquire/Grant | |
| S7F3 | S7F4 | Unformatted Process Program Send | |
| S7F5 | S7F6 | Unformatted Process Program Request | |
| S9F1 | -- | Error, Device ID | |
| S9F3 | -- | Error, Stream | |
| S9F5 | -- | Error, Function | |
| S9F7 | -- | Error, Data | |
| S9F9 | -- | Error, Transaction Timeout | |
| S9F11 | -- | Error, Data Too Long | |
| S10F1 | S10F2 | Terminal Request | |

3 Operating Characteristics

3.1 Overview

This section describes the operating characteristics of the Equipment.


3.2 Communications States

The Equipment represents the current state of its SECS link using a Communication Finite State Machine diagram. The purpose is to make clear how this link is initiated and terminated. The Communications State is displayed in the GEM status bar and the SECS/GEM tab of the Fluidmove Run Window.

Initially, the INITCOMMSTATE variable is set to place the Equipment into the Disabled state at power-up. Once Fluidmove has completed initialization, Fluidmove will change the Communications State to the default communication state selected by the user. The loss of communications during Running or Pausing will not affect the ability of Fluidmove to complete operations in the Process Program. However, automatic reestablishment of the Process State may require manual intervention if Fluidmove has changed state during the loss of communications period.

3.2.1 Communications Finite State Description

Figure 3-1 illustrates the Communications Finite State Machine that the Equipment maintains.

 **NOTE** Refer to Table 3-1 for definition of numbers used in Figure 3-1.




Figure 3-1 Communication Finite State Diagram

3.2.1.1 State Transitions

The following table describes the transitions that can occur. Transitions shown in Figure 3-1 do not cause the Equipment to signal any Collection Event ID (CEID) or to send Event Reports to the Host.

**NOTE**

The numbers in the # column refers to those in Figure 3-1.

Table 3-1 State Transitions

| # | From | Trigger | To | Description |
|---|----------------------|---|-------------------|--|
| 1 | Unknown | Power-Up | Conditional | Equipment will initialize itself to either the Disabled or Enabled state, depending on the configuration of the EC INITCOMMSTATE (VID 7). |
| 2 | Disabled | Operator enables SECS link. | Enabled | Equipment will attempt to establish communications with the Host. The Equipment will periodically send a Connect Request at an interval dictated by the EC ESTABLISHCOMMUNICATIONS-TIMER (VID 44). |
| 3 | Enabled | Operator disables the SECS link. | Disabled | Communications are abruptly terminated. Any outstanding messages queued for send are discarded. The Equipment will not respond to a Host-initiated ENQ. |
| 4 | Disabled or Power-Up | Request has been made for the Equipment to start communicating. | Not Communicating | Equipment immediately attempts to establish communications with the Host. The Equipment will periodically send a Connect Request message at an interval dictated by the EC ESTABLISHCOMMUNICATIONS-TIMER (VID 44). |
| 5 | Not Communicating | Successful completion of Connect Request transaction. | Communicating | The Host / Equipment link is "up". Normal SECS transactions can occur. |
| 6 | Communicating | A Communications failure has occurred. | Not Communicating | Equipment immediately attempts to establish communications with the Host. The Equipment will periodically send a Connect Request message at an interval dictated by the EC ESTABLISHCOMMUNICATIONS-TIMER (VID 44). |

3.2.1.2 Communications States

The current communication state will be one of the values specified in Table 3-2. There is no variable indicating the communication state. The communication state is presented to the Operator on the main Operator interface screen.

Table 3-2 Communication State Values

| Value | Description |
|---------------------------|---|
| DISABLED | The SECS link to the Host is disabled at the Equipment. The Equipment will send no messages to the Host. The Equipment will not respond to a Host-initiated ENQ. |
| ENABLED | When communications are Enabled, the Equipment's intention is to be in communication with the Host. Whether or not the Equipment is currently communicating with the Host determines which sub-state of the Enabled super-state the Equipment is in. |
| ENABLED/COMMUNICATING | <p>The SECS link between the Equipment and the Host is operating normally.</p> <p>Periodically, the Equipment will send a "Heartbeat" message S1F1 to ensure that the link is still operating. The heartbeat frequency is controlled by equipment constant "HEARTBEAT". "HEARTBEAT" (VID 26) can range from 0 to 32000, with default value 30.</p> <p>If the Equipment encounters a SECS-I Retry Limit (RTY) error when attempting to send a block to the Host, it discards any messages queued for send and the communication state transits to ENABLED.</p> |
| ENABLED/NOT COMMUNICATING | <p>The SECS link to the Host is enabled at the Equipment, and the Equipment is attempting to determine if the link is active. The Equipment periodically sends S1F13 (Establish Communications Request). If the connect is not successful for any reason, the Equipment will try again periodically forever. The time between attempts is controlled by the equipment constant "ESTABLISHCOMMUNICATIONSTIMER". This variable (VID 44) can range from 0 to 32000 seconds, with default of 60 seconds.</p> <p>Once the Host has responded with S1F14 (Establish Communications Acknowledge), the Communication State will change to COMMUNICATING.</p> <p>The Host can also attempt to establish communications by sending S1F13. The Equipment will accept the message and respond with S1F14 and the Communication State will change to COMMUNICATING.</p> <p>In ENABLED state, the Equipment will accept messages from the Host, but will ignore any messages except S1F13 and S1F14. The Equipment will respond to the S1F13 while the Communication State is ENABLED or COMMUNICATING, but it will not send S1F13 once communications have been established.</p> |

3.2.2 Power Up

At Power Up (or System Start), the equipment constant “INITCOMMSTATE” (VID 7) controls whether the state is initialized to DISABLED or ENABLED. The factory setting is DISABLED.

3.2.3 Related Variables

Table 3-3 lists the variables (SVs, ECs, or DVs) which are relevant to establishing communications. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-3 Related Variables

| Variable Name | VID |
|------------------------------|-----|
| CONFIGCONNECT | 2 |
| INITCOMMSTATE | 8 |
| ESTABLISHCOMMUNICATIONSTIMER | 6 |
| HEARTBEAT | 10 |
| CONFIGSPOOL | 63 |

3.2.4 Compatibility

If the Host intends to use the Control State Off-Line feature, CONFIGCONNECT should always be set to S1F13/14.

3.3 Control States

This section describes the Control characteristics of the Equipment. The Equipment may be in one of the control states in the following table. This value is reflected in status variable CONTROLSTATE (VID 28).

Table 3-4 Control States

| Value | State |
|-------|-----------------------------|
| 1 | Off-Line/Equipment Off-Line |
| 2 | Off-Line/Attempt On-Line |
| 3 | Off-Line/Host Off-Line |
| 4 | On-Line/Local |
| 5 | On-Line/Remote |

GWGEM software maintains the GEM Control State finite state machine.


Fluidmove provides the following:

- GUI display of the current State.
- Provide Operator commands for Go Local and Go Remote.
- When ControlState is LOCAL, reject remote commands are appropriately rejected.
- When ControlState is REMOTE, reject local commands are appropriately rejected.

The current Control State is displayed in the GEM status bar in lower portion of all windows. In Remote State configuration, teaching, and tools features are not available to the Operator. This prevents the Operator from interfering with remote operations.

3.3.1 Control Finite State Description

Figure 3-2 and Table 3-5 describe the Equipment Control State. The Equipment behaves differently and will accept different messages depending on its current control state. The purpose of this diagram is to make clear to the Host exactly what is happening at the Equipment. The logic for these states and transitions is the logic specified in the GEM standard.

 **NOTE** Refer to Table 3-5 for definition of numbers used in Figure 3-2.




Figure 3-2 Equipment Control State Diagram

3.3.1.1 Control State Transitions

Certain state transitions will cause a collection event to be signaled. If the event is enabled, this event will be sent to the Host along with the appropriate reports if appropriate. Table 3-5 lists the state transitions and notes when events will be sent to the Host.


 **NOTE** The numbers in the # column refer to those in Figure 3-2.

Table 3-5 Control State Transitions

| # | From | Trigger | To | Description |
|----|--------------------|---|-------------------------------|--|
| 1 | Unknown | Power-Up | Conditional | This transition is made to either the Off-Line or On-Line state, depending on the EC INITCONTROLSTATE (VID 9). |
| 2 | Unknown | Power-Up | Conditional | This conditional transition is governed by the value of the OFFLINESUBSTATE EC (VID 42). |
| 3 | Equipment Off-Line | Operator requests to go On-Line. | Attempt On-Line | The Equipment will immediately send an S1F1 to request to go On-Line. |
| 4 | Attempt On-Line | Unsuccessful On-Line request | Conditional | This transition occurred because the Host did not reply to an S1F1 with an S1F2 or because the S1F1 was not successfully sent. |
| 5 | Conditional | ONLINEFAILED Equipment Constant configured to Equipment Off-Line. | Equipment Off-Line | Equipment will allow the Operator to attempt to go On-Line again. |
| 6 | Conditional | ONLINEFAILED Equipment Constant configured to Host Off-Line. | Host Off-Line | The Equipment will accept a Host initiated request to go On-Line by replying to the S1F17 with ONLACK = 0x00. |
| 7 | Host Off-Line | Operator requests to go Off-Line. | Equipment Off-Line | A Host request to go On-Line will not be accepted. |
| 8 | Attempt On-Line | Successful On-Line request. | On-Line | The Equipment is now On-Line. |
| 9 | On-Line | Host puts the Equipment Off-Line by sending S1F15 and receiving the S1F16 with OFLACK = 0x00. | Host Off-Line | EVENT: GemEquipmentOFFLINE (CEID 22). The Equipment will accept a Host initiated request to go On-Line by replying to the S1F17 with ONLACK = 0x00. |
| 10 | Host Off-Line | Successful completion of S1F17 / S1F18 transaction, with ONLACK = 0x00. | On-Line | The Equipment is now On-Line. |
| 11 | Unknown | Entry into On-Line super-state. | Conditional (Local or Remote) | EVENT: GemControlStateLOCAL (CEID 8) or GemControlStateREMOTE (CEID 9). The Equipment will transition to whichever state is specified in the EC ONLINE- SUBSTATE (VID 44). |
| 12 | Local | Operator or Host requests to go Remote. | Remote | EVENT: GemControlStateREMOTE (CEID 9). All documented messages will be accepted in this state, including remote commands. |
| 13 | Remote | Operator or Host requests to go Local. | Local | EVENT: GemControlStateLOCAL (CEID 8). Remote commands will be rejected. Except for the REMOTE command. |
| 14 | On-Line | Operator requests to go Off-Line. | Equipment Off-Line. | EVENT: GemEquipmentOFFLINE (CEID 3). A Host request to go On-Line will not be accepted. |

3.3.1.2 Control States

The variable CONTROLSTATE (VID 28) represents the current control state, and will be one of the values listed in Table 3-6.

Table 3-6 Control State Values

| Value | Description |
|-----------------------------|--|
| Off-Line/EQUIPMENT OFF-LINE | The Operator has put the Equipment off-line. In this state, only the Operator can put the Equipment on-line. Any Host-initiated primary message (except S1F13 and S1F17) will be replied to with an SnF0 ABORT message by the Equipment. The Equipment will not send any primary messages except for S1F13 when necessary to establish communications, and the S9F1 and S9F9 messages for SECS errors. |
| Off-Line/HOST OFF-LINE | <p>While in this state, the Equipment will accept either the S1F17 (Go Online), or the S1F13 (Connect Request) message. When in this state, the Operator has allowed the Host to put the Equipment on-line, but the Host has not yet done so, or the Host has just put the Equipment off-line by sending S1F15. The Host may request for the Equipment to come on-line by sending the S1F17 (Go Online) message. The Operator cannot put the Equipment on-line from this state.</p> <p>The S1F13/S1F14 messages are used to maintain the Communications Finite State Machine. All messages (except S1F13 and S1F17) received will be replied to with the SnF0 ABORT message. The Equipment will not send any primary messages except for S1F13 when necessary to establish communications, and the S9F1 and S9F9 messages for SECS errors.</p> |
| Off-Line/ATTEMPT ON-LINE | The Operator has requested that the Equipment go On-Line, causing the transition to this state. The Equipment sends a single S1F1, indicating its desire to go on-line. When either a transmission failure (T3 or RTY errors) occurs or a successful reply to the S1F1 has been received, a transmission is made out of this state. |
| On-Line/LOCAL | <p>The local Operator has control of the Equipment. The Host can send S2F41 (Remote Command), but the Equipment will reject it with 0x40 return code. The REMOTE command sent by the Host will not be rejected by the Equipment. See 3.8 Remote Commands or 4.2.41 S2F42 - Remote Command Acknowledge for details.</p> <p>In LOCAL mode, the Equipment continues to send event and alarm reports to the Host. The Host can monitor operations, but cannot control processing. However, the Host can still exert “controls” other than S2F41 which do not directly affect processing. For example, the Host can enable/disable alarms and set the clock.</p> |
| On-Line/REMOTE | <p>The remote Host Computer has control of the Equipment using S2F41 (Remote Command). For details refer to 3.8 Remote Commands.</p> <p>The Operator may issue the PAUSE, STOP, and ABORT commands while in Remote state. These commands will generate an OperatorCommand event (CEID 4) as well as other messages attached to these activities. Refer to Appendix B for further detail.</p> |

3.3.2 Power Up

At power-up, the equipment constant “INITCONTROLSTATE” (VID 9) controls whether ControlState is initialized to ONLINE or OFFLINE. Within the Off-Line super-state, the equipment constant “OFFLINESUBSTATE” (VID 42) controls whether the Control State defaults to:

1. Equipment Off-Line
2. Host Off-Line
3. Attempt On-Line

If INITCONTROLSTATE (VID 9) initializes to On-Line, the variable ONLINESUBSTATE (VID 44) determines whether the default state is:

1. Local
2. Remote

When the Operator changes the default control state through Fluidmove’s SECS/GEM Setup dialog box, INITCONTROLSTATE gets updated. ONLINE/REMOTE is recommended for this value.

3.3.3 Related Variables

Table 3-7 lists the variables (SVs, ECs, or DVs) which are relevant to the Control State. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-7 Control State Variables

| Variable Name | VID |
|----------------------|-----|
| INITCONTROLSTATE | 9 |
| OFFLINESUBSTATE | 42 |
| ONLINEFAILED | 43 |
| ONLINESUBSTATE | 44 |
| CONTROLSTATE | 28 |
| PREVIOUSCONTROLSTATE | 35 |

3.3.4 Related Events

Table 3-8 lists the collection events (CEIDs) which are relevant to the Control State. For a more complete description of these events, refer to [Appendix B](#) or the description in this chapter.

Table 3-8 Control State CEIDS

| Collection Event | CEID |
|-----------------------|------|
| GemControlStateLOCAL | 8 |
| GemControlStateREMOTE | 9 |
| GemEquipmentOFFLINE | 22 |

3.4 Process States

See Figure 3-4 for a description of the Fluidmove processing state model.

The Process State changes in response to either Operator or Host command inputs. Change of control state from local to remote or vice versa is only allowed in the Idle Process State. This prevents loss of command synchronization.

The Host may command Start, Stop, Pause, Resume, Local, Remote, and Abort. The Operator may command Start, Stop, Pause, Resume, Local, Remote, and Abort.

3.4.1 E10 State

Figure 3-3 illustrates the state of the Equipment in relationship to overall factory production. The E10 state diagram is implemented in the Equipment according to the details specified in the SEMI E10 document. The following summarizes the Equipment's implementation of the E10 standard:

The Equipment can transition from any state to any other state except for "Productive". The "Productive" state can only be entered from the "Standby" state. Upon startup, the Equipment is in "Non-Scheduled Time".

E10 states are not available to the host computer via SECS/GEM.



NOTE

Refer to Table 3-9 for definition of numbers used in Figure 3-3.




Figure 3-3 E10 State Diagram

3.4.1.1 E10 State Transitions

Certain state transitions will cause a collection event to be signaled. If the event is enabled, this event will be sent to the Host along with the appropriate reports if appropriate. Table 3-9 lists the state transitions and notes when events will be sent to the Host.

**NOTE**

The numbers in the # column refer to those in Figure 3-3.

Table 3-9 E10 State Transitions

| # | From | Trigger | To | Description |
|---|----------------|--------------------------------|--------------------|--|
| 1 | Unknown | Power-Up | Non-Scheduled Time | Upon Power-Up, the Equipment defaults to this state. |
| 2 | Unknown | Operator Request | Conditional | The Operator changes states from the previous state to the new state. The conditional depends on the Operator's intentions. |
| 3 | Non-Productive | Operator Request | Non-Productive | — |
| 4 | Standby | Processing of material begins. | Productive | Equipment is processing material. |
| 5 | Productive | Operator Request | Non-Productive | The Operator changes states from Productive to a new Non-Productive state. Transition will be made according to conditional transition #2. |

3.4.1.2 E10 STATE Values

The values for E10 states are listed in Table 3-10.

Table 3-10 E10 State Values

| Value | Description |
|---|---|
| Non-Productive/ Non-Scheduled Time | The Equipment is not scheduled to be used in production. An Operator can put the Equipment into this state at any time. |
| Non-Productive/ Unscheduled Downtime | The Equipment has been scheduled to be used in production, but is unable to be used because of unforeseen events. Possible reasons for transitions into this state include: 1) maintenance delay 2) repair 3) replacement of a disposable 4) bad input (bad boards, etc.) 5) facility related downtime |
| Non-Productive/ Scheduled Downtime | The Equipment has been scheduled to be out of production so that maintenance can be performed. |
| Non-Productive/ Engineering | The Equipment may be actively running boards, but these are not intended to be used in normal production. This state signifies that Engineering data is being gathered from the Equipment separate from an actual productive run. |
| Non-Productive/ Standby | The Equipment is ready for production, but is awaiting resources. These resources may be in the form of physical material (boards) or in the form of information (process program, and START command). |
| Productive | The Equipment is actively processing boards for use in production. |

3.4.2 Equipment Process States

Figure 3-4 illustrates in greater detail the processing at the Equipment. This diagram depicts the working states of the Equipment.



NOTE

Refer to Table 3-11 for definition of numbers used in Figure 3-4.




Figure 3-4 Equipment Process States

3.4.2.1 Equipment Process State Transitions

**NOTE**

The numbers in the # column refer to those in Figure 3-4.

Table 3-11 Process State Transitions

| # | From | Trigger | To | Description |
|----|----------|----------------------------|----------|--|
| 1 | Unknown | Power-Up | Idle | At power-up, the Equipment defaults to the IDLE state. |
| 2 | Idle | Run Command | Running | Either the Host or Operator issues a run command. This command can be issued by a remote command from the Host or by local Operator. |
| 3 | Running | Pause Command | Paused | Either the Host or Operator issues a pause command. This command can be issued by a remote command from the Host or by local Operator. |
| 4 | Paused | Unpause Command | Running | Either the Host or Operator issues an Unpause command. This command can be issued by a remote command from the Host or by local Operator. |
| 5 | Running | Stop Command | Idle | Either the Host or Operator issues a Stop command. This command can be issued by a remote command from the Host or by the local Operator. This command will stop processing after the current board has completed. |
| 6 | Running | Error Occurrence | Error | An error has occurred on the Equipment. |
| 7 | Error | Operator Error Acknowledge | Idle | Once the Operator has acknowledged the error, the Equipment will transition to the Idle state. |
| 8 | Running | Abort Command | Aborting | Either the Host or Operator issues an Abort command. This command can be issued by a remote command from the Host or by the local Operator. |
| 9 | Aborting | Machine stopped | Idle | Once the machine has halted, the Equipment will transition to the Idle state. |
| 10 | Paused | Stop Command | Idle | Either the Host or Operator issues a Stop command. This command can be issued by a remote command from the Host or by the local Operator. |

3.4.2.2 Equipment Process State Values

The values for Equipment process states are listed in Table 3-12.

Table 3-12 Equipment Process State Values

| Value | Description |
|----------|--|
| Idle | The Equipment is initialized to this state. This state indicates that the Equipment is not dispensing on a board nor is it waiting for a board to arrive at the dispense station. |
| Active | <p>The Active state includes the following:</p> <p>Running - While in this state, the Equipment is either currently waiting for a board to arrive at the dispense station, processing a board, or unloading a processed board out of the dispense station.</p> <p>Paused - This state indicates that the Equipment is paused during the processing of a board. Processing continues on the current board when the UNPAUSE command is issued. The transition to the Idle state can occur if the stop command is issued.</p> |
| Aborting | When in the Running state, upon receiving an ABORT command, the Equipment will command the machine to stop all processing immediately. This state indicates that this is currently occurring. Once all processing has been halted, the transition to the Idle state will occur. |
| Error | An error has occurred while in the Running state. A description of the error will be displayed to the user. Upon acknowledgment of the error, the Equipment will transition to the Idle state. |

3.4.3 Related Variables

Table 3-13 lists the variables (SVs, ECs, or DVs) which are relevant to the Equipment processing states. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-13 Equipment Processing Variables

| Variable Name | VID |
|----------------------|-----|
| PREVIOUSPROCESSSTATE | 36 |
| PROCESSSTATE | 37 |

3.4.4 Related Collection Events

Many of the Equipment's collection events relate to process state changes. For a complete listing of these, refer to [Appendix B](#).

3.5 Data Collection

Note the three types of variables: Status Variable (SV), Data Variable (DV), and Equipment Constants (EC). The Host sets only ECs. DVs are time stamped by being associated with Collection Events IDs (CEID), and will be reported by Fluidmove in Event Reports.

3.5.1 Variables

The Equipment has a fixed set of Variables which can be read by the Host. Each variable is identified by a unique Variable ID (VID). [Appendix A](#) lists all variables for both Fluidmove and standard GEM operations.

There are three types of variables: Status Variables, Data Variables, and Equipment Constants. The Host can read variables of any type, but can set values only for equipment constants. The Host can read values for Status variables and equipment constants whenever the Equipment is on-line, but values for Data Variables are typically meaningful only immediately after certain Collection Events (CEIDs), and so are typically reported only in Event Reports (S6F11).

3.5.2 Are You There

The Host can send S1F1 at any time to determine if the SECS link is operational. The Equipment responds with S1F2, if the Equipment is in the ONLINE & COMMUNICATING states. This indicates Model Number (MDLN) and Software Revision Number (SOFTREV).

3.5.3 Host Requests Status

The Host can send S1F3 when the Equipment is on-line to read equipment constants.

The Host can send S2F13 when the Equipment is on-line to read equipment constants.

For this Equipment, S1F3 and S2F13 with a list of VIDs are essentially the same. That is, either message can return Variables of any type. However, S1F3 with a zero-length list will return only VIDs of type SV, and S2F13 with a zero-length list will return only VIDs of type EC.

3.5.4 Setting Equipment Constants

The Operator can change the value for equipment constants. Once the Operator has changed an EC value, the Equipment will note the EqConstChange event. The VID for the changed EC will be reported to the Host in the variable ECIDCHANGE.

3.5.5 Event Reports

The Equipment has a fixed set of Events which can occur. Each Event is identified by a unique Collection Event ID (CEID). The CEIDs are listed in [Appendix B](#).

When an event occurs, the Equipment sends the appropriate S6F11 Event Report message to the Host (if that particular event has been enabled). Event Reports are defined by the Host (S2F33) and linked to a specific CEID (S2F35).

The Equipment allows the Host to enable and disable Event Reports using S2F37. If the Host enables a CEID, for which no Event Report is defined, the Equipment will send a “null” (no data) report when the event occurs.

The Host can “force” Event Reports on the Equipment using the following Event Report Request messages:

| | |
|-------|--|
| S6F15 | Host requests an Event Report associated with a CEID. |
| S6F17 | Host requests an Annotated Event Report associated with a CEID. |
| S6F19 | Host requests an Event Report associated with a Report ID. |
| S6F21 | Host requests an Annotated Event Report associated with a Report ID. |

3.5.6 Time Driven Trace

The Equipment supports Time Driven Trace initiated from the Host. The Host initializes a trace using S2F23. The Equipment will send the data requested after the specified time interval has expired. The data will be sent using the S6F1 (Trace Data Send) message.

The Equipment can handle several concurrent traces. The number of concurrent traces is determined by the size of the trace data requested. The Equipment can support at least four concurrent traces to a maximum size (i.e. all variables requested).

The Equipment allows Host definition of trace data to exceed the one-block limit when reported. That is, the SEMI E5 standard states that the S6F1 (Trace Data Send) message is limited to a single SECS block; but the Equipment will allow this point to be overlooked at the Host’s request. If the Host does define trace data to be larger than one SECS block, then the Equipment will send the multiple blocks, not preceded by the S6F5/S6F6 Inquire/Grant scenario.

3.5.7 Limits Monitoring

The Host can define limits for various Variables on the Equipment. When the appropriate limits transitions occur, the Equipment will report this occurrence by sending an event to the Host (if the event is enabled). The Host may define limits for a particular Variable through the S2F45 (Define Variable Limit Attributes). Through this message, the Host may define up to seven limits for each eligible Variable. For each limit (LIMITID), the Host defines an UPPERDB and a LOWERDB. The Equipment generates events when a transition across these boundaries occurs. The Host may set the rate at which the Equipment polls the Variables to determine if a limit has been crossed by setting the GEMLIMITSDELAY variable (VID 60).

3.5.7.1 Event Signaling

For any event that exists on the Equipment, the event message will be sent to the Host only if the reporting for that particular event has been enabled. In this “EVENT SIGNALING” section, assume that the Host has enabled the proper reporting so that these events will be sent to the Host.

After the Host sets UPPERDB and LOWERDB values for a particular limit, the Equipment will send an event message when a transition occurs across these boundaries. The procedure for reporting is illustrated in Figure 3-5 and Figure 3-6.




Figure 3-5 Limits Events Signaling




Figure 3-6 Limits State Diagram

3.5.8 Limits State Transitions

Table 3-14 Limits State Transitions

| # | From | Trigger | To | Description |
|---|-------------|--|-------------|--|
| 1 | Enabled | Host undefines limits attributes. | Disabled | Host sends S2F45 to undefine limits. |
| 2 | Disabled | Host defines limits. | Conditional | Host sends S2F45 to define limits. |
| 3 | Below Limit | Variable changes to greater than or equal to UPPERDB. | Above Limit | Limit transition event is signaled to Host if enabled. |
| 4 | Above Limit | Variable changes to less than or equal to LOWERDB. | Below Limit | Limit transition event is signaled to Host if enabled. |
| 5 | No Zone | Variable changes to less than or equal to LOWERDB from No Zone. | Below Limit | Limit transition event is signaled to Host if enabled. |
| 6 | No Zone | Variable changes to greater than or equal to UPPERDB from No Zone. | Above Limit | Limit transition event is signaled to Host if enabled. |

3.5.8.1 Limits States

A variable's defined limits may be in any of the states specified in Table 3-15:

Table 3-15 Limits States

| State | Limits |
|-------------|---|
| Enabled | Within this super-state, a limit has been defined, and monitoring of the variable is taking place. |
| Disabled | Limits are not defined. |
| Below Limit | The value of the variable is less than or equal to LOWERDB. |
| Above Limit | The value of the variable is greater than or equal to UPPERDB. |
| No Zone | This limit has just been defined, and the value of the variable is less than UPPERDB and greater than LOWERDB. No limits transitions have occurred. |

3.5.9 Disk Files

The Equipment maintains a disk file which contains the current equipment constant settings. The file is updated each time the Operator or Host changes an equipment constant. The most recent settings for some of the equipment constants are read from the file when the Equipment is powered-on.

All Event Report definitions, links, and enable status as well as Limits attributes are also maintained on separate disk files.

3.5.10 Related Variables

The following table lists the variables (SVs, ECs, or DVs) which are relevant to data collection setup and maintenance. This section does not list the variables which contain Equipment-specific information. For a more complete description of specific variables, refer to [Appendix A](#).

Table 3-16 Data Collection / Setup Variables

| Variable Name | VID |
|---------------|-----|
| ECIDCHANGE | 67 |

3.5.11 Related Events

The following table lists the collection events (CEIDs) which are relevant to data collection. In addition to these, each variable which is eligible for limits monitoring must have a specific collection event associated with it. For a more complete description of these events, refer to [Appendix B](#) or the description in this section.

Table 3-17 Data Collection CEIDS

| Collection Event | CEID |
|------------------|------|
| EqConstChange | 20 |

3.6 Alarm Management

The Equipment has a fixed set of alarm conditions which can occur. Each alarm is identified by a unique Alarm ID (ALID), and has an associated severity code (ALCD) and alarm text (ALTX). Examples of possible alarms are shown in [Appendix C](#).

3.6.1 Alarm States

Each alarm (ALID) can be in either of two states: CLEAR (off) or SET (on). Several alarms can be SET simultaneously. At power-up, all alarms are cleared.

3.6.2 Reporting

The Equipment reports alarms to the Host when they occur, without Host action, using the alarm report message S5F1 or configurable option, depending on CONFIGALARMS. The transition of an ALID from OFF to ON is referred to as “going on” or “leading edge”, and the transition from ON to OFF as “going off” or “trailing edge”. The Equipment reports both leading and trailing edge transitions.

The Equipment has two CEIDs for each ALID, one for the “going on” transition and one for the “going off” transition. In addition to the Alarm Report, the Equipment sends an Event Report if the CEID associated with the alarm change is enabled. If the CEID is enabled and no report is defined, a “null” Event Report is sent. The Event Report for an alarm transition is sent if it is enabled, even if the reporting for the alarm is disabled.

3.6.3 Enable/Disable

The Host can use S5F3 (Enable/Disable Alarms) to control which alarms the Equipment should report. Using S5F3, the Host can specify for each ALID whether the Equipment should report that alarm when it occurs. When an alarm transition occurs, if that ALID is enabled the Equipment will send an alarm report message to the Host. If the ALID is disabled, the Equipment will not send the alarm message. The Host can use S2F37 to enable or disable the CEIDs associated with these alarm transitions.

The Equipment saves Alarm Enable/Disable settings on a disk file. When the Equipment powers up, it will restore Alarm Enable/Disable settings to the same condition they had at power off.

3.6.4 Host Requests Alarm Status

The Host can use S5F5 to request the Equipment to report all alarms which exist and the ON/OFF state for each.

The Host can use S5F7 which is similar, but which causes the Equipment to report only those alarms (ALIDs) which are Enabled, regardless of whether the alarm is ON or OFF.

3.6.5 Compatibility

The Equipment supports the following Alarm Report message formats for older Host implementations (refer to [1.9.3 GEM Configuration](#).)

- S5F71/S5F72
- S5F73/S5F74

3.6.6 Related Variables

The following table lists the variables (SVs, ECs, or DVs) which are relevant to alarm management. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-18 Alarm Management Variables

| Variable Name | VID |
|---------------|-----|
| CONFIGALARMS | 1 |
| WBITS5 | 19 |
| ALARMID | 22 |
| ALARMSENABLED | 23 |
| ALARMSSET | 24 |
| ALARMSTATE | 25 |
| ALARMSERIAL | 26 |

3.6.7 Related Collection Events

Each alarm defined in the Equipment has two unique collection events associated with it: a “Going-On” event, and a “Going-Off” event. The CEIDs are listed in [Appendix B](#).

3.7 Process Program Management

Processing on the Equipment is controlled by Process Programs. The Equipment requires selection of a Process Program for each process. The Equipment supports the use of unformatted process programs.

Fluidmove uses proprietary ASCII and binary image files to define process programs (recipes).

3.7.1 Equipment Management of Process Programs

The Equipment provides a Process Program Library, implemented as a set of binary files maintained on a hard disk. Each Process Program is identified by a unique Process Program ID (PPID). Upper and lower case alphabetic characters are not considered distinct, and the Equipment will not distinguish between them.

For Fluidmove, the PPID corresponds to the name of a recipe file which is the culmination of the main program and various support files.

The Operator may modify any one of the Process Programs stored on the Equipment. The Host will be notified via the GemPPChangeEvent Collection Event if the Operator creates, changes, or deletes a Process Program. The Operator can also select a PPID to be uploaded to the Host (S7F3), or download from the Host (S7F5).

3.7.2 Host Management of Process Programs

Process Programs are saved to disk on the Equipment. Process Programs are typically created and updated at the Equipment. However, the Equipment provides complete facilities for the Host to manage the storage and use of Process Programs. This allows the Equipment to operate cooperatively Host-implemented systems. The Host has the following capabilities:

- The Host can upload a Process Program from the Equipment Library by using S7F5 (Process Program Request). The Operator can also initiate a Process Program Upload through the Equipment's user interface.
- The Host can download a Process Program to the Equipment library by using S7F3 (Process Program Send). The Host may send S7F1 (Multi-block Inquire) to the Equipment before sending a multi-block Process Program. The Operator can also initiate a Process Program Download through the Equipment's user interface.
- The Host can delete one or more Process Programs from the Equipment library by using S7F17 (Process Program Delete).
- The Host can determine which Process Programs are currently stored in the Equipment library by using S7F19 (Process Program Directory).

3.7.3 Related Variables

The following table lists the variables (SVs, ECs, or DVs) which are relevant to process program management. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-19 Process Program Management Variables

| Variable Name | VID |
|----------------|-----|
| PPCHANGENAME | 40 |
| PPEXECNAME | 32 |
| PPCHANGESTATUS | 41 |

3.7.4 Related Events

The following table lists the collection events (CEIDs) which are relevant to process program management. For a more complete description of these events, refer to [Appendix B](#).

Table 3-20 Process Program Management CEIDS

| Collection Event | CEID |
|---------------------|------|
| GemPPChangeEvent | 3 |
| GemBadDownloadEvent | 7 |

3.8 Remote Commands

Processing at the Equipment can be guided by either a local Operator or by a Host computer. This section describes the remote commands available to the Host.

Much of the behavior of the Equipment and its acceptance of remote commands is directed by requirements of the Control State. For a complete description of the Control State, refer to [3.3 Control States](#).

The Equipment will accept remote commands only when the Control State is Remote.

The Host has the ability to configure whether the Equipment will transition to Remote or Local as a default upon entering the On-Line state from Off-Line. This can also be done through the SECS/GEM Setup dialog box in Fluidmove.

Once in the Remote state, the Host has the authority to issue any of these remote commands and they will not be rejected because of an invalid control state. Commands may be rejected for other reasons (trying to start a process with no material loaded, etc.).

While in Remote state, the Operator still has the ability to issue commands and change the control state. If the Operator issues a command while in Remote state, the Equipment will send the Operator Command collection event if enabled. When the Operator “grabs” control away from the Host by changing the Control State to Local, the Equipment will send either the GemControlStateLOCAL or GemEquipmentOFFLINE event to the Host. The Host also has the ability to put the Equipment into a Local state by sending the LOCAL remote command while in Remote state. Furthermore, if the Operator presses any of the buttons on the Run Window (GO, PAUSE, STOP, ABORT), the Host will get the corresponding events (StartCmd, PauseCmd, StopCmd, AbortCmd - refer to [Appendix B](#)).

3.8.1 S2F41 Commands

The general format for remote commands using the S2F41 message is:

```
S2F41 [W]                                * H->E

<L [2]

    <A RCMD>                               * Remote command string

    <L

        <L [2]

            <A CPNAME>                       * Command Parameter Name

            <CPVAL>                           * Command Parameter Value

        >

    ...

    >

> .
```

The following commands may be sent by the Host to the Equipment:

START

This command starts processing on the Equipment assuming all proper initialization has taken place and material is present.

```
S2F41 [W]
    <L [2]
        <A 'START'>
        <L>
    > .
```

STOP

This command will stop the processing of material at the Equipment. Boards currently in process will be completed, but no new boards will be loaded.

```
S2F41 [W]
    <L [2]
        <A 'STOP'>
        <L>
    > .
```

PAUSE

The PAUSE command will cause the Equipment to complete the current instruction in process, but not to start the next instruction until the RESUME command has been given.

```
S2F41 [W]
    <L [2]
        <A 'PAUSE'>
        <L>
    > .
```

RESUME

After a PAUSE command has been given, the RESUME command will continue to process the existing board according to the recipe.

```
S2F41 [W]
    <L [2]
        <A 'RESUME'>
        <L>
    > .
```

LOCAL

While the Equipment is in Remote state, the Host can put the Equipment into Local state by sending the LOCAL command.

```
S2F41 [W]
    <L [2]
        <A 'LOCAL'>
        <L>
    > .
```

ABORT

The Host can abort processing at the next safe stopping point by sending the ABORT command with the AbortLevel parameter as follows:

```
S2F41 [W]
    <L [2]
        <A 'ABORT'>
        <L
            <L
                <A 'AbortLevel'>    *CPNAME
                <U1 1>              *CPVAL
            >
        >
    > .
```

3.8.2 Related Variables

The following table lists the variables (SVs, ECs, or DVs) which are relevant to remote control. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-21 Remote Control Variable

| Variable Name | VID |
|-----------------|-----|
| ABORTLEVEL | 21 |
| PREVIOUSCOMMAND | 34 |

3.8.3 Related Events

The following table lists the collection events (CEIDs) which are relevant to remote control. For a more complete description of these events, refer to [Appendix B](#) or the description in this chapter.

Table 3-22 Remote Control CEIDS

| Collection Event | CEID |
|------------------|------|
| OperatorCommand | 4 |
| StartCmd | 14 |
| StopCmd | 15 |
| PauseCmd | 16 |
| ResumeCmd | 17 |
| AbortCmd | 18 |

3.9 Material Movement

Material movement on the Equipment consists of the following three board holding areas:

- Pre-dispense Area
- Dispensing Area
- Post-dispense Area

In order for processing to begin, a board must arrive from the upstream machine. The Equipment then conveys the board to the pre-dispense area, conveys it to the dispensing area, processes it, and then conveys the board to the post-dispense area. Before a new lot can be started, the board must be removed from the dispensing area. Collection events can be triggered only when a board arrives and leaves the dispensing area.

3.9.1 Related Variables

For a complete description of the variables relevant to material movement, refer to [Appendix A](#).

3.9.2 Related Collection Events

Many collection events relate directly to material movement or imply that material movement has taken place. For a complete listing of these collection events, refer to [Appendix B](#).

3.10 Equipment Terminal Services

The Equipment supports exchange of free text messages with the Host (SECS Stream 10). This Equipment accepts the following messages from the Host, and responds accordingly if the W-Bit is set to 1:

S10F3 /* Single Line Data */

S10F5 /* Multi-Line Data */

S10F9 /* Broadcast */

The message text will be displayed on the Equipment's CRT. Collection Event S10Ack (CEID 21) occurs once the Operator has acknowledged the message and an Event Report will be sent to the Host (if enabled).

The S10F3 and S10F9 are restricted to a single TEXT data item, but S10F5 can contain multiple TEXT data items. Each TEXT data item is limited to 160 characters.

If the Operator has not acknowledged an existing message when the Host sends another message, the new message will be displayed and the old one discarded.

The Host can send a message with a 0-length text to clear the Operator text display.

Also, the Equipment allows the Operator to send a single block message to the Host via S10F1. The maximum length of this text is 160 characters. The S10F2 response from the Host is ignored.

Fluidmove provides this functionality by allowing an operator to enter his message through the SECS/GEM Setup dialog box (Terminal tab), or via the SECS/GEM tab in the Run Window. The message will be sent when the Operator presses the Send button on screen.

Fluidmove also provides a Terminal Display to display text received from the Host from the SECS/GEM Setup dialog box (Terminal tab) or via the SECS/GEM tab in the Run Window.

Fluidmove notifies the Operator that a text message has arrived from the Host by blinking the GEM status bar at lower portion of screen. If the beep option has been selected a beep once every half a second will be used to catch Operator's attention. The Operator can then view the incoming message through the SECS/GEM Setup dialog box (Terminal tab), or via the SECS/GEM tab in the Run Window. In the same locations, there are provisions for the Operator to send a message to the Host.

3.11 Error Messages

The Equipment provides standard Stream 9 messages to report SECS-I errors. Refer to [5.7 SECS Error Messages](#) for detailed description of these messages:

| | |
|--------------|------------------------|
| S9F1 | Unrecognized Device ID |
| S9F3 | Unrecognized Stream |
| S9F5 | Unrecognized Function |
| S9F7 | Invalid Data |
| S9F9 | Transaction Timeout |
| S9F11 | Data Too Long |

Fluidmove can reject a primary message received from the Host as incorrectly formatted for SECS-II (invalid data, or data too long).

3.12 Clock

The Equipment contains Clock/Calendar hardware, by which it knows the current date and time. This allows the following:

- The Host can send S2F31 to set the Equipment's Clock/Calendar hardware.
- The Host can send S2F17 to read the Equipment's Clock/Calendar hardware.
- The Operator can initiate a Date/Time request from the Host. This is done through the SECS/GEM Setup dialog box (Control tab).

3.12.1 Related Variables

Table 3-23 lists the relevant clock variables (SVs, ECs, or DVs). For a complete description of these variables, refer to [Appendix A](#).

Table 3-23 Clock Variables

| Variable Name | VID |
|---------------|-----|
| CLOCK | 27 |

When time update messages from the Host are not arriving, a time update request to the Host shall be made approximately once per hour until the Host resumes time update messages.

3.13 Spooling

When the SECS link between the Host and the Equipment goes down (RTY error on the Equipment side), the Equipment will spool appropriate messages so that the Host can read them once the link comes back up (after a successful Connect Request transaction).

The Host can set spooling attributes on the Equipment by setting certain equipment constants with the S2F15/16 transaction.

The Host can define streams and functions of messages to be spooled through the S2F43/44 transaction. Stream one (S1Fx) messages are not eligible for spooling. The Host can also disable spooling for messages through this S2F43/44 transaction. Stream 9 messages are not spooled.

The Host may read spooled messages or purge the Equipment's spool through the S6F23/24 transaction.

3.13.1 A Word of Caution

If the Host does not intend to use the spooling features of the Equipment, the equipment constant ConfigSpool should be set to zero. Setting this EC to zero disables the spooling feature. If this is not set to zero, and the Host does not support spooling, the SECS connection with the Equipment will be crippled. This happens because of the following:

1. When spooling becomes active (transmission error), the Equipment will not send "Non-Stream 1" primary messages to the Host. That is, it will not send events, alarms, process programs, terminal display, etc.
2. When spooling becomes active, the ONLY way to deactivate it is to read (purge) or delete the spool from the Host. In complying with the GEM standard, the Equipment does not have the ability to reset its spooling state.
3. Therefore, if your Host does not support spooling and spooling becomes active, you will never again receive non stream 1 messages from the Equipment. If this occurs, you will need to use a Host simulator such as SECSIM to delete the spool.

3.13.2 Spooling Sequence

Messages are sent to the spool only if the Host has enabled these messages for spooling. This precondition will not be repeated throughout this section. Assume that the messages referred to in this section have been enabled for spooling.

While spooling is active, the Host may initiate primary messages and the Equipment will respond, if it is in the COMMUNICATING state.

Figure 3-7 and Table 3-24 describe the spooling sequence. Refer to Table 3-24 for definition of numbers used in the figure.




Figure 3-7 Spooling State Diagram

**NOTE**

The numbers in the # column refer to those in Figure 3-7.

Table 3-24 Spooling State Transitions

| # | From | Trigger | To | Description |
|----|-----------------|--|------------------------|--|
| 1 | Power On | Equipment shutdown | Power Off | The Equipment may power off at any time. |
| 2 | Power Off | Equipment Startup | History* (Power On) | Equipment re-boots after a shutdown. Spooling will continue according to its state when the Equipment was powered off. |
| 3 | Spool Inactive | The Equipment experiences a transmission failure and the variable GemConfigSpool (VID 66) is set to "1" (enabled). | Spool Active | The Equipment will now start spooling any messages which have been defined by the Host. If the Host does not wish to implement Spooling, the EC GemConfigSpool should be set to "0" and the spool state will never become active. |
| 4 | Default | Entry into Spool Active | No Spool Output | No spooled messages are being read by the Host. |
| 5 | Default | Entry into Spool Active | Spool Not Full | The spool file has not yet filled up. |
| 6 | Spool Not Full | The Equipment's spool has reached capacity. | Spool Full | The Equipment will start to either discard new messages destined for the spool or overwrite the beginning of the spool, depending on the setting of GemOverWriteSpool (VID 62). |
| 7 | Transmit Spool | The Equipment has de-spoiled some messages, but not all have been sent to the Host. | No Spool Output | No spooled messages are being read by the Host. |
| 8 | No Spool Output | The Host has requested spooled messages to be sent by sending S6F23. | Transmit Spool | The Equipment will send messages according to the setting of GemMaxSpoolTransmit (VID 46). If GemMaxSpoolTransmit is zero, all messages will be sent, otherwise only the number of messages specified in this variable will be sent. |
| 9 | No Spool Output | The Host requests the Equipment to purge its spool. | Purge Spool | The Equipment will delete its spool. |
| 10 | Spool Output | Entire spool has either been read or purged by the Host. | Spool Inactive | The Equipment will continue normal SECS communicating. |

3.13.2.1 Spooling Starts

When a transmission failure occurs, the first message sent to the spool is the event message GemSpoolingActivated. The next message sent to the spool is the message which caused the communications failure. Table 3-25 depicts the activity at the Equipment when spooling starts.

Table 3-25 Spooling Activity

| # | Equipment Send Sequence | Spool Sequence | Description |
|---|---------------------------|---|---|
| 1 | S5F1 (Alarm Report 1) | S6F11 (Spool Activated Event Report) | Equipment attempts to send an alarm report to the Host, but experiences a transmit failure. The GemSpoolingActivated event (CEID 23) is sent to the spool. Variable GEMSPPOOLSTARTTIME (VID 52) is updated. |
| 2 | | S5F1 (Alarm Report 1) | The Alarm Report message is sent to the spool. |
| 3 | S6F11 (Event Report 1) | S6F11 (Event Report 1) | The Equipment generates an Event Report and it is sent to the spool. |
| 4 | S5F1 (Alarm Report 2) | S5F1 (Alarm Report 2) | The Equipment generates an alarm report and it is sent to the spool. |

3.13.2.2 Equipment Spools Messages

While spooling messages, the Equipment will increment the GEMSPPOOLCOUNTACTUAL and GEMSPPOOLCOUNTTOTAL status variables for each message spooled. Messages which require an inquire/grant scenario are spooled along with the inquire message as a single message. That is, if a multi-block S6F11 (Event Report) message is being sent to the Host and spooling is active, the S6F5 (inquire) as well as the S6F1 are sent to the spool and GEMSPPOOLCOUNTTOTAL and GEMSPPOOLCOUNTACTUAL are incremented by one.

The Equipment maintains two equipment constants which affect the spooling of messages. The first is CONFIGSPOOL. If this is set to zero, then spooling will never become active. If it is set to one, spooling will become active when a transmission failure occurs.

The EC OVERWRITESPOOL determines if the Equipment should over-write the oldest messages with new ones when the spool becomes full. If OVERWRITESPOOL is TRUE, old messages will be over-written with new ones. If FALSE, new messages will be discarded when the spool is full.

3.13.2.3 Host Reads Spooled Data

The Host can read spooled messages by sending the S6F23 message. Upon receipt of this message, the Equipment will reply and attempt to send spooled messages. Messages are sent in order of oldest to newest, with no priority given to a particular kind of message. The EC MAXSPOOLTRANSMIT determines the maximum number of spooled messages which are sent per S6F23 message received from the Host. If zero, all spooled messages are sent, if any other number, that number of messages are sent.

During the de-spooling of messages, the Equipment maintains only one outstanding Equipment-initiated transaction. The Equipment will wait for either a reply to the primary or a T3 timeout before starting another transaction. If the de-spooled message requires an inquire/grant scenario, the Equipment will initiate this transaction first. If the Host accepts the inquiry, the message is sent. If not, then the Equipment removes the message from the spool and discards it.

If a transmission failure occurs while attempting to send the spool, the event GemSpoolTransmitFailure is sent to the spool and spooling will remain active. While the spool is active, any new (spoolable) messages generated by the Equipment are also sent to the spool.

When the spool has been completely transmitted, the event GemSpoolingDeactivated is sent to the Host.

Instead of reading spooled messages, the Host can purge the spool by sending S6F23 with RSDC = 1. For details, refer to [4.2.80 S6F23 – Request Spooled Data](#).

3.13.3 Spool States

3.13.3.1 Power Off

The Equipment is completely shut down.

3.13.3.2 Power On

The Equipment is “on” and in a stable state. Table 3-26 describes the substates.

Table 3-26 Power On Spool Substates

| Substate | Description |
|----------------|--|
| Spool Inactive | Spooling is not activated. This is either because GemConfigSpool is “0” (disabled) in which case, spooling will never be active, or because while GemConfigSpool is enabled (“1”), a RTY error has not occurred. In this state, no messages are sent to the spool. The Host may define or un-define messages eligible for spooling should the link go down. |
| Spool Active | <p>While GemConfigSpool is enabled (“1”), the Equipment has experienced a transmission failure (RTY error). Upon entry into this state, the first message sent to the spool is the GemSpoolingActivated event, assuming that this event is enabled and that spooling for the particular stream and function have been enabled. This message will enter the spool even before the message which originally caused the RTY error.</p> <p><u>Spool Not Full</u> - The file containing the spooled messages has not reached its capacity.</p> <p><u>Spool Full</u> - The file containing the spooled messages has reached its capacity.</p> <p><u>No Spool Output</u> - In this state, the Host is not reading or purging the Equipment’s spool.</p> <p><u>Spool Output</u> - This super-state contains the two sub-states in which the Equipment’s spool is either being read or purged by the Host.</p> <p><u>Purge Spool</u> - The Equipment is purging its spool, erasing all spooled messages.</p> <p><u>Transmit Spool</u> - The Equipment is transmitting spooled messages to the Host.</p> |

3.13.4 Related Variables

The following table lists the variables (SVs, ECs, or DVs) which are relevant to spooling. For a more complete description of these variables, refer to [Appendix A](#).

Table 3-27 Spooling Variables

| Variable Name | VID |
|---------------------|-----|
| MAXSPOOLTRANSMIT | 46 |
| SPOOLCOUNTACTUAL | 48 |
| SPOOLCOUNTTOTAL | 49 |
| SPOOLFULLTIME | 50 |
| SPOOLLOADSUBSTATE | 51 |
| SPOOLSTARTTIME | 52 |
| SPOOLSTATE | 53 |
| SPOOLUNLOADSUBSTATE | 54 |
| OVERWRITESPOOL | 62 |
| CONFIGSPOOL | 63 |

3.13.5 Related Events

The following table lists the collection events (CEIDs) which are relevant to spooling. For a more complete description of these events, refer to [Appendix B](#) or the description in this chapter.

Table 3-28 Spooling CEIDS

| Collection Event | CEID |
|-------------------------|------|
| GemSpoolingActivated | 23 |
| GemSpoolingDeactivated | 24 |
| GemSpoolTransmitFailure | 25 |

4 SECS Message Detail

This section describes the basics of SML notation and lists each message sent or understood by the Equipment.

4.1 SML Notation

Message descriptions are shown using “SECS Message Language” (SML) notation. SML is a general notation developed by GW Associates for describing SECS messages. SML is similar to the notation used in the SECS Standards documents, but SML is a more precise and regular notation.

4.1.1 Data Item Format

In SML, the format for a Data Item is as follows:

< type [count] value >

The components of a Data Item are listed and described in Table 4-1.

Table 4-1 Components of a SML Data Item

| Component | Description | | | | | | | | | | | | | | |
|----------------|---|---|-------|---|--------|---|-------|----------------|-----------------|----------------|-------------------|--------|----------------|---------|------------|
| < > | Angle Brackets. Each Data Item is enclosed within angle brackets (“less than”, “greater than”). This notation implies that each Data Item has a Data Item Format and Data Item Length as required by SECS-II. | | | | | | | | | | | | | | |
| Type | <p>This specifies the SECS-II Data Item format. It will have one of the following values:</p> <table><tr><td>A</td><td>ASCII</td></tr><tr><td>B</td><td>Binary</td></tr><tr><td>J</td><td>JIS-8</td></tr><tr><td>I1, I2, I4, I8</td><td>Signed Integers</td></tr><tr><td>U1, U2, U4, U8</td><td>Unsigned Integers</td></tr><tr><td>F4, F8</td><td>Floating Point</td></tr><tr><td>BOOLEAN</td><td>True/False</td></tr></table> | A | ASCII | B | Binary | J | JIS-8 | I1, I2, I4, I8 | Signed Integers | U1, U2, U4, U8 | Unsigned Integers | F4, F8 | Floating Point | BOOLEAN | True/False |
| A | ASCII | | | | | | | | | | | | | | |
| B | Binary | | | | | | | | | | | | | | |
| J | JIS-8 | | | | | | | | | | | | | | |
| I1, I2, I4, I8 | Signed Integers | | | | | | | | | | | | | | |
| U1, U2, U4, U8 | Unsigned Integers | | | | | | | | | | | | | | |
| F4, F8 | Floating Point | | | | | | | | | | | | | | |
| BOOLEAN | True/False | | | | | | | | | | | | | | |
| Count | <p>Count of the element values that make up the item. If present, the count is enclosed within square brackets “[]”. The count may be omitted, in which case the square brackets are also omitted.</p> <p>The “count” specifies the number of value elements in the Data Item Value. For String formats (ASCII, Binary, JIS-8), “count” specifies the number of characters in the string. For Numeric formats (I1, I2, I4, I8, U1, U2, U4, U8, F4, F8, BOOLEAN), “count” specifies the number of values in the array. For simple scalar numeric values, “count” is usually “1”. For LIST items, “count” specifies the number of items in the list.</p> <p>If “count” is omitted, then the length of the Data Item is implied by the value which follows. The “count” can range between known limits. It may be specified as minimum and maximum “counts”, separated by two dots. (For example, [0..40]).</p> | | | | | | | | | | | | | | |

Table 4-1 Components of a SML Data Item (continued)

| Component | Description |
|-----------|---|
| Value | <p>Value of a single item element. Values are shown in a notation that depends on the item type. For example, ASCII values are shown as characters enclosed in quotes, Unspecified Binary values are shown in hexadecimal.</p> <p>An ellipsis (...) is used to indicate additional elements may occur, as for example where substructures may repeat in a List structure.</p> <p>As an example, a two-byte unsigned integer Data Item with an array of three values 21, 22, and 23 is represented as:</p> <p><U2 [3] 21 22 23></p> <p>Numeric values shown are considered decimal integers unless otherwise indicated. Negative values are shown with a leading minus sign “-“. Hexadecimal values are shown in C-Language convention, with a leading “0x”.</p> <p>10 Decimal Ten</p> <p>0x10 Hexadecimal 10</p> <p>-10 Decimal Negative 10</p> <p>Where a value is not fixed, the SECS variable name is used directly. For Example:</p> <p><A [6] SOFTREV></p> |

4.1.2 Message Format

The format of a complete message is as follows:

SnFn W item .

The components of a complete message are described in Table 4-2.

Table 4-2 Components SML Notation

| Component | Description |
|-----------|---|
| SnFn | The Stream and Function Codes, S1F1 for example. |
| W | The W-Bit, if set. Omitted if not set. If the W-Bit is optional, it is coded within brackets "[W]". |
| Item | A Data Item that is formatted as described in 4.1.1. |
| . | A period (.) ends the message definition. |

For example, the S1F3 message might be described in SML as follows:

```
S1F3 W
    <L
        <U4 13>
        <U4 7>
    > .
```

4.2 SECS Messages

The following subsections describe the SECS messages sent or understood by the Equipment.

4.2.1 S1F1 - Are You There

S1F1 W. * H<->E

The Host may send this message to the Equipment at any time.

The Equipment sends this message periodically as a “heartbeat” to determine if the SECS link is operational.

The equipment constant ConfigConnect can be set to cause the Equipment to send S1F1 instead of S1F13 for Connect Request.

4.2.2 S1F2 - On Line Data (Equipment to Host)

S1F2 * H<-E
<L
 <A MDLN> * MDLN Model Number
 <A SOFTREV> * SOFTREV Software Revision
> .

The Equipment reports its Model Number and Software Revision.

4.2.3 S1F2 - On Line Data (Host to Equipment)

S1F2 * H->E
<L> .

4.2.4 S1F3 - Selected Status Request

```
S1F3 W                                * H-> E
<L
    <U4 VID>                          * Variable ID
    ...
    > .
```

The Host requests status from the Equipment. The Host sends the VIDs of interest. Several VIDs can be specified if desired.

Normally, only VIDs of class SV (i.e. Status Variables) are used in this message. However, the Equipment allows the Host to use any VID of class DV, EC, or SV.

If S1F3 contains a zero-length list, then the Equipment will report all variables of class SV, in order by VID.

For compatibility with older Host implementations, the Equipment allows the following alternative form for this message using an array format:

```
S1F4 W                                * H->E
    <U4 VID...>.
```

4.2.5 S1F4 - Selected Status Data

```
S1F4 W                                * H<-E
<L
    <V>                                * Status Variable Value
    ...
    > .
```

The Equipment returns the Variable Values in the order requested by S1F3. If any VID specified in S1F3 is invalid, the corresponding V in S1F4 has the following error format:

```
<L>                                * V for Invalid VID
```

4.2.6 S1F11 - Status Variable Namelist Request

```
S1F11 W                                * H->E
<L
    <U4 VID>                           * Status Variable ID
    ...
    >.
```

The Host format descriptions for the specified Variables. Several VIDs can be specified if desired.

Normally, only VIDs of class SV (i.e. Status Variables) are used in this message. However, any VID of class DV, EC, or SV can be used.

If S1F11 contains a zero-length list, then the Equipment will report all variables of class SV, in order by VID.

```
S1F11 W                                * H->E
<L> .
```

4.2.7 S1F12 - Status Variable Namelist Reply

```
S1F12                                * H<-E
<L
    <L [3]
        <U4 VID>                       * Variable ID
        <A SVNAME>                     * Status Variable Name
        <A UNITS>                       * Units of Measure
    ...
    > .
```

The Equipment returns the Variable descriptions in order requested in S1F11. If any VID specified in S1F11 is invalid, the corresponding List in S1F12 has the following error format:

```
<L>                                * Instead of L [3]
```

4.2.8 S1F13 - Connect Request

The Equipment sends this message using the following format:

```
S1F13 W * H<-E
<L
    <A MDLN>
    <A SOFTREV>
> .
```

The Host sends this message using the following format:

```
S1F13 W * H->E
<L> .
```

Either end of the link may send S1F13 as the first message to establish connection of the link.

Under the Equipment's initialization logic, the Equipment will always attempt to establish the link. If no Host acceptance reply is received, the Equipment sends this message periodically.

4.2.9 S1F14 - Connect Request Acknowledge

The Equipment sends this message using the following format:

```
S1F14 * H<-E
<L
    <B [1] 00> * COMMACK
    <L
        <A MDLN>
        <A SOFTREV>
    >
> .
```

The Host sends this message using the following format:

```
S1F14 * H->E
<L
    <B [1] 00> * COMMACK
    <L>
> .
```

The Equipment always sends the value 0x00 for COMMACK. In messages received from the Host, COMMACK value 0x00 indicates acceptance of the connect request. Any other value indicates refusal.

4.2.10 S1F15 - Request Off-Line

S1F15 W . * H -> E

Host requests the Equipment to go Off-Line.

4.2.11 S1F16 - Off-Line Acknowledge

S1F16 * H <- E
<B [1] 0x00> . * OFLACK

Equipment Control State transits to Host Off-Line and sends this message in response to S1F15 primary. OFLACK is always zero.

4.2.12 S1F17 - Request On-Line

S1F17 W . * H -> E

Host requests the Equipment to go On-Line.

4.2.13 S1F18 - On-Line Acknowledge

S1F18 * H <- E
<B [1] ONLACK> .

Equipment responds to S1F17 primary in an attempt to go On-Line. Data item ONLACK indicates the success or failure of the attempt.

Table 4-3 On-Line Acknowledge

| ONLACK | Description |
|--------|--|
| 0x00 | OK. Equipment On-Line transition successful. Equipment Control State transits to either Local or Remote while On-Line as guided by the EC "GemOnlineSubstate". |
| 0x01 | On-Line not allowed. |
| 0x02 | Equipment already On-Line. |

4.2.14 S1F65 - Connect Request

**NOTE**

This message is provided only for compatibility with Host computers which support an older version of GEM.

The equipment constant ConfigConnect can be set to cause the Equipment to send S1F65 instead of S1F13 for Connect Request.

The Equipment sends this message using the following format:

```
S1F65 W                                * H<-E
<L
    <A MDLN>
    <A SOFTREV>
> .
```

Format 1: The Host sends this message using the following format:

```
S1F65 W                                * H->E
<L> .
```

Format 2: The Equipment also accepts the following form of this message:

```
S1F65 W .                                * H->E
```

Either end of the link may send S1F65 as the first message to establish connection of the link.

Under the Equipment's initialization logic, the Equipment will always attempt to establish the link. If no Host acceptance reply is received, the Equipment sends this message periodically.

4.2.15 S1F66 - Connect Request Acknowledge

**NOTE**

This message is provided only for compatibility with Host computers which support an older version of GEM.

If the Host sends S1F65, Format 1, the Equipment replies S1F66 using the following format:

```
S1F66                                * H<-E
<L
    <B [1] 00>                        * COMMACK
    <L
        <A MDLN>
        <A SOFTREV>
    >
> .
```

If the Host sends S1F65, format 2, the Equipment replies S1F66 using the following format:

```
S1F66                                * H<-E
<B [1] 00> .                          * COMMACK
```

The Host sends this message using the following format:

```
S1F66                                * H->E
<L
    <B [1] 00>
    <L>
> .
```

The Equipment also accepts the following form of this message.

```
S1F66                                * H->E
    <B [1] 00> .                      * COMMACK
```

The Equipment always sends the value 0x00 for COMMACK.

In messages received from the Host, COMMACK value 0x00 indicates acceptance of the connect request. Any other values indicates refusal.

4.2.16 S2F13 - Equipment Constant Request

```
S2F13 W * H->E
<L
    <U4 VID> * Equipment Constant ID
    ...
    > .
```

The Host requests the VIDs of interest. Several VIDs can be specified if desired.

Normally, only VIDs of class EC (i.e. equipment constants) are used in this message. However, any VID of class DV, EC, or SV can be used.

If S2F13 contains a zero-length list, then the Equipment will report all variables of class EC, in order by VID.

For compatibility with older Host implementations, the Equipment allows the following alternative form for this message, using an array format:

```
S2F13 W * H->E
    <U4 VID VID ...> . * Equipment Constant ID
```

4.2.17 S2F14 - Equipment Constant Data

```
S2F14 * H<-E, Multiblock
<L
    <V> * Equipment Constant Value
    ...
    > .
```

The Equipment returns the equipment constants in the order requested in S2F13. If any VID specified in S2F13 is invalid, the corresponding V in S2F14 has the following error format:

```
<L> * V for Invalid VID
```

4.2.18 S2F15 - New Equipment Constant Send

```
S2F15 W * H->E
<L
  <L [2]
    <U4 VID> * Equipment Constant ID
    <V>
  >
...
> .
```

The Host sends new values for desired equipment constants. Several equipment constants can be specified if desired.

Only VIDs of class EC can be used in this message.

4.2.19 S2F16 - Equipment Constant Send Acknowledge

```
S2F16 * H<-E
<B [1] EAC> . * Equipment Acknowledge Code
```

Normal completion returns a zero (0) in EAC. If any ECID or ECV in S2F15 is invalid, then EAC contains a non-zero value, and the Equipment rejects the entire S2F15.

Table 4-4 EAC Values

| EAC | Description |
|------|-----------------------------------|
| 0x00 | OK. |
| 0x01 | At least one ECID is invalid. |
| 0x03 | At least one ECV is out of range. |

4.2.20 S2F17 - Date and Time Request

S2F17 W . * H<->E

The Host may send this message at any time to determine the Date and Time base that the Equipment is currently using.

The Equipment sends this message at the request of the Operator.

4.2.21 S2F18 - Date and Time Data

S2F18 * H<->E
* TIME - Date and Time

<A 'YYMMDDhhmmss'> . * If TIMEFORMAT = 0
– OR –
<A 'YYYYMMDDhhmmsscc'> . * If TIMEFORMAT = 1

This message contains the current Date and Time:

| | | |
|-------------|----------------------------------|------------------|
| YY | Year (last two digits), 00 to 99 | (TIMEFORMAT = 0) |
| YYYY | Year (all four digits) | (TIMEFORMAT = 1) |
| MM | Month, 01 to 12 | |
| DD | Day, 01 to 31 | |
| hh | Hours, 00 to 23 | |
| mm | Minutes, 00 to 59 | |
| ss | Seconds, 00 to 59 | |
| cc | Centiseconds, 00 to 99 | (TIMEFORMAT = 1) |

When the Equipment receives a good S2F18, it sets its internal clock/calendar. When receiving S2F18, the Equipment will discard an invalid date or time. For example, if the date is good but the time is bad, the Equipment sets its date but not its time.

4.2.22 S2F23 - Trace Initialize Send

| | |
|--------------|------------------------------|
| S2F23 W | * H->E |
| <L [5] | |
| <U4 TRID> | * Trace ID |
| <A 'hhmmss'> | * DSPER - Data Sample Period |
| <U4 TOTSMPS> | * Total Number of Samples |
| <U4 REPGSZ> | * Reporting Group Size |
| <L | |
| <U4 SVID> | * Status Variable ID |
| ... | |
| > | |
| > | |

The Host requests the Equipment to initiate a time driven trace operation.

The Equipment will send trace data using S6F1.

If TRID in S2F23 matches TRID of an existing trace, the existing trace operation is canceled, and replaced by the new one.

Up to four (4) separate TRIDs can be in operation simultaneously.

Within DSPER, must be a valid hour/minute/second format (hh 0-23, mm 0-59, ss 0-59), and cannot be 000000. The practical minimum value of DSPER is application dependent.

The Equipment will send the first S6F1 at one time period (DSPER * REPGSZ) after receiving S2F23.

If TOTSMPS is zero, then S2F23 is a request to cancel an existing trace. Any trace with the specified TRID is canceled.

REPGSZ minimum value is 1. REPGSZ may not be so large that S6F1 would be a multi-block message. Typical value is 1.

Several SVIDs can be specified if desired. You must not specify so many SVIDs that S6F1 becomes a multi-block message.

Normally, only Variables of class SV are used in this message. However, any VID of class DV, EC, or SV can be used.

For compatibility with older Host implementations, the Equipment allows the following alternative form for this message, using an array format:

```

S2F23 W                                * H->E
<L [5]
    <U4 TRID>                          * Trace ID
    <A 'hhmmss'>                      * DSPER - Data Sample Period
    <U4 TOTSMPL>                      * Total Number of Samples
    <U4 REPGSZ>                       * Reporting Group Size
    <U4 SVID SVID ...>                * Status Variable ID array
> .

```

4.2.23 S2F24 - Trace Initialize Acknowledge

```

S2F24                                * H<-E
    <B [1] TIAACK> .                * TIAACK - Trace Init. Ack. Code

```

Table 4-5 Trace Initialize Acknowledge

| TIAACK | Description |
|--------|---|
| 0x00 | Normal. Everything correct. |
| 0x03 | Invalid period. DSPER is incorrect. The Equipment does not start the trace. |

The Equipment does not signal an error if a Host error in S2F23 causes S6F1 to be multi-block. Instead, this Equipment sends multi-block S6F1 as requested by the Host.

This Equipment does not signal an error if the Host initiates more than four (4) simultaneous traces. The maximum number of traces supported depends on the size of the trace data, but is always at least 4.

4.2.24 S2F25 - Diagnostic Loopback Request

```

S2F25 W                                * H->E
    <B ABS> .                          * ABS - Any Binary String

```

The Host sends an arbitrary binary string to test operation of the link.

The Equipment never sends this message to the Host.

4.2.25 S2F26 - Diagnostic Loopback Data

S2F26 * H<-E
<B ABS> . * ABS - Any Binary String

The Equipment “echoes” back the binary data from the Host’s S2F25.

4.2.26 S2F27 - Initiate Process Request

S2F27 [W] * H->E
<L [3]
 <B LOC> * Location (always ‘0’)
 <A [1..12] PPID> * Process Program ID
 <L [1]
 <A [1..16] MID> * Lot ID
 >
> .

The Host sends this command to initiate a new lot for processing.

The Equipment ignores case when performing validity checks on the PPID string.

The Host may optionally set the W-Bit to “1” in S2F27. If so, the Equipment replies with S2F28.

PPID is the DOS 8.3 file name for the recipe. It should include the extension (RCP).

4.2.27 S2F28 - Initiate Process Acknowledge

S2F28 * H<-E
<B [1] CMDA> . * Command Ack. Code

Normal completion returns a zero (0) in CMDA.

A non-zero value for CMDA indicates that the Equipment has rejected the Remote Command.

Table 4-6 CMDA Values

| CMDA | Description |
|------|--|
| 0x00 | OK. All normal. |
| 0x01 | Invalid command. Equipment rejects command. |
| 0x02 | Cannot perform now. Equipment rejects command. |
| 0x40 | Control State is Local. Equipment rejects command. |
| 0x41 | Incorrect Process State for this command. Equipment rejects command. |
| 0x42 | Process program format error. |

4.2.28 S2F29 - Equipment Constant Namelist Request

```
S2F29 W * H->E
<L
  <U4 VID> * Equipment Constant ID
  ...
> .
```

The Host requests format descriptions for the specified equipment constants. Several VIDs can be specified if desired.

Only VIDs of class EC (i.e. equipment constants) can be used in this message.

If S2F29 contains a zero-length list, then the Equipment will report all variables of class EC, in order by VID.

4.2.29 S2F30 - Equipment Constant Namelist Reply

```
S2F30 * H<-E, Multiblock
<L
  <L [6]
    <U4 VID> * Equipment Constant ID
    <A ECNAME> * Equipment Constant Name
    <ECMIN> * ECV Minimum Value
    <ECMAX> * ECV Maximum Value
    <ECDEF> * ECV Default Value
    <A UNITS> * Units of Measure
  >
  ...
> .
```

The Equipment returns the equipment constant descriptions in the order requested in S2F29. If any VID specified in S2F29 is invalid, the corresponding List in S2F30 has the following error format:

```
<L> * Instead of L [6]
```

4.2.30 S2F31 - Date and Time Send

S2F31 W * H->E

* TIME - Date and Time

<A 'YYMMDDhhmmss'> . * If TIMEFORMAT = 0

- OR -

<A 'YYYYMMDDhhmmsscc'> . * If TIMEFORMAT = 1

The Host commands the Equipment to set its Date and Time base to the specified value.

When the Equipment receives a good S2F31, it sets its internal clock/calendar. When receiving S2F31, the Equipment will discard an invalid date or time. For example, if the date is good but the time is bad, the Equipment sets its date but not its time.

4.2.31 S2F32 - Date and Time Acknowledge

S2F32 * H<-E

<B [1] TIACK> . * TIACK - Acknowledge Code

Table 4-7 TIACK

| TIACK | Description |
|-------|-----------------------------|
| 0x00 | Normal. Everything correct. |
| 0x01 | Invalid Date and/or Time. |

4.2.32 S2F33 - Define Report

S2F33 W * H->E, Multiblock

<L [2]

<U4 DATAID> * DATAID

<L

<L [2]

<U4 RPTID> * Report ID

<L

<U4 VID> * Variable ID

...

>

>

...

>

> .

The Host specifies one or more Report IDs, and defines which Variables should be included in each report.

If S2F33 is multi-block, the Host may optionally send the S2F39/S2F40 Inquire/Grant Transaction before sending S2F33, but this Equipment does not require it.

The Equipment ignores DATAID.

If the Equipment already contains existing Report Definitions, then this message can be used to download additional definitions for RPTIDs not yet defined. The Host cannot download a new Report Definition for a RPTID for which a Report Definition already exists in the Equipment. Instead, to change a Report Definition the Host must first delete the old Report Definition and then send a new Report Definition for that RPTID.

The Host can delete selected report definitions and associated links in the Equipment by using the following specifications in S2F33:

```
...
<L [2]
<U4 RPTID>                * Report ID to delete
<L>
...
```

The Host can delete all report definitions and associated links in the Equipment by using the following special format:

```
S2F33 W                    * H->E
<L [2]
  <U4 DATAID>             * DATAID
  <L>
  > .
```

4.2.33 S2F34 - Define Report Acknowledge

```
S2F34                      * H<-E
  <B [1] DRACK> .          * DRACK - Acknowledge Code
```

Normally, DRACK is zero. Any non-zero DRACK indicates the Equipment has rejected the entire S2F33 message.

Table 4-8 DRACK Values

| DRACK | Description |
|-------|---|
| 0x00 | OK. |
| 0x02 | Denied. Invalid format. |
| 0x03 | Denied. At least one RPTID already defined. |
| 0x04 | Denied. At least one VID does not exist. |

4.2.34 S2F35 - Link Event Report

```
S2F35 W                                * H->E, Multiblock
<L [2]
    <U4 DATAID>                        * DATAID
    <L
        <L [2]
            <U4 CEID>                    * Collection Event ID
            <L
                <U4 RPTID>                * Report ID
                ...
            >
        >
    ...
    >
> .
```

The Host links Report Ids to selected Collection Event Ids. The Specified CEIDs are initialized to “disabled”. See [4.2.36 S2F37 - Enable/Disable Event Report](#) for enabling CEIDs.

If S2F35 is multi-block, the Host may optionally send the S2F39/S2F40 Inquire/Grant transaction before sending S2F35, but the Equipment does not require it.

The Equipment ignores DATAID.

The Host can eliminate all links for a CEID by sending the following format in S2F35 for that CEID:

```
...
<L [2]
<U4 CEID>                            * Collection Event ID
<L>
>
...
```

4.2.35 S2F36 - Link Event Report Acknowledge

S2F36 * H<-E
<B [1] LRACK> . * LRACK - Acknowledge Code

Normally, LRACK is zero. Any non-zero LRACK indicates the Equipment has rejected the entire S2F35 message.

Table 4-9 LRACK Values

| LRACK | Description |
|-------|---|
| 0x00 | OK. |
| 0x02 | Denied. Invalid format. |
| 0x03 | Denied. At least one CEID link already defined. |
| 0x04 | Denied. At least one CEID does not exist. |
| 0x05 | Denied. At least one RPTID does not exist. |
| Other | Equipment has rejected the S2F35 message. |

4.2.36 S2F37 - Enable/Disable Event Report

S2F37 W * H<-E
<L [2]
 <BOOLEAN CEED> * Coll. Event Enable
 <L
 <U4 CEID> * Collection Event ID
 ...
 >
> .

The Host enables reporting for a list of Collection Event IDs, or disables reporting for the list.

CEED is “True” to indicate Enabling, or “False” to indicate Disabling reporting for the specified CEIDs.

The Host can enable or disable all CEIDs by using the following special format:

S2F37 W * H->E
<L [2]
 <BOOLEAN CEED> * Coll. Event Enable
 <L>
> .

4.2.37 S2F38 - Enable/Disable Event Report Acknowledge

S2F38

* H<-E

<B [1] ERACK> .

* ERACK - Acknowledge Code

Table 4-10 describes the ERACK values. Normally, ERACK is zero. Any non-zero ERACK indicates the Equipment has rejected the entire S2F37 message.

Table 4-10 ERACK Values

| ERACK | Description |
|-------|---|
| 0x00 | OK. |
| 0x01 | Denied. At least one CEID does not exist. |

4.2.38 S2F39 - Multi-Block Inquire

S2F39 W

* H->E

<L [2]

<U4 DATAID>

* DATAID

<U4 DATALENGTH>

> .

The Host may send this Inquire/Grant transaction preceding any multiblock S2F33 or S2F35. For this Equipment, this Inquire/Grant is optional. The Equipment accepts it, but ignores it, commits no resources, and initiates no Conversation Timeout. The Equipment accepts multiblock S2F33 or S2F35 even if not preceded by the Inquire/Grant.

4.2.39 S2F40 - Multi-Block Grant

S2F40

* H<-E

<B [1] 00> .

* GRANT

The Equipment always sends GRANT value "0".

4.2.40 S2F41 - Remote Command with Parameters

```
S2F41 [W]                                *H->E
<L [2]
    <A RCMD>                             *Remote command string
    <L
        <L [2]
            <A CPNAME>                    *Command Parameter Name
            <CPVAL>                       *Command Parameter Value
        >
    ...
>
> .
```

The Host sends a command with parameters to the Equipment. If a command has no parameters, S2F41 has the following format:

```
S2F41 [W]                                * H->E
<L [2]
    <A RCMD>                             * Remote Command String
    <L>
> .
```

The Equipment ignores case when performing validity checks on the RCMD and CPNAME strings. The ASCII strings described in may be sent in any combination of upper and lower case characters.

Table 4-11 ERACK Values

| RCMD String | Function |
|-------------|---------------------------------------|
| “START” | Starts a Process Program. |
| “STOP” | Stops a running Process Program. |
| “ABORT” | Aborts a running Process Program. |
| “PAUSE” | Pauses a running Process Program. |
| “RESUME” | Resumes a paused Process Program. |
| “REMOTE” | Switches Equipment to “Remote” state. |
| “LOCAL” | Switches Equipment to “Local” state. |

The Host may optionally set the W-Bit to “1” in S2F41. If so, the Equipment replies with S2F42.

4.2.41 S2F42 - Remote Command Acknowledge

S2F42 * H<-E

<L [2]

<B [1] HCAACK> * Host Command Ack. Code

<L [n]

<L [2]

<A CPNAME> * Name of Parameter

<B [1] CPACK> * Cmd Param Ack Code

>

...

>

> .

Normal completion returns a zero (0) in HCAACK. The number of erroneous parameters “N” in S2F42 will be zero.

A non-zero value for HCAACK indicates that the Equipment has rejected the Remote Command. The number of erroneous parameters “n” can be zero or greater.

Table 4-12 HCAACK Values

| HCAACK | Description |
|--------|---|
| 0x00 | OK. All normal. |
| 0x01 | Invalid command. Equipment rejects command. |
| 0x02 | Cannot perform now. Equipment rejects command. Fluidmove is not in Run Window screen. |
| 0x03 | At least one parameter is invalid. Equipment rejects the command. |
| 0x40 | Control State is Local. Equipment rejects command. |
| 0x41 | Incorrect Process State for this command. Equipment rejects command. |
| 0x42 | Process Program contains an invalid format. Unable to load program. |



NOTE Fluidmove is currently not returning the HCAACK rejection codes (upon successful completion HCAACK will still be returned as zero). To indicate command rejection, the RCMD string will be echoed back to the Host with no HCAACK value.

Table 4-13 CPACK Values

| CPACK | Description |
|-------|---|
| 0x01 | Invalid parameter name (CPNAME). The CPNAME is not a valid parameter for this command. |
| 0x02 | Illegal parameter value (CPVAL). The parameter value is out of range. |
| 0x03 | Illegal format for parameter (CPVAL). The value for this parameter does not use the correct SECS-II data item type. |
| 0x40 | Duplicate parameter name. This parameter name occurred at least twice in the S2F41 command. |

4.2.42 S2F43 - Reset Spooling Streams and Functions

```

S2F43 W                                * H -> E
<L
    <L [2]
        <U1 STRID>                      * Message Stream
        <L
            <U1 FCNID>                  * Message Function
            ...
        >
    >
    ...
> .

```

The Host sends message to specify which messages the Equipment should spool in the event of a communications loss. When this message is received by the Equipment, all previous definitions of messages to spool are replaced.

The following version of S2F43 will enable spooling for all messages within the specified stream:

```

S2F43 W                                * H -> E
<L
    <L [2]
        <U1 STRID>                      * Message Stream
        <L>
    >
    ...
> .

```

To disable spooling of all messages, the following version of S2F43 may be used.

```

S2F43 W                                * H -> E
<L>.

```

Spooling is not allowed for even-numbered function messages (replies) or stream one messages.

4.2.43 S2F44 - Reset Spooling Acknowledge

The S2F44 message has two forms, depending on the return code in RSPACK. If there are no errors in S2F43, the format of S2F44 is as follows.

```
S2F44                                * H <- E

<L [2]
  <B [1] 00>                        * RSPACK
  <L>
> .
```

If S2F43 contains any errors, the Equipment will discard the entire S2F43, and return error information in S2F44, as follows:

```
S2F44                                * H <- E

<L [2]
  <B [1] 01>                        * RSPACK
  <L
    <L [3]
      <U1 STRID>                    * Msg String
      <B STRACK>                    * Stream Ack Code
      <L
        <U1 FCNID>                  * Msg Function
        ...
      >
    >
  ...
>
> .
```

The RSPACK code indicates whether the Equipment accepted the S2F43 message:

Table 4-14 RSPACK Values

| RSPACK | Description |
|--------|---|
| 0x00 | Acknowledge, spooling setup accepted. |
| 0x01 | Spooling setup rejected. At least one message requested as spool-able could not be made so. |

When errors exist in the request to set some messages as spool-able, the Equipment will return codes explaining the nature of the error. These codes are found in the STRACK data item.

Table 4-15 STRACK Values

| STRACK | Description |
|--------|---|
| 0x01 | Spooling not allowed for this stream. Spooling is never allowed for stream one. |
| 0x04 | Requested message is a secondary message and therefore ineligible for spooling. |

4.2.44 S2F45 - Define Variable Limits Attributes

```

S2F45 W                                * H -> E
<L [2]
  <U4 DATAID>
  <L
    <L [2]
      <U4 VID>                        * Variable ID
      <L
        <L [2]
          <B [1] LIMITID>
          <L [2]
            <UPPERDB>
            <LOWERDB>
          >
        >
      >
    ...
  >
  ...
>
> .

```

With this message, the Host defines a set of limits for a single variable or a series of variables.

DATAID may be any value, and is ignored by the Equipment.

VID must specify the Variable ID of a Variable for which Limits Monitoring is allowed.

LIMITID must be between 0x01 and 0x07. It specifies one of the seven allowable limits for the variable.

UPPERDB and LOWERDB must match the value format of the specified variable.

The Host may undefine all limits for all VIDs:

```
S2F45 W                                * H -> E

<L [2]
    <U4 DATAID>
    <L>
> .
```

The Host may undefine all limits for a specific VID:

```
S2F45 W                                * H -> E

<L [2]
    <U4 DATAID>
    <L
        <L [2]
            <U4 VID>
            <L>
        >
        ...
    >
> .
```

The Host may undefine a specific limit for a specific VID:

```
S2F45 W                                * H -> E

<L [2]
    <U4 DATAID>
    <L
        <L [2]
            <U4 VID>
            <L
                <L [2]
                    <B [1] LIMITID>
                    <L>
                >
            >
            ...
        >
        ...
    >
> .
```

4.2.45 S2F46 - Variable Limit Attribute Acknowledge

This message acknowledges the successful setting of limits as defined in the Host-generated S2F45.

```
S4F46                                * H <- E

<L [2]
  <B [1]                             * VLAACK
  <L>
> .
```

If any of the limits proposed in S4F45 are invalid, all limits for all variables in this message are rejected. The following message is sent in the event of an error:

```
S4F46                                * H <- E

<L [2]
  <B [1] VLAACK>
  <L
    <L [3]
      <U4 VID>
      <B [1] 0x00>          * LVACK
      <L [2]
        <B [1] LIMITID>
        <B [1] LIMITACK>
      >
    >
  ...
> .
```

Data item VLAACK reports to the Host the status of the request to define limits for the requested variables.

Table 4-16 VLAACK Values

| VLAACK | Description |
|--------|-----------------------------------|
| 0x00 | OK. Limits successfully defined. |
| 0x01 | Limit attribute definition error. |

The LVACK data item gives information to the Host about the status of setting a specific variable when the request to set it is unsuccessful.

Table 4-17 LVACK Values

| LIMIT-ACK | Description |
|------------------|---|
| 0x01 | Requested variable does not exist. |
| 0x02 | Variable is not eligible for limits definition. |
| 0x03 | Requested variable was repeated in request message. |
| 0x04 | Error in setting limit due to reason specified in LIMITACK. |

The LIMITACK data item indicates the status of an attempt to set an individual limit for a variable.

Table 4-18 VLACK Values

| VLACK | Description |
|--------------|--|
| 0x01 | LIMITID does not exist. |
| 0x02 | Requested UPPERDB is greater than LIMITMAX. |
| 0x03 | Requested LOWERDB is lower than LIMITMIN. |
| 0x04 | UPPERDB < LOWERDB. |
| 0x05 | Illegal format specified for UPPERDB or LOWERDB. |

4.2.46 S2F47 - Variable Limit Attribute Request

```
S2F47 W * H -> E
<L
    <U4 VID> * Requested Variable ID
    ...
> .
```

The Host sends this message to the Equipment to request the limits attributes for specific variables. The Host may request the limits attributes for all defined variables with the following message.

```
S2F47 W * H -> E
<L> .
```

In response to this message, the Equipment reports all limits attributes for all variables. If a variable is eligible for limits monitoring, but does not have any limits defined, it is not reported.

4.2.47 S2F48 - Variable Limit Attributes Send

```
S2F48 * H <- E
<L
    <L [2]
        <U4 VID> * Variable ID
        <L [4]
            <A UNITS> * Units of Measure
            <LIMITMIN> * Minimum Limit
            <LIMITMAX> * Maximum Limit
            <L * Up to 7 Possible
                <L [3]
                    <B [1] LIMITID> * Limit ID
                    <UPPERDB> * Upper Deadband
                    <LOWERDB> * Lower Deadband
                >
            ...
        >
    >
> .
```

The Equipment sends this message in response to a Host S2F47 and reports the characteristics of limits for specified variables. In response to a request from the Host for all limits for all variables, only variables with limits defined are reported. If the Host requests specific variables which are not eligible for limits monitoring, the following message will be reported for that variable:

```

S2F48                                * H <- E

<L
    <L [2]
        <U4 VID>                    * Variable ID
        <L>                        * Not eligible for Limits
    >
    ...
> .

```

If the Host requests the limits for a specific variable which is eligible for limits monitoring but does not have any limits defined, this variable will be reported as follows:

```

S2F48                                * H <- E

<L
    <L [2]
        <U4 VID>                    * Variable ID
        <L [4]
            <A UNITS>                * Units of Measure
            <LIMITMIN>               * Minimum Limit
            <LIMITMAX>               * Maximum Limit
            <L>                      * No Limits Defined
        >
    >
    ...
> .

```

4.2.48 S5F1 - Alarm Report

| | |
|--------------------------|---------------------------|
| S5F1 [W] | * H<-E |
| <L [3] | |
| <B [1] ALCD> Severity | * ALCD - Alarm On/Off and |
| <U4 ALID> | * ALID - Alarm ID |
| <A [40] ALTX> | * ALTX - Alarm Text |
| > . | |

This message is the “normal” message that the Equipment uses to report alarms. In order for this message to be used, the equipment constant “ConfigAlarms” must be set to “0”. If “ConfigAlarms” is set to “0”, the Equipment sends S5F1 instead of the normal S5F73 Alarm Notification Send. The Equipment reports that an alarm condition has changed.

ALID identifies the Alarm.

The high-order bit of ALCD will be “1” if this alarm is currently On (Unsafe), or “0” if it is currently Off (Safe). The low-order seven bits of ALCD contain the severity code for this alarm.

ALTX contains up to 40 bytes of Alarm Text. Refer to [Appendix C](#) for a table of possible alarms.

Equipment constant “WBitS5” controls whether the Equipment sends S5F1 with W-Bit “1” (Reply Expected) or “0” (No Reply Expected).

4.2.49 S5F2 - Alarm Acknowledge

| | |
|-------------|----------------------------|
| S5F2 | * H->E |
| <B [1] 00>. | * ACK5 - Alarm Acknowledge |

The Host acknowledges the Alarm Report. This Equipment ignores the ACKC5.

4.2.50 S5F3 - Enable/Disable Alarm Send

S5F3 [W] * H->E

<L [2]

<B [1] ALED> * ALED - Alarm Enable/Disable
Code

<U4 ALID> * ALID - Alarm ID

> .

The Host commands the Equipment to enable or disable (depending on ALED) reporting for the specified Alarm ID in S5F1, S5F8, S5F71, and S5F73.

Table 4-19 ALED Values

| ALED | Description |
|------|------------------------|
| 0x80 | Enable sending alarm. |
| 0x00 | Disable sending alarm. |

The following special format can be used to enable or disable all ALIDs.

S5F3 [W] * H->E

<L [2]

<B [1] ALED> * ALED - Alarm Enable/Disable
Code

<U4> * ALID - Alarm ID

> .

The Host may optionally set the W-Bit to “1” in S5F3. If so, the Equipment replies with S5F4.

4.2.51 S5F4 - Enable/Disable Alarm Acknowledge

S5F4 * H<-E

<B [1] ACKC5> . * ACKC5 - Acknowledge Code

Table 4-20 ACKC5 Values

| ACKC5 | Description |
|-------|-----------------------------|
| 0x00 | Normal. Everything correct. |
| 0x01 | Invalid ALID. |

4.2.52 S5F5 - List Alarms Request

S5F5 W * H->E
<U4 ALID ...> . * Alarm ID Array

The Host requests the Equipment to send the current status of the specified Alarm IDs.

The Host can use the following special format to request the status of all Alarm IDs:

S5F5 W
<U4> . * ALID

4.2.53 S5F6 - List Alarm Data

S5F6 * H<-E, Multiblock
<L
 <L [3]
 <B [1] ALCD> * ALCD - Alarm On/Off and
 Severity Code
 <U4 ALID> * Alarm ID
 <A ALTX> * ALTX - Alarm Text
 >
 ...
 > .

The high-order bit of ALCD will be “1” if this alarm is currently On (Unsafe), or “0” if it is currently Off (Safe). The low-order seven bits of ALCD contain the severity code for this alarm.

For any invalid ALID specified in S5F5, the corresponding entry in S5F6 has the following special error format:

<L [3]
 * ALCD - Alarm On/Off and
 Severity Code
 <U4 ALID> * Alarm ID
 <A> * ALTX - Alarm Text
 >

If S5F5 specified all alarms, S5F6 reports alarms in order by alarm ID.

4.2.54 S5F7 - List Enabled Alarms Request

S5F7 W . * H->E

The Host requests the Equipment to send the current status of all Alarm IDs which are currently enabled (refer to [4.2.50 S5F3 - Enable/Disable Alarm Send](#)).

4.2.55 S5F8 - List Enabled Alarm Data

S5F8 * H<-E, Multiblock
<L
 <L [3]
 <B [1] ALCD> * ALCD - Alarm On/Off and
 Severity Code
 <U4 ALID> * Alarm ID
 <A ALTX> * ALTX - Alarm Text
 >
 ...
 > .

The high-order bit of ALCD will be “1” if this alarm is currently On (Unsafe), or “0” if it is currently Off (Safe). The low-order seven bits of ALCD contain the severity code for this alarm.

S5F8 contains only those ALIDs which are currently enabled for reporting (refer to [4.2.50 S5F3 - Enable/Disable Alarm Send](#)).

S5F8 reports alarms in order by Alarm ID.

4.2.56 S5F71 - Alarm Report Block Send

```
S5F71 [W] * H<-E
<L [2]
    <U1 0> * ALPY Alarm Priority
    <L [1]
        <L [4]
            <U4 ALID> * ALID - Alarm ID
            <BOOLEAN ASTAT> * T = Alarm On, F = Alarm Off
            <U4 ASER> * ASER Alarm Serial Number
            <A [16] 'YYYYMMDDhhmmsscc'> * CLOCK
        >
    >
> .
```



NOTE

This message is provided only for compatibility with Host computers which support an older version of GEM.

If the equipment constant “ConfigAlarms” is set to “1”, the Equipment sends S5F71 instead of the normal S5F1 Alarm Notification Send.

The Equipment reports that an alarm condition has changed.

ALID identifies the Alarm.

ASTAT value is “True” (Non-zero) if this alarm is currently On (Unsafe), or “False” (Zero) if it is currently Off (Safe).

ASER (Alarm Serial Number) is assigned by the Equipment. Its value begins at “1” and is incremented by 1 for each alarm reported.

ALPY (Alarm Priority) is always zero.

CLOCK indicates the date and time of the alarm change.

Equipment constant “Wbits5” controls whether the Equipment sends S5F71 with W-bit “1” (Reply Expected) or “0” (No Reply Expected).

4.2.57 S5F72 - Alarm Report Block Acknowledge

S5F72 * H->E
<L> .

The Host acknowledges Alarm Report. This Equipment ignores the data portion of S5F72.

4.2.58 S5F73 - Alarm Report Block Acknowledge

S5F73 [W] * H<-E
<L [3]
 <U4 ALID> * ALID - Alarm ID
 <BOOLEAN ASTAT> * T = Alarm On, F = Alarm Off
 <A [16] 'YYYYMMDDhhmmsscc'> * TIMESTAMP
 > .



NOTE

This message is provided only for compatibility with older Host computers which support GEM 3.1 (refer to [1.9.3 GEM Configuration](#)).

In order for this message to be used, the equipment constant “ConfigAlarms” must be set to “2”.

The Equipment reports that an alarm condition has changed.

ALID identifies the Alarm.

ASTAT value is “True” (Non-zero) if this alarm is currently On (Unsafe), or “False” (Zero) if it is currently Off (Safe).

TIMESTAMP indicates the date and time of the alarm change.

Equipment constant “WBitS5” controls whether the Equipment sends S5F73 with W-Bit “1” (Reply Expected) or “0” (No Reply Expected).

4.2.59 S5F74 - Alarm Notification Acknowledge

S5F74 * H->E
 <B [1] ACK5> .

The Host acknowledges Alarm Report. This Equipment ignores ACKC5.

4.2.60 S6F1 - Trace Data Send

| | |
|------------------------|---|
| S6F1 [W] | * H<-E |
| <L [4] | |
| <U4 TRID> | * Trace ID |
| <U4 SMPLN> | * Sample Number * STIME - Sample Date/Time |
| <A 'YYMMDDhhmmss'> | * If TIMEFORMAT = 0 |
| • | OR - |
| <A 'YYYYMMDDhhmmsscc'> | * If TIMEFORMAT = 1 |
| <L | |
| <V> | * Variable Value |
| ... | |
| > | |
| >. | |

The Equipment sends time driven trace data, as previously requested by the Host using S2F23.

TRID is the Trace ID as initiated by the Host.

SMPLN is the sample number. The first sample is "1", the next "2", and so on. If REPGSZ is greater than 1, SMPLN is the number of the last sample contained in this S6F1.

STIME is the date and time at which this sample was taken. If REPGSZ is greater than 1, STIME is the date and time of the last sample contained in this S6F1.

The V's appear in the same order they were specified in S2F23.

S6F1 is normally single block. However, if the Host erroneously initiates a multiblock trace using an incorrect S2F23, S6F1 may be multi-block. The Equipment never sends an Inquire/Grant message preceding S6F1.

Equipment constant "WBitS6" controls whether the Equipment sends S6F1 with W-Bit "1" (Reply Expected) or "0" (No Reply Expected).

S6F2 * H->E

The Host acknowledges the data. The Equipment ignores ACKC6.

S6F3 [W]

<L [3]

* DATAID

* Collection Event ID

<L [2]

* DSID=RPTID Report ID

* Variable ID

* Variable Value

...

 \succ γ

...

 \geq
$$> .$$


The Equipment generates a value for DATAID to uniquely identify this Conversation. If S6F3 is multiblock, the Equipment first sends the S6F5/S6F6 Inquire/Grant transaction, and DATAID in S6F3 will match DATAID in S6F5.

If the CEID is enabled, but no Reports are linked to this CEID, S6F3 has the following special format:

| | |
|-------------|-----------------------|
| S6F3 [W] | * H<-E |
| <L [3] | |
| <U4 DATAID> | * DATAID |
| <U4 CEID> | * Collection Event ID |
| <L> | |
| > . | |

Equipment constant “Wbits6” controls whether the Equipment sends S6F3 with W-Bit “1” (Reply Expected) or “0” (No Reply Expected).

4.2.63 S6F4 - Annotated Event Report Acknowledge

| | |
|--------------|---------|
| S6F4 | * H->E |
| <B [1] 00> . | * ACKC6 |

The Host acknowledges the Event Report. The Equipment ignores ACKC6.

4.2.64 S6F5 - Multi-Block Data Send Inquire

| | |
|-----------------|----------|
| S6F5 W | * H<-E |
| <L [2] | |
| <U4 DATAID> | * DATAID |
| <U4 DATALENGTH> | |
| > . | |

The Equipment sends this Inquire/Grant transaction preceding any multiblock S6F3, S6F9, S6F11, or S6F13.

The DATAID specified here will appear in the following S6F3, S6F9, S6F11, S6F13.

DATALLENGTH value is the total number of text bytes (excluding SECS block headers) in the following S6F3, S6F9, S6F11, or S6F13 message.

4.2.65 S6F6 - Multi-Block Grant

S6F6

* H->E

<B [1] GRANT6> .

* GRANT6

The Host grants permission for the Equipment to send a multi-block Event Report.

Table 4-21 Multi-Block Event Values

| GRANT6 | Description |
|--------|---|
| 0x00 | Normal. Permission granted. |
| Other | Permission not granted. The Equipment will not send the following S6F3, S6F9, S6F11, or S6F13, and will discard the data. |

4.2.66 S6F9 - Event Report



NOTE

This message is provided only for compatibility with older Host computers which do not support GEM. (Refer to [1.9.3 GEM Configuration](#).)

S6F9 [W]

* H<-E, Multiblock

<L [4]

 $\langle B \ [1] \ 00 \rangle$

* PFCD (always zero)

&ltU4 DATAID>

* DATAID

<U4 CEID>

* Collection Event ID

<L

<L [2]

<U4 DSID>

* DSID=RPTID Report ID

 $\leq L$ $\langle V \rangle$

* Variable Value

...

 \triangleright \triangleright

...

 \geq \succ

If the equipment constant “ConfigEvents” is set to “0”, the Equipment sends S6F9 instead of the normal S6F11 Event Report.

An Event Report will be sent if a Collection Event has occurred at the Equipment. The Host has enabled Event Reporting for this CEID (refer to [4.2.36 S2F37 - Enable/Disable Event Report](#)). The Host has set the equipment constant “RpType” to “False” (normal report format desired). The Equipment sends one or more Event Reports which the Host has previously linked to that CEID (refer to [4.2.34 S2F35 - Link Event Report](#)). Each report contains specific Variables which the Host has previously defined for that Report (refer to [4.2.32 S2F33 - Define Report](#)).

The Equipment generates a value for DATAID to uniquely identify this Conversation. If S6F9 is multiblock, the Equipment first sends the S6F5/S6F6 Inquire/Grant transaction, and the DATAID in S6F9 will match DATAID in S6F5.

If the CEID is enabled, but no Reports are linked to this CEID, S6F9 has the following special format:

```

S6F9 [W]                                * H<-E
<L [4]
    <B [1] 00>                          * PFCD (always zero)
    <U4 DATAID>                        * DATAID
    <U4 CEID>                          * Collection Event ID
    <L>
    > .

```

Equipment constant “WBitS6” controls whether the Equipment sends S6F9 with W-Bit “1” (Reply Expected) or “0” (No Reply Expected).

4.2.67 S6F10 - Event Report Acknowledge

```

S6F10 * H->E
    <B [1] 00> .                        * ACKC6

```

The Host acknowledges the Event Report. The Equipment ignores ACKC6.

4.2.68 S6F11 - Event Report Send

```

S6F11 W                                * H<-E
<L [3]
    <U4 DATAID>                        * DATAID
    <U4 CEID>                          * Collection Event ID
    <L
        <L [2]
            <U4 RPTID>                  * Report ID
            <L
                <V>                    * Variable Value
                ...
                >
            >
        ...
    > .

```

This message is the “normal” message that the Equipment uses to report events. In order for this message to be used, the equipment constant “ConfigEvents” must be set to “1”.

An Event Report will be sent if a Collection Event has occurred at the Equipment. The Host has enabled Event Reporting for this CEID (refer to [4.2.36 S2F37 - Enable/Disable Event Report](#)). The Host has set the equipment constant “RpType” to “False” (normal report format desired). The Equipment sends one or more Event Reports which the Host has previously linked to that CEID (refer to [4.2.34 S2F35 - Link Event Report](#)). Each report contains specific Variables which the Host has previously defined for that Report (refer to [4.2.32 S2F33 - Define Report](#)).

The Equipment generates a value for DATAID to uniquely identify this Conversation. If S6F11 is multiblock, the Equipment first sends the S6F5/S6F6 Inquire/Grant transaction, and the DATAID in S6F11 will match DATAID in S6F5.

If the CEID is enabled, but no Reports are linked to this CEID, S6F11 has the following special format:

| | |
|-------------|-----------------------|
| S6F11 W | * H<-E |
| <L [3] | |
| <U4 DATAID> | * DATAID |
| <U4 CEID> | * Collection Event ID |
| <L> | |
| > . | |

4.2.69 S6F12 - Event Report Acknowledge

| | |
|--------------|---------|
| S6F12 | * H->E |
| <B [1] 00> . | * ACKC6 |

The Host acknowledges the Event Report. The Equipment ignores ACKC6.

4.2.70 S6F13 - Annotated Event Report Send

```
S6F13 W                                * H<-E, Multiblock

<L [3]
  <U4 DATAID>                         * DATAID
  <U4 CEID>                             * Collection Event ID
  <L
    <L [2]
      <U4 RPTID>                       * Report ID
      <L
        <L [2]
          <U4 VID>                     * Variable ID
          <V>                         * Variable Value
        >
      ...
    >
  >
  ...
> .
```

**NOTE**

This message is provided only for compatibility with older Host computers which support older versions of GEM (refer to [1.9.3 GEM Configuration](#)).

An Event Report will be sent if a Collection Event has occurred at the Equipment. The Host has enabled Event Reporting for this CEID (refer to [4.2.36 S2F37 - Enable/Disable Event Report](#)). The Host has set the equipment constant “RpType” to “True” (annotated report format desired). The equipment constant “ConfigEvents” has been set to 1. The Equipment sends one or more Event Reports which the Host has previously linked to that CEID (refer to [4.2.34 S2F35 - Link Event Report](#)). Each report contains specific Variables which the Host has previously defined for that Report (refer to [4.2.32 S2F33 - Define Report](#)).

The Equipment generates a value for DATAID to uniquely identify this Conversation. If S6F11 is multiblock, the Equipment first sends the S6F5/S6F6 Inquire/Grant transaction, and the DATAID in S6F11 will match DATAID in S6F5.

If the CEID is enabled, but no Reports are linked to this CEID, S6F11 has the following special format:

| | |
|-------------|-----------------------|
| S6F13 W | * H<-E |
| <L [3] | |
| <U4 DATAID> | * DATAID |
| <U4 CEID> | * Collection Event ID |
| <L> | |
| > . | |

4.2.71 S6F14 - Annotated Event Report Acknowledge

| | |
|--------------|---------|
| S6F14 | * H->E |
| <B [1] 00> . | * ACKC6 |

The Host acknowledges the Event Report. The Equipment ignore ACKC6.

4.2.72 S6F15 - Event Report Request

| | |
|-------------|-----------------------|
| S6F15 W | * H->E |
| <U4 CEID> . | * Collection Event ID |

The Host sends the CEID of interest, requesting normal format reports.

4.2.73 S6F16 - Event Report Data

| | |
|-------------|-----------------------|
| S6F16 | * H<-E, Multiblock |
| <L [3] | |
| <U4 DATAID> | * DATAID |
| <U4 CEID> | * Collection Event ID |
| <L | |
| <L [2] | |
| <U4 RPTID> | * Report ID |
| <L | |
| <V> | * Variable Value |
| ... | |
| > | |
| > | |
| ... | |
| > | |
| > . | |

The Equipment sends one or more Event Reports which the Host has previously linked to that CEID (refer to [4.2.34 S2F35 - Link Event Report](#)). Each report contains specific Variables which the Host has previously defined for that Report (refer to [4.2.32 S2F33 - Define Report](#)).

This message occurs whether or not the Host has enabled Event Reporting for this CEID (refer to [4.2.36 S2F37 - Enable/Disable Event Report](#)), and regardless of how the Host has set the equipment constant “RpType” (report format).

The Equipment generates a meaningless value for DATAID.

CEID contains the CEID specified in S6F15.

If the CEID specified in S6F15 is invalid, or if no reports are linked to this CEID, this message has the following special format:

| | |
|-------------|-----------------------|
| S6F16 | * H<-E, Multiblock |
| <L [3] | |
| <U4 DATAID> | * DATAID |
| <U4 CEID> | * Collection Event ID |
| <L> | |
| > . | |

4.2.74 S6F17 - Annotated Event Report Request

S6F17 W * H->E
<U4 CEID> . * Collection Event ID

The Host sends the CEID of interest, requesting annotated format reports.

4.2.75 S6F18 - Annotated Event Report Data

S6F18 * H<-E
<L [3]
 <U4 DATAID> * DATAID
 <U4 CEID> * Collection Event ID
 <L
 <L [2]
 <U4 RPTID> * Report ID
 <L
 <L [2]
 <U4 VID> * Variable ID
 <V> * Variable Value
 >
 ...
 >
 >
 ...
 >
> .

The Equipment sends one or more Event Reports which the Host has previously linked to that CEID (refer to [4.2.34 S2F35 - Link Event Report](#)). Each report contains specific Variables which the Host has previously defined for that Report (refer to [4.2.32 S2F33 - Define Report](#)).

This message occurs whether or not the Host has enabled Event Reporting for this CEID (refer to [4.2.36 S2F37 - Enable/Disable Event Report](#)), and regardless of how the Host has set the equipment constant “RpType” (report format).

The Equipment generates a meaningless value for DATAID.

CEID contains the CEID specified in S6F17.

If the CEID specified in S6F17 is invalid, or if no reports are linked to this CEID, this message has the following format:

| | |
|-------------|-----------------------|
| S6F18 | * H<-E, Multiblock |
| <L [3] | |
| <U4 DATAID> | * DATAID |
| <U4 CEID> | * Collection Event ID |
| <L> | |
| > . | |

4.2.76 S6F19 - Request Report Request

| | |
|--------------|-------------|
| S6F19 W | * H->E |
| <U4 RPTID> . | * Report ID |

The Host requests a Report for the specified RPTID.

4.2.77 S6F20 - Request Report Data

| | |
|-------|--------------------|
| S6F20 | * H<-E, Multiblock |
| <L | |
| <V> | |
| ... | |
| > . | |

The Equipment sends the Report.

If no report is defined for the RPTID in S6F19, S6F20 has the following special error format:

| | |
|-------|--------|
| S6F20 | * H<-E |
| <L> . | |

4.2.78 S6F21 - Request Annotated Report Request

| | |
|--------------|-------------|
| S6F21 W | * H->E |
| <U4 RPTID> . | * Report ID |

The Host requests an Annotated Report for the specified RPTID.

4.2.79 S6F22 - Request Annotated Report Data

```
S6F22                                * H<-E, Multiblock
<L
    <L [2]
        <U4 VID>                      * VID - Variable ID
        <V>
    >
    ...
> .
```

The Equipment sends the Annotated Report.

If no Report is defined for the RPTID in S6F21, S6F22 has the following special error format:

```
S6F22                                * H<-E
<L> .
```

4.2.80 S6F23 - Request Spooled Data

```
S6F23 W                                * H -> E
    <U1 RSDC> .
```

The Host sends this message to start the transfer of spooled messages from the Equipment to the Host, or to delete the contents of the spool file, depending on the value of RSDC.

When the Host requests the spooled messages (RSDC is zero), the Equipment will send messages according to EC “MaxSpoolTransmit”. All messages are sent from oldest to newest, and once the message is successfully sent, it is removed from the spool. If MaxSpoolTransmit is zero, all messages will be sent one at a time until the last message has been delivered. If MaxSpoolTransmit is set to a non-zero value, the Equipment will send the lesser of MaxSpoolTransmit or messages left in spool. If in this case the Equipment sends MaxSpoolTransmit messages, and messages remain in the spool, the Equipment will wait for another S6F23 to deliver the next messages.

If the Host sends S6F23 with RSDC set to one, this will be interpreted by the Equipment as a request to purge the spool.

Table 4-22 RSDC

| RSDC | Description |
|------|----------------------------|
| 0 | Transmit spooled messages. |
| 1 | Purge spooled messages. |

4.2.81 S6F24 - Request Spooled Data Acknowledge

S6F24 * H <- E
<B [1] RSDA> .

Equipment acknowledges the Host's request to either purge spooled messages or send spooled messages to the Host.

Table 4-23 RSDA Values

| RSDA | Description |
|------|---|
| 0x00 | Normal. Equipment will start to send spooled data or optionally purge the spool. Action performed will depend on value for RSDC in S6F23. |
| 0x02 | Denied. Spooled data does not exist. |

4.2.82 S7F1 - Process Program Load Inquire

S7F1 W * H<->E
<L [2]
 <A PPID> * Process Program ID
 <U4 LENGTH> * Length of text
> .

PPID should be the recipe file name and should include the extension RCP.

The Sender requests permission to send a Process Program. The Process Program may be either a Load Recipe or Process Recipe.

The Equipment always sends this Inquire/Grant transaction before sending any multi-block S7F3. LENGTH specifies the number of bytes in the following S7F3 message, excluding SECS-I block-length bytes, block headers, and checksums.

For Host-to-Equipment transfers, this Inquire/Grant is optional. The Equipment accepts it, but ignores it, commits no resources, and initiates no Conversation timeout. The Equipment will accept a multi-block S7F3 even if not preceded by the Inquire/Grant.

4.2.83 S7F2 - Process Program Load Grant

S7F2 * H<->E

<B [1] 00> .

* PPGNT

The Receiver grants permission to send a Process Program. The Receiver sends PPGNT value 0x00 to indicate it will accept the Process Program, and the Sender should send S7F3. If the Receiver sends any other value in S7F2, it refuses the Grant, and the Sender should not send S7F3.

The Process Program may be either a Load Recipe, Process Recipe, or Parameter Table.

When the Equipment sends S7F2, PPGNT may contain the following codes:

Table 4-24 S7F2 PPGNT Values

| PPGNT | Description |
|-------|-----------------------------|
| 0x00 | Normal. Permission granted. |

When the Host sends S7F2, the Equipment interprets PPGNT as follows:

Table 4-25 S7F2 PPGNT Interpretations

| PPGNT | Description |
|-------|---|
| 0x00 | Normal. The Equipment sends S7F3. |
| Other | Refusal. The Equipment does not send S7F3 and the upload operation fails. |

4.2.84 S7F3 - Process Program Send

S7F3 W

* H<->E, Multiblock

<L [2]

<A PPID>

* PPID - Process Program ID

<A PPBODY>

* PPBODY – Process Program
Body

PPID is the recipe file name and should include the extension RCP.

Send an Unformatted Process Program. Before sending a multi-block S7F3, the Equipment always first sends the S7F1/S7F2 Inquire/Grant transaction. The Host may send S7F1/S7F2 before sending S7F3. The Equipment accepts it, but does not require it.

4.2.85 S7F4 - Process Program Acknowledge

S7F4 * H<->E
<B [1] ACKC7> . * ACKC7

The Receiver acknowledges the receipt of the Process Program. If the transfer succeeds, ACKC7 will contain 0x00, and the Receiver stores the new Process Program into its library. Any previous Process Program with the same PPID is deleted. Any non-zero ACKC7 indicates refusal of the Process Program.

When the Equipment sends S7F4, ACKC7 may contain the following codes. Any non-zero code indicates that S7F3 has not changed the Equipment Library.

Table 4-26 S7F4 ACKC7 Values

| ACKC7 | Description |
|-------|---|
| 0x00 | Normal. Process Program Accepted and stored into Library. |
| 0x01 | Permission Not Granted. Insufficient space in Library. |
| 0x40 | Process Program Format Error. |
| 0x41 | Process Program Data Error (Verify Failed). |

When the Host sends S7F4, the Equipment interprets ACKC7 as follows:

Table 4-27 S7F4 ACKC7 Interpretations

| ACKC7 | Description |
|-------|--------------------------------------|
| 0x00 | Normal. |
| Other | Refusal. The upload operation fails. |

4.2.86 S7F5 - Process Program Request

S7F5 W * H<->E
<A PPID> . * Process Program ID

PPID is the recipe file name and should include the extension RCP.

Request the other end of the link to send a specified Process Program from its library.

4.2.87 S7F6 - Process Program Data

| | |
|------------|---------------------------------|
| S7F6 | * H<->E, Multiblock |
| <L [2] | |
| <A PPID> | * Process Program ID |
| <A PPBODY> | * PPBODY - Process Program Body |

PPID is the recipe file name and should include the extension RCP.

Send the requested Process Program.

If the specified PPID is not found in the library, S7F6 has the following special format:

| | |
|-------|---------|
| S7F6 | * H<->E |
| <L> . | |

If the Equipment receives S7F6 and cannot store the Process Program in its library, the CEID BadDownload is signaled, with PPChangeName set to the PPID of the requested Process Program. This occurs if the received S7F6 is of the special “not found” form, if the S7F6 message is not in the expected format, or if an error is detected in PPBODY (for example, a parameter out of range).

4.2.88 S7F17 - Process Program Delete

| | |
|----------|----------------------|
| S7F17 W | * H->E |
| <L | |
| <A PPID> | * Process Program ID |
| ... | |
| > . | |

PPID is the recipe file name and should include the extension RCP.

The Host deletes one or more Process Programs from the Equipment library.

If S7F17 contains a zero-length List, the entire library is deleted.

4.2.89 S7F18 - Process Program Delete Acknowledge

S7F18 * H<-E
<B [1] ACKC7> . * ACKC7 - Acknowledge Code

The Equipment acknowledges the Process Program delete.

Table 4-28 S7F18 ACKC7 Values

| ACKC7 | Description |
|-------|--|
| 0x00 | Normal. All specified PPIDs have been deleted. |
| 0x04 | Error: At least one specified PPID was not found. However, correct PPIDs have been deleted from the Equipment Library. |

4.2.90 S7F19 - Process Program Directory Request

S7F19 W . * H->E

The PPIDs returned are the recipe file names and should include the extension RCP.

The Host requests a directory of the Process Programs currently in the Equipment library.

4.2.91 S7F20 - Process Program Directory

S7F20 * H<-E
<L
 <A PPID> * Process Program ID
 ...
 > .

The Equipment sends a directory of its Process Program library. If the library is empty, the list will be zero length.

4.2.92 S9F1 - Unrecognized Device ID

S9F1 * H<-E
<B [10] MHEAD> . * MHEAD - Header of bad msg

4.2.93 S9F3 - Unrecognized Stream

S9F3

<B [10] MHEAD> .

* H<-E

* MHEAD - Header of bad msg

4.2.94 S9F5 - Unrecognized Function

S9F5

<B [10] MHEAD> .

* H<-E

* MHEAD - Header of bad msg

4.2.95 S9F7 Invalid Data

S9F7

<B [10] MHEAD> .

* H<-E

* MHEAD - Header of bad msg

4.2.96 S9F9 Transaction Timer Timeout

S9F9

<B [10] SHEAD> .

* H<-E

* SHEAD - Stored Header

4.2.97 S9F11 - Data Too Long

S9F11

<B [10] MHEAD> .

* H<-E

* MHEAD - Header of bad msg

4.2.98 S10F1 - Terminal Request

S10F1 [W]

<L [2]

* H<-E

<B [1] TID>

* Terminal ID

<A [160] TEXT>

* Message Text

 \geq

The Equipment sends text to the Host. This Equipment may send the following values for TID:

Table 4-29 S10F1 TID Values

| TID | Description |
|------|--------------|
| 0x00 | Always sent. |

Equipment constant “WBitS10” controls whether the Equipment sends S10F1 with W-Bit “1” (Reply Expected) or “0” (No Reply Expected).

4.2.99 S10F2 - Terminal Request Acknowledge

S10F2 * H->E
<B [1] ACKC10> . * Acknowledge Code

The Host may send the following values for ACKC10:

Table 4-30 S10F2 ACKC10 Values

| ACKC10 | Description |
|--------|---------------------------------|
| 0x00 | Normal. Host accepts the S10F1. |
| Other | Host rejects the S10F1. |

4.2.100 S10F3 - Terminal Display, Single

S10F3 [W] * H->E
<L [2]
<B [1] TID> * Terminal ID
<A [160] TEXT> * Message Text
> .

The Host sends to the Equipment. The Equipment interprets TID as follows:

Table 4-31 S10F3 TID Values

| TID | Description |
|-----|---|
| Any | Equipment displays the text on its CRT. |

The Host may optionally set the W-Bit to “1” in S10F3. If so, the Equipment replies with S10F4.

4.2.101 S10F4 - Terminal Display Single Acknowledge

S10F4 * H<-E
<B [1] ACKC10> . * Acknowledge Code

This Equipment may send the following values for ACKC10:

Table 4-32 S10F4 ACKC10 Values

| ACKC10 | Description |
|--------|-------------|
| 0x00 | Normal. |

4.2.102 S10F5 - Terminal Display, Multiblock

S10F5 [W] * H->E, Multiblock
<L [2]
 <B [1] TID> * Terminal ID
 <L
 <A [160] TEXT> * Message Text
 ...
 >
> .

S10F5 can contain multiple TEXT data items. Each TEXT data item is limited to 160 characters. Each data item in S10F5 will be displayed on a separate line at the Equipment.

The Host sends text to the Equipment. The Equipment interprets TID as follows:

Table 4-33 S10F5 TID Values

| TID | Description |
|-----|---|
| Any | Equipment displays the text on its CRT. |

The Host may optionally set the W-Bit to “1” in S10F5. If so, the Equipment replies with S10F6.

4.2.103 S10F6 - Terminal Display Multiblock Acknowledge

S10F6 * H<-E
 <B [1] ACKC10> . * Acknowledge Code

This Equipment may send the following values for ACKC10:

Table 4-34 S10F6 ACKC10 Values

| ACKC10 | Description |
|--------|-------------|
| 0x00 | Normal. |

4.2.104 S10F9 - Broadcast

S10F9 [W] * H->E
<A [160] TEXT> . * Message Text

The Host sends text to the Equipment. The Equipment displays the text on its CRT.

The Host may optionally set the W-Bit to “1” in S10F9. If so, the Equipment replies with S10F10.

4.2.105 S10F10 - Broadcast Acknowledge

S10F10 * H<-E
<B [1] ACKC10> . * Acknowledge Code

This Equipment may send the following values for ACKC10:

Table 4-35 S10F10 ACKC10 Values

| ACKC10 | Description |
|--------|-------------|
| 0x00 | Normal. |

5 SECS Scenarios

Unless otherwise noted in this section, the Communications State is “Communicating” and the Control state is either “On-Line/Local” or “On-Line/Remote”.

5.1 Equipment Communications

5.1.1 Equipment Establishes Communications

Assumption: Equipment’s Communication state is “Enabled/Not Communicating”.

Table 5-1 SECS Messages Equipment Establishes Communications

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H <- E S1F13 W | Equipment attempts to send Establish Communications Request. |
| 2 | | If the send is not successful, or if no reply is received from the Host, wait “ESTABLISHCOMMUNICATIONSTIMER” seconds, then go to Step 1. |
| 3 | H -> E S1F14 | The Host responds with Establish Communications Acknowledge. If COMMACK in this message is non-zero, wait “ESTABLISHCOMMUNICATIONSTIMER” seconds, then go to Step 1. If COMMACK is zero, proceed to the next step. |
| 4 | | Communications is successfully established. The Equipment changes its communication state to Communicating. Normal SECS message processing begins. |

5.1.2 Host Establishes Communications

Assumption: Equipment’s Communication state is either “Enabled/Not Communicating” or “Enabled/Communicating”.

Table 5-2 SECS Messages Host Establishes Communications

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S1F13 W | Host sends Establish Communications Request. |
| 2 | H <- E S1F14 | The Equipment responds with Establish Communications Acknowledge, with COMMACK set to zero. After this message is successfully sent, communications is established. If the current communication state is “Not Communicating”, the Equipment changes its communication state to “Communicating”. If the state is “Communicating”, no change in communication state occurs. In either case, subsequently received messages are processed normally. |

5.1.3 Simultaneous Establish Communications

Assumption: Equipment's Communication state is "Enabled/Not Communicating".

Table 5-3 SECS Messages Simultaneous Establish Communications

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H <- E S1F13 W | Equipment sends Establish Communications Request. |
| 2 | H -> E S1F13 W | Host sends Establish Communications Request. |
| 3 | H <- E S1F14 | The Equipment responds with Establish Communications Acknowledge, with COMMACK set to zero. After this message is successfully sent, communications is established. The Equipment changes its communication state to Communicating. |
| 4 | H -> E S1F14 | The Host responds with Establish Communications Acknowledge, with COMMACK set to zero. This step could occur before Step 3, in which case communications would be established at this step. |

5.1.4 Losing Connection, Re-Connecting

Table 5-4 SECS Messages Losing Connection, Re-Connecting

| Step | SECS Message | Description |
|------|---------------|---|
| 1 | H <- E SxFy | Any Message. The Equipment encounters SECS block transmission errors while attempting to send a message to the Host., and reaches its Retry Limit (RTY). The Equipment considers the SECS link as disconnected. Spooling will become Active if enabled. |
| 2 | H <-E S1F13 W | Connect Request. The Equipment attempts to re-establish the link. |
| 3 | | If the send is not successful, or if no reply is received from the Host, the Equipment waits for "EstablishCommunicationsTimer" seconds and then goes back to Step 2. |
| 4 | H -> E S1F14 | The Host acknowledges, sending COMMACK of "0". The link is now re-connected. |

5.1.5 Heartbeat

Table 5-5 SECS Messages Heartbeat

| Step | SECS Message | Description |
|------|---------------|---|
| 1 | H <- E S1F1 W | Are You There. The Equipment sends this message periodically to determine if the SECS link is still intact. |
| 2 | H -> E S1F2 | On Line Data. The Host replies. The Equipment knows that the link is still intact. |

5.2 Data Collection

5.2.1 Host Initializes Event Reporting

Table 5-6 SECS Messages Host Initializes Event Reporting

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S2F37 W | Disable Event Reports. The Host disables reporting for all Collection Events. S2F37 W <L [2] <BOOLEAN F> <L> > . |
| 2 | H <- E S2F38 | The Equipment acknowledges. Temporarily, the Equipment will make no event reports. |
| 3 | H ->E S2F33 W | Define Report. The Host erases all previous report definitions and links: S2F33 W <L [2] <U4 DATAID> <L> > . |
| 4 | H <- E S2F34 | The Equipment acknowledges. |
| 5 | H -> E S2F33 W | Define Report. The Host sends report definitions. |
| 6 | H <-E S2F34 | The Equipment acknowledges. |
| 7 | H -> E S2F35 W | Link Events/Reports. The Host links reports to the desired Collection Events. Linked Reports are initially "disabled". |
| 8 | H <- E S2F36 | The Equipment acknowledges. |
| 9 | H -> E S2F15 W | Equipment constant "Send". The Host sets equipment constant "RpType" to indicate whether event reports should be in "Normal" or "Annotated" format. |
| 10 | H <- E S2F16 | The Equipment acknowledges. |
| 11 | H -> E S2F37 W | Enable event reports. The Host enables reporting for desired collection events. |
| 12 | H <- E S2F38 | The Equipment acknowledges. From this point on, the Equipment will report events as they occur. |

5.2.2 Equipment Reports Event

Table 5-7 SECS Messages Equipment Reports Event

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | | The Equipment recognizes that an event has occurred. The Host has enabled reporting for the CEID, and possibly has defined one or more Reports and linked them to the CEID. The equipment constant "RpType" is set to "False", requesting normal reports. |
| 2 | H <- E S6F5 W | Inquire. If S6F13 will be multi-block, the Equipment first sends this Inquire to request permission. If S6F11 is single-block, skip this and the next step. |
| 3 | H -> E S6F6 | Grant. The Host grants permission to send multi-block Event Report. If GRANT6 is non-zero, this scenario fails here, and the event data is discarded. |
| 4 | H <- E S6F11 W | The Equipment sends Event reports for the CEID that occurred. |
| 5 | H -> E S6F12 | The Host acknowledges the report. |

5.2.3 Equipment Reports Annotated Event

Table 5-8 SECS Messages Equipment Reports Annotated Event

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | | The Equipment recognizes that an event has occurred. The Host has enabled reporting for the CEID, and possibly has defined one or more Reports and linked them to the CEID. The equipment constant "RpType" is set to "True", requesting Annotated reports. |
| 2 | H <- E S6F5 W | Inquire. If S6F13 will be multi-block, the Equipment first sends this Inquire to request permission. If S6F13 is single-block, skip this and the next step. |
| 3 | H -> E S6F6 | Grant. The Host grants permission to send multi-block Event Report. If GRANT6 is non-zero, this scenario fails here, and the event data is discarded. |
| 4 | H <- E S6F13 W | The Equipment sends annotated Event Reports for the CEID that occurred. |
| 5 | H -> E S6F14 | The Host acknowledges the report. |



NOTE

In all other scenarios in which Event Reports occur, the Events or Annotated Events are shown in abbreviated form (S6F11/S6F12 only). The complete Event Report Scenarios are shown here.

5.2.4 Host Initiates Trace

Table 5-9 SECS Messages Host Initiates Trace

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S2F23 W | The Host initiates a trace. |
| 2 | H <- E S2F24 | The Equipment acknowledges the trace request. If the data in S2F23 is not valid, the acknowledge code in this message is non-zero and the scenario ends. Otherwise, the following steps are done "TOTSMP" times, where TOTSMP is the total number of samples to be done. |
| 3 | | The Equipment waits "DSPER" (data sample period). While waiting, the Equipment continues to operate normally, responding to any SECS messages that may be received, etc. After the wait is finished, the values of the variable(s) to be traced are obtained and saved. If "REPGSZ" samples have been saved, or if this is the last sample, do the following steps. |
| 4 | H <- E S6F1 W | The Equipment sends trace data. |
| 5 | H -> E S6F2 | If the S6F1 has its W-bit set to 1, the Host acknowledges the trace data. |
| 6 | | If this is the last sample, the Equipment terminates this trace and the scenario ends. Otherwise, go back to the beginning of Step 3. |

5.2.5 Host Terminates Trace

Assumption: The Host started a Trace report as in the above scenario.

Table 5-10 SECS Messages Host Terminates Trace

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S2F23 W | The Host initiates a trace, with the same trace ID as the currently running trace, and with TOTSMP (number of samples) set to "0". |
| 2 | H <- E S2F24 | The Equipment acknowledges the trace request. If the data in S2F23 is valid, the Equipment terminates the trace. |
| 3 | | If the Equipment has saved trace data that has not yet been sent to the Host, it discards the saved data. |

5.2.6 Host Requests Status

Table 5-11 SECS Messages Host Requests Status

| Step | SECS Message | Description |
|------|---------------|--|
| 1 | H -> E S1F3 W | Discrete Variable Request. The Host requests the VIDs of interest. |
| 2 | H <- E S1F4 | The Equipment sends the Variable values. |

5.2.7 Host Defines Limits

Table 5-12 SECS Messages Host Defines Limits

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S2F45 W | Host defines new variable limits attributes. |
| 2 | H <- E S2F46 | Equipment accepts new limits definitions, and responds with VLAACK = 0x00. |

5.2.8 Host Queries Defined Limits

Table 5-13 SECS Messages Host Queries Defined Limits

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S2F47 W | Host requests listing of defined limits. This request may be for limits of individual variables listed in this message, or if this message is an empty list, all limits will be replied. |
| 2 | H <- E S2F48 | Equipment sends limits values as required. |

5.2.9 Host Requests Report by CEID

Table 5-14 SECS Messages Host Requests Report by CEID

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S6F15 W | Request Event Report. The Host requests a report for the specified CEID. In this way, the Host requests the Equipment to “pretend” that the specified CEID has occurred. |
| 2 | H <- E S6F16 | The Equipment sends reports linked to that CEID. |

5.2.10 Host Requests Annotated Report by CEID

Table 5-15 SECS Messages Host Requests Annotated Report by CEID

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S6F17 W | Request Annotated Event Report. The Host requests a report for the specified CEID. In this way, the Host requests the Equipment to “pretend” that the specified CEID has occurred. |
| 2 | H <- E S6F18 | The Equipment sends annotated reports linked to that CEID. |

5.2.11 Host Requests Report by RPTID

Table 5-16 SECS Messages Host Requests Report by RPTID

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S6F19 W | Request Report. The Host requests a report for the specified RPTID. |
| 2 | H <- E S6F20 | The Equipment sends the report. |

5.2.12 Host Requests Annotated Report by RPTID

Table 5-17 SECS Messages Host Requests Annotated Report by RPTID

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S6F21 W | Request Annotated Report. The Host requests an annotated report for the specified RPTID. |
| 2 | H <- E S6F22 | The Equipment sends the annotated report. |

5.2.13 Are You There

Table 5-18 SECS Messages Are You There

| Step | SECS Message | Description |
|------|---------------|--|
| 1 | H -> E S1F1 W | Are You There. The Host sends this simple message. |
| 2 | H <- E S1F2 | The Equipment reports its MDLN and SOFTREV. |

5.2.14 Host Reads Equipment Constants

Table 5-19 SECS Messages Host Reads Equipment Constants

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S2F13 W | Host requests the values of one or more equipment constants. |
| 2 | H <- E S2F14 | The Equipment responds with the values of the requested equipment constants. |

5.2.15 Host Sets Equipment Constants

Table 5-20 SECS Messages Host Sets Equipment Constants

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S2F15 W | Host sends new values for one or more equipment constants. |
| 2 | H <- E S2F16 | If all new values are valid, the Equipment saves the new values and sends this message with an acknowledge code of "0". If one or more new values are not valid, no equipment constants are changed and the acknowledge code in this message is non-zero. |

5.3 Alarms

5.3.1 Equipment Reports Alarm

Table 5-21 SECS Messages Equipment Reports Alarm

| Step | SECS Message | Description |
|------|-----------------|---|
| 1 | H <- E S5F1 [W] | If reporting for this alarm ID is disabled, skip this and the following step. Otherwise send the alarm. The equipment constant "WBitS5" determines whether the W-bit is "0" or "1" in this message. |
| 2 | H -> E S5F2 | If the W-bit in S5F1 is 1, the Host acknowledges the alarm report. Otherwise, skip this step. |
| 3 | H <- E S6F11 W | If the event ID associated with this alarm state is enabled, send the Event Report. Otherwise, the scenario ends. |
| 4 | H -> E S6F12 | The Host acknowledges the Event Report. |

5.3.2 Host Enables/Disables Alarms

Table 5-22 SECS Messages Host Enables/Disables Alarms

| Step | SECS Message | Description |
|------|-----------------|--|
| 1 | H -> E S5F3 [W] | The Host specifies ALIDs to be enabled or disabled. |
| 2 | H <- E S5F4 | If the W-bit in S5F3 is 1, the Equipment acknowledges. |

5.3.3 Host Requests Alarms

Table 5-23 SECS Messages Host Requests Alarms

| Step | SECS Message | Description |
|------|---------------|--|
| 1 | H -> E S5F5 W | The Host requests whether specified ALIDs are "on" or "off". |
| 2 | H <- E S5F6 | The Equipment sends Alarm status. |

5.3.4 Alarm Report (GEM, Ver 3.1 Compatibility)



NOTE This scenario is provided only for compatibility with Host computers which support GEM, Version 3.1.

Table 5-24 SECS Messages Alarm Report (GEM, Ver 3.1 Compatibility)

| Step | SECS Message | Description |
|------|------------------|--|
| 1 | | The equipment constant "ConfigAlarms" is set to 2 for non-GEM compatibility. The Equipment recognizes that an alarm condition has gone "on" (i.e. has become Unsafe). |
| 2 | H <- E S5F73 [W] | The Equipment reports the Alarm going on. The high-order bit of ALCD is "1". |
| 3 | H -> E S5F74 | If the W-bit of S5F74 is 1, the Host acknowledges the Alarm. |
| 4 | | The Equipment recognizes that the alarm condition has gone "off" (i.e. has become Safe). |
| 5 | H <- E S5F73 [W] | The Equipment reports the Alarm going off. The high-order bit of ALCD is "0". |
| 6 | H -> E S5F74 | If the W-bit in S5F74 is 1, the Host acknowledges the Alarm. |

5.3.5 Alarm Report (GEM, Ver 1.7 Compatibility)



NOTE This scenario is provided only for compatibility with Host computers which support GEM, Version 1.7.

Table 5-25 SECS Messages Alarm Report (GEM, Ver 1.7 Compatibility)

| Step | SECS Message | Description |
|------|------------------|---|
| 1 | | The equipment constant "ConfigAlarms" is set to 1 for GEM, Version 1.7 compatibility. The Equipment recognizes that an alarm condition has gone "on" (i.e. has become Unsafe). |
| 2 | H <- E S5F71 [W] | The Equipment reports the Alarm going on. The high-order bit of ALCD is "1". |
| 3 | H -> E S5F72 | If the W-bit in S5F71 is 1, the Host acknowledges the Alarm. |
| 4 | | The Equipment recognizes that the alarm condition has gone "off" (i.e. has become Safe). |
| 5 | H <- E S5F71 [W] | The Equipment reports the Alarm going off. The high-order bit of ALCD is "0". |
| 6 | H -> E S5F72 | If the W-bit in S5F71 is 1, the Host acknowledges the Alarm. |

5.4 Control State

5.4.1 Host Sends On-Line Command

Assumption: Control State is “Host Off-Line”. Variable GemControlState = 3.

Table 5-26 SECS Messages Host Sends On-Line Command

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S1F17 W | Host instructs the Equipment to go “On-Line”. |
| 2 | H <- E S1F18 | Equipment responds to successful On-Line transition with ONLACK=0. Control state transits to either Local or Remote as guided by EC GemOnlineSubstate. |
| 3 | H <- E S6F11 W | The Equipment signals CEID: GemControlState LOCAL or GemControlState REMOTE. |
| 4 | H -> E S6F12 | The Host acknowledges the event. |

5.4.2 Host Sends Off-Line Command

Assumption: Control State is “On-Line”.

Table 5-27 SECS Messages Host Sends Off-Line Command

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S1F15 W | Host instructs the Equipment to go “Off-Line”. |
| 2 | H <- E S1F16 | Equipment Control State transitions to “Host Off-Line” (GemControlState = 3) and responds to primary. OFLACK = 0. |

5.4.3 Host Sends Remote Command

Assumption: Control State is on-line and Remote.

Table 5-28 SECS Messages Host Sends Remote Command

| Step | SECS Message | Description |
|------|------------------|---|
| 1 | H -> E S2F41 [W] | The Host sends the command. The W-bit in this message may be either 0 or 1. |
| 2 | H <- E S2F42 | If the W-bit was 1, the Equipment acknowledges the command. If the Equipment cannot perform the command, the acknowledge code in this message is non-zero. If the command can be completed “immediately”, the command is performed and the acknowledge code in this message is 0. Otherwise, if the command takes a significant amount of time to complete, the acknowledge code is 4. Successful completion of a command may trigger one or more events. |

5.4.4 Equipment Rejects Host Command

Assumption: Control State is Local and On-Line

Table 5-29 SECS Messages Equipment Rejects Host Command

| Step | SECS Message | Description |
|------|------------------|---|
| 1 | H -> E S2F41 [W] | The Host sends the command. The W-bit in this message may be either 0 or 1. |
| 2 | H <- E S2F42 | If the W-bit in S2F41 is 1, the Equipment acknowledges the command. The acknowledge code in this message is 64 (Control State is incorrect). If the W-bit is 0, this message is not sent. In either case, the Equipment does not perform the command. |

5.4.5 Go Remote, Operator-Initiated

Table 5-30 SECS Messages Go Remote, Operator-Initiated

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | | ControlState is Local. The Operator switches the Equipment to Remote Control. |
| 2 | H <- E S6F11 W | The Equipment signals CEID GemControlState REMOTE. Event Reports as appropriate. |
| 3 | H -> E S6F12 | The Host acknowledges the report. |

5.4.6 Go Local, Operator-Initiated

Table 5-31 SECS Messages Go Local, Operator-Initiated

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | | ControlState is Remote. The Operator switches the Equipment to Local control state. |
| 2 | H <- E S6F11 W | The Equipment signals CEID GemControlState LOCAL. Event Reports as appropriate. |
| 3 | H -> E S6F12 | The Host acknowledges the report. |

5.4.7 Go Local, Host-Initiated

Table 5-32 SECS Messages Go Local, Host-Initiated

| Step | SECS Message | Description |
|------|------------------|--|
| 1 | | ControlState is Remote. |
| 2 | H -> E S2F41 [W] | Remote Command (GO LOCAL). The Host commands the Equipment to go into Local control state. |
| 3 | H <- E S2F42 | If the W-bit in S2F41 is 1, the Equipment acknowledges the command. HCACK is zero. |
| 4 | H <- E S6F11 W | The Equipment signals CEID GemControlState LOCAL. Event Reports as appropriate. |
| 5 | H -> E S6F12 | The Host acknowledges the report. |

5.4.8 Operator Command, Successful

Table 5-33 SECS Messages Operator Command, Successful

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | | ControlState is Local. The Operator issues a front-panel INITIATE PROCESS command. The Equipment performs the command. |
| 2 | H <- E S6F11 W | The Equipment signals CEID LotStart. Event Reports as appropriate. |
| 3 | H -> E S6F12 | The Host acknowledges the report. |

5.5 Process Program Management

5.5.1 Unformatted, Host-Initiated Download

Table 5-34 SECS Messages Unformatted, Host-Initiated Download

| Step | SECS Message | Description |
|------|---------------|--|
| 1 | H -> E S7F1 W | Host requests permission to send a multi-block Process Program to the Equipment. If the Process Program is single-block, this step and the next one may be skipped. |
| 2 | H <- E S7F2 | The Equipment grants permission for the Host to send the Process Program. |
| 3 | H -> E S7F3 W | Host sends the process Program to the Equipment. |
| 4 | H <- E S7F4 | The Equipment acknowledges receipt of the Process Program. The Equipment checks the received Process Program for validity. If the process Program is valid, the Equipment stores the Process Program in its library and sends an acknowledge code of zero in this message. If the Process Program is not valid, or could not be stored in the library, the acknowledge code in this message is non-zero. |

5.5.2 Unformatted, Host-Initiated Upload

Table 5-35 SECS Messages Unformatted, Host-Initiated Upload

| Step | SECS Message | Description |
|------|---------------|--|
| 1 | H -> E S7F5 W | Host requests a Process Program from the Equipment library. |
| 2 | H <- E S7F5 | The Equipment sends the Process Program. If the Process Program does not exist, the data portion of this message is an empty list. |

5.5.3 Unformatted, Equipment-Initiated Download

Table 5-36 SECS Messages Unformatted, Equipment-Initiated Download

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H <- E S7F5 W | Equipment requests a Process Program. |
| 2 | H -> E S7F6 | The Host sends the Process Program. If the Process Program is valid, the Equipment stores the Process Program in its library, and the scenario ends. If the data portion of S7F6 is an empty list, or if the Process Program is not valid, the Equipment does not store it in its library and the scenario continues. |
| 3 | H <- E S6F11 W | The Equipment sets "PPCHANGENAME" to the requested PPID and signals CEID GemBadDownloadEvent. Event reports as appropriate. |
| 4 | H -> E S6F12 | The Host acknowledges the report. |

5.5.4 Unformatted, Equipment-Initiated Upload

Table 5-37 SECS Messages Unformatted, Equipment-Initiated Upload

| Step | SECS Message | Description |
|------|---------------|--|
| 1 | H <- E S7F1 W | Process Program Inquire. If S7F3 is multi-block, the Equipment requests permission to send a multi-block message. If S7F3 is single-block, skip this and the following step. |
| 2 | H -> E S7F2 | Process Program Grant. The Host grants permission. If PPGNT is non-zero, the scenario fails here. |
| 3 | H <- E S7F3 W | Send Process Program. The Equipment uploads Process Program to Host. |
| 4 | H -> E S7F4 | The Host acknowledges. The Equipment ignores ACKC7. |

5.5.5 Host Deletes Process Program

Table 5-38 SECS Messages Host Deletes Process Program

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S7F17 W | Host sends a request to delete one or more Process Programs from the Equipment's library of Process Programs. |
| 2 | H <- E S7F18 | The Equipment replies with an acknowledge code. If all specified Process Program(s) were deleted successfully, the acknowledge code is 0. If one or more of the specified Process Programs could not be deleted, the acknowledge code is non-zero. |

5.5.6 Host Requests Directory

Table 5-39 SECS Messages Host Requests Directory

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S7F19 W | Host requests the names (PPIDs) of all Process Programs that are stored in the Equipment's Process Program library. |
| 2 | H <- E S7F20 | The Equipment replies with the list of PPIDs. |

5.5.7 Operator Changes Process Program Library

Table 5-40 SECS Messages Operator Changes Process Program Library

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | | The Operator creates, changes, or deletes a Process Program in the Library. |
| 2 | H <- E S6F11 W | The Equipment sets PPCHANGESTATUS to "Create", "Change", or "Delete", as appropriate, sets PPCHANGENAME, and signals CEID GemPPChangeEvent. Event Reports as appropriate. |
| 3 | H -> E S6F12 | The Host acknowledges the report. |

5.6 Equipment Terminal Communications

5.6.1 Host to Equipment, Single Line

Table 5-41 SECS Messages Host to Equipment, Single Line

| Step | SECS Message | Description |
|------|------------------|--|
| 1 | | The Host has data to display at the Equipment's front panel. |
| 2 | H -> E S10F3 [W] | Terminal Display. The Host sends text. The Equipment displays the text on its front panel. |
| 3 | H <- E S10F4 | If the W-bit in S10F3 is 1, the Equipment acknowledges. |
| 4 | | The Operator acknowledges that he/she has read the message. |
| 5 | H <- E S6F11 W | The Equipment signals CEID S10Ack. Event Reports as appropriate. |
| 6 | H -> E S6F12 | The Host acknowledges the report. |

5.6.2 Host to Equipment, Multi-Line

Table 5-42 SECS Messages Host to Equipment, Multi-Line

| Step | SECS Message | Description |
|------|------------------|---|
| 1 | | The Host has a multi-line data to display at the Equipment front panel. |
| 2 | H -> E S10F5 [W] | Terminal Display Multiple. The Host sends text. The Equipment displays the text on its front panel. |
| 3 | H <- E S10F6 | If W-bit in S10F5 is 1, the Equipment acknowledges. |
| 4 | | The Operator acknowledges that he/she has read the message. |
| 5 | H <- E S10F11 W | The Equipment signals CEID HostMsgAck. Event Reports as appropriate. |
| 6 | H -> E S6F12 | The Host acknowledges the report. |

5.6.3 Equipment Sends Text to Host

Table 5-43 SECS Messages Equipment Sends Text to Host

| Step | SECS Message | Description |
|------|------------------|---|
| 1 | | The Operator enters data to send to the Host. |
| 2 | H <- E S10F1 [W] | Equipment sends text to Host. The W-bit in this message may be either 0 or 1. The Host displays the message for the Operator. |
| 3 | H -> E S10F2 | If the W-bit in S10F1 is 1, the Host acknowledges the text message. |

5.7 SECS Error Messages

5.7.1 Unrecognized Device ID

Table 5-44 SECS Messages Unrecognized Device ID

| Step | SECS Message | Description |
|------|-----------------|--|
| 1 | H -> E SnFn [W] | Host sends a message with a bad Device ID in the header. The W-bit can be either 0 or 1. |
| 2 | H <- E S9F1 | Equipment replies with “Unrecognized Device ID”. |

5.7.2 Unrecognized Stream

Table 5-45 SECS Messages Unrecognized Stream

| Step | SECS Message | Description |
|------|-----------------|--|
| 1 | H -> E SnFn [W] | Host sends a primary message with a stream number that the Equipment does not support. The W-bit can be either 0 or 1. |
| 2 | H <- E S9F3 | Equipment replies with “Unrecognized Stream”. |

5.7.3 Unrecognized Function

Table 5-46 SECS Messages Unrecognized Function

| Step | SECS Message | Description |
|------|-----------------|---|
| 1 | H -> E SnFn [W] | Host sends a primary message with a stream number for which the Equipment recognizes some messages, but with a function number that the Equipment does not support for that stream. The W-bit can be either 0 or 1. |
| 2 | H <- E S9F5 | Equipment replies with “Unrecognized Function”. |

5.7.4 Illegal Data Format

Table 5-47 SECS Messages Illegal Data Format

| Step | SECS Message | Description |
|------|-----------------|--|
| 1 | H -> E SnFn [W] | Host sends a message with a stream and function that the Equipment recognizes, but with a data format that is incorrect. The W-bit can be either 0 or 1. |
| 2 | H <- E S9F7 | |

5.7.5 Data Too Long

Table 5-48 SECS Messages Data Too Long

| Step | SECS Message | Description |
|------|-----------------|--|
| 1 | H -> E SnFn [W] | Host sends a message with a stream and function that the Equipment recognizes, but contains more data than expected. The W-bit can be either 0 or 1. |
| 2 | H <- E S9F11 | Equipment replies with "Data Too Long". If the erroneous message is a primary with the W-bit set to 1, then in some cases the Equipment will reply with the usual secondary response with an appropriate error code, instead of S9F11. If the erroneous message is a secondary, the Equipment makes no reply at all. |

5.8 Clock

5.8.1 Host Sets Date and Time

Table 5-49 SECS Messages Host Sets Date and Time

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S2F31 W | Date and Time Send. The Host sends a new Date and Time to the Equipment. |
| 2 | H <- E S2F32 | The Equipment sets its Clock/Calendar hardware and acknowledges the command. |

5.8.2 Host Requests Date and Time

Table 5-50 SECS Messages Host Requests Date and Time

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S2F17 W | Date and Time Request. The Host requests Date and Time from the Equipment. |
| 2 | H <- E S2F18 | The Equipment sends its Date and Time. |

5.8.3 Equipment Requests Date and Time

Table 5-51 SECS Messages Equipment Requests Date and Time

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H <- E S2F17 W | Date and Time Request. The Equipment requests Date and Time from the Host. |
| 2 | H -> E S2F18 | The Host sends its Date and Time. The Equipment sets its Clock/Calendar hardware according to the contents of this message. |

5.9 Spooling

For all of the spooling scenarios, spooling is meaningful only when Control State (CONTROLSTATE = 4 or 5) is “On-Line”. When CONTROLSTATE is “Off-Line” (CONTROLSTATE = 1, 2, or 3), the Equipment sends only stream one primaries and SnF0 secondaries, neither of which are eligible for spooling.

5.9.1 Host Enables Spooling of Messages

Table 5-52 SECS Messages Host Enables Spooling of Messages

| Step | SECS Message | Description |
|------|----------------|---|
| 1 | H -> E S2F43 W | <p>Host requests that messages be eligible for spooling using the following message:</p> <pre>S2F43 W * H -> E <L <L [2] <U1 STRID> * Msg Stream <L <U1 FCNID> * Msg Fcn ... > ... > .</pre> |
| 2 | H <- E S2F44 | <p>The Equipment enables spooling for the messages requested by the Host. Response has RSPACK set to zero as follows:</p> <pre>S2F44 <L [2] <B [1] 00> * RSPACK <L> > .</pre> |

5.9.2 Messages Spooled and Transmitted

Assumption: Spool State is “Spool Inactive”.

Table 5-53 SECS Messages Spooled and Transmitted

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H <- E SnFn | Equipment attempts to send any message to the Host. |
| 2 | | After failure to deliver message, the Equipment assumes that the link is down, and will start to spool all messages marked for spooling. The first message spooled is the collection event “SpoolActivated”. |
| 3 | H <- E S1F13 W | Equipment attempts to establish communications. This message will repeat every “EstablishCommunicationsTimer” seconds until successful. |
| 4 | H -> E S1F14 | Communications established. Communications state transits to “Communicating”. If COMMACK is not zero, communications are not established and scenario proceeds at Step 3. |
| 5 | H -> E S6F23 W | Host requests that Equipment begin de-spooling messages. RSDC is zero in this message. |
| 6 | H <- E S6F24 | Equipment indicates that it will start to send spooled messages with return code RSDA = 0x00. |
| 7 | | Equipment will start to de-spool messages. This process is single-threaded. That is, when Equipment sends a de-spooled message with the W-bit set to “1”, Equipment must receive the Host reply before the Equipment will send next de-spooled message. If EC “MaxSpoolTransmit” is zero, all messages will be transmitted. If it is set to another number, this number of messages will be sent. The Equipment will await the next S6F23 to send the next messages. |
| 8 | H <- E S6F11 W | The Equipment signals CEID GemSpoolActivated. This was the first message in the spool if it was not over-written. |
| 9 | H -> E S6F12 | Host acknowledges the start of the spool transfer. |
| 10 | | <p>Equipment will de-spool messages one at a time from oldest to youngest until one of the following criteria is met:</p> <ol style="list-style-type: none"> 1. All messages have been transmitted (go to Step 13); or 2. When “MaxSpoolTransmit” is not zero, and the messages transmitted has reached MaxSpoolTransmit limit (go to Step 11). <p>Some spooled messages (usually multi-block) consist of a SECS conversation of type “Inquire, Grant, Send, Acknowledge”. During de-spool, if the Host rejects the Inquire, the multi-block message is removed from the spool and not transmitted. De-spooling continues.</p> |

Table 5-53 SECS Messages Spooled and Transmitted (Continued)

| Step | SECS Message | Description |
|------|----------------|--|
| 11 | H -> E S6F23 W | The Host requests that the Equipment continue de-spooling messages. |
| 12 | H <- E S6F24 | Equipment indicates that it will start to send spooled messages with return code RSDA = 0x00. Go to Step 10. |
| 13 | H <- E S6F11 W | Equipment notifies the Host that sending of spooled messages has been completed by sending CEID GemSpooling Deactivated. |
| 14 | H -> E S6F12 | Host acknowledges that the spool has been cleared and is deactivated. |

5.9.3 Host Purges Spool

Assumption: spool state is “Spool Active”

Table 5-54 SECS Messages Host Purges Spool

| Step | SECS Message | Description |
|------|----------------|--|
| 1 | H -> E S6F23 W | Host sends S2F23, requesting that spool be discarded with RSDC set to one. |
| 2 | H <- E S6F24 | Equipment deletes spooled data and returns RSDA code zero. |

6 Machine Variable Definitions

The following data variables are collected by the Host to support intelligent communications with the Equipment:

- [Status Variables](#)
- [Data Variables](#)
- [Equipment Constants](#)

Each variable is given a header line with its associated ID value and its name. The storage type and the definition of the variable are listed below in smaller type. Variables listed in the header in capital letters are GEM standards. The others belong to Fluidmove.

All variables are listed in alphabetical order.

6.1 Status Variables

Table 6-1 Status Variables

| Variable Name | ID | Storage Type | Description |
|------------------|-----|--------------|--|
| ABORTLEVEL | 21 | U1 | The abort level of the most recent ABORT command. |
| ALARMID | 22 | U4 | This variable contains the ID of the last alarm to be reported to the Host. |
| ALARMSENABLED | 23 | List | This variable contains the list of the currently enabled alarms. Refer to Appendix A for the format. |
| ALARMSERIAL | 26 | U4 | The sequence number (count) of the most recent alarm change (going on or going off). This number starts at zero at power-up and increments by one for each following alarm transition. |
| ALARMSSET | 24 | List | This variable contains the list of alarms which are currently set. |
| ALARMSTATE | 25 | U1 | The state of the current alarm. Non zero values indicate the alarm is set. |
| BoardCount | 106 | U4 | The number of boards processed since the Power On event or since the last Process entry into the Running state. |
| CameraXFieldMils | 700 | U2 | The size in mils of the X coordinate axis field of view seen by the camera. |
| CameraYFieldMils | 701 | U2 | The size in mils of the Y coordinate axis field of view seen by the camera. |

Table 6-1 Status Variables (continued)

| Variable Name | ID | Storage Type | Description |
|----------------------|-----|--------------|---|
| CLOCK | 27 | A[16] | The current value of the clock accurate to hundredths of a second. The format is: YYMMDDHHmmsscc . This format is always the same, regardless of TIMEFORMAT. |
| CONTROLSTATE | 28 | U1 | The value indicating the current Control State Machine state: 1 - OffLine/Equipment OffLine 2 - OffLine/Attempt OnLine 3 - OffLine/Host OffLine 4 - OnLine/Local 5 - OnLine/Remote |
| DeviceID | 115 | A[12] | The SECS Device ID. |
| EventLogFilename | 104 | A[12] | The name of the file holding the event log. |
| EVENTSENABLED | 30 | List | This is the list of events which are enabled for reporting to the Host. |
| FluidFileName | 300 | A[12] | The name of the data file holding the dispensing fluid data. Fluid files have the ".flu" extension. |
| FluidLotNumber | 301 | A[20] | The lot number of the dispensing fluid. |
| FluidThawTime | 302 | A[14] | The time stamp, in the YYMMDDhhmmss format, at which the fluid was removed from the refrigerator and began to warm up. |
| MachineID | 102 | A[20] | The model number and serial number of the Asymtek machine. Refer to Appendix A for the format. |
| MDLN | 31 | A[6] | The model designation for this machine. |
| PPDirectory | 103 | A[30] | The directory path of the Process Programs on the hard disk. |
| PPEXECNAME | 32 | A[0..80] | The currently selected Process Program ID number. |
| PREVIOUSCEID | 33 | U4 | The latest event ID to be sent to the Host. |
| PREVIOUSCOMMAND | 34 | A[0..9] | The latest remote command received from the Host. |
| PREVIOUSCONTROLSTATE | 35 | U1 | The value indicating the previous Control State for the Equipment: 1 - Off-Line / Equipment Off-Line 2 - Off-Line /Attempt On-Line 3 - Off-Line/Host Off-Line 4 - On-Line Local 5 - On-Line Remote |

Table 6-1 Status Variables (continued)

| Variable Name | ID | Storage Type | Description |
|----------------------|-----|--------------|--|
| PREVIOUSPROCESSSTATE | 36 | U1 | The previous Process State for the Equipment. The values for this state can be found in Appendix A . |
| PROCESSSTATE | 37 | U1 | The current Process State for the Equipment. The values for this state can be found in Appendix A . |
| ProductionStartTime | 105 | A[14] | The time stamp at which the last production run began. Refer to Appendix A for the format. |
| RunMode | 110 | U1 | The specific type of runtime operation being conducted; dry run, production run, pass-through, or prototype test run. |
| SOFTREV | 38 | A[6] | The software revision number in ASCII code. |
| SoftwareID | 101 | A[20] | Fluidmove name and version code. |
| SPOOLCOUNTACTUAL | 48 | U4 | A count of the number of messages actually present on the spool disk, adjusted for any messages which have been overwritten or discarded. |
| SPOOLCOUNTTOTAL | 49 | U4 | A count of the number of messages the Equipment attempted to write to the spool disk. This number includes messages actually present on the spool disk, and any messages which may have been overwritten or discarded. |
| SPOOLFULLTIME | 50 | A[16] | The date and time at which the Spool file became full. The format is : YYMMDDhhmmsscc . |
| SPOOLLOADSUBSTATE | 51 | U4 | The current state within the SPOOL LOAD super-state. 1 - Spool Active 2 - Spool Inactive |
| SPOOLSTARTTIME | 52 | A[16] | See CLOCK variable above for this format. |
| SPOOLSTATE | 53 | U4 | The current Spool State within the POWER ON super-state. 3 - Purge Spool 4 - Transmit Spool 5 - No Spool output |
| SPOOLUNLOADSUBSTATE | 54 | U4 | The current Spool State within the SPOOLUNLOAD super-state. 6 - Spool not full 7 - Spool full |
| TIME | 39 | A[12] | The current time accurate to the second. The format is YYMMDDhhmmss . This format is always the same, regardless of TIMEFORMAT. |

6.2 Data Variables

Table 6-2 Data Variables

| Variable Name | ID | Storage Type | Description |
|-------------------|------|--------------|--|
| ALARMTEXT | 1000 | A[0..40] | The Alarm Text (ALTX) for the most recent alarm transition. |
| ALARMSEVERITYCODE | 1001 | B[1] | The Severity Code (the low order seven bits) of the most recent alarm transition. |
| BarcodeRaw | 350 | A[30] | The barcode string exactly as it is read by the scanner from the barcode tag on the board at the dispense station. |
| BarcodeFiltered | 351 | A[30] | The barcode string read in from the scanner after unwanted characters are filtered out as specified by the Operator. |
| BoardCycleTime | 114 | U2 | The number of seconds required to complete dispensing an entire board of substrates. |
| ConveyorSpeed1 | 500 | F4 | The Conveyor 1 belt speed during board transfer between dispensing positions. The units are in./sec. |
| ConveyorSpeed2 | 501 | F4 | The Conveyor 2 belt speed during board transfer between dispensing positions. The units are in./sec. |
| DWVRESULT | 408 | U2 | <p>Result of Dispense Weight Verification Routine:</p> <p>0 = Pass</p> <p>1 = Fail: Setup error (scale not ready, limits out of range, etc.)</p> <p>2 = Fail: Out of Range</p> <p>3 = Fail: Weight measured below min deviation</p> <p>4 = Fail: Weight measured above max deviation</p> <p>5 = Fail: User abort</p> <p>6 = Fail: Other reason than listed above</p> |

Table 6-2 Data Variables (continued)

| Variable Name | ID | Storage Type | Description |
|-------------------|-----|--------------|---|
| DWVVALVE | 409 | U2 | <p>Valve used during Dispense Weight Verification:</p> <p>1 = Valve 1</p> <p>2 = Valve 2</p> <p>3 = Valve 3</p> <p>Valid only after collection event "DispenseWeightComplete" occurs.</p> |
| DWVTARGET | 410 | F8 | <p>Dispense Weight Verification target weight.</p> <p>Valid only after collection event "DispenseWeightComplete" occurs.</p> |
| DWVTARGETRANGE | 412 | F8 | <p>Dispense Weight Verification Target Range: If range limit checking is enabled, this variable will contain the maximum allowable range for the dispense weight verification routine. If limit checking is not enabled, this variable will contain "-1".</p> <p>Valid only after collection event DispenseWeightComplete" occurs.</p> |
| DWVTARGETMINLIMIT | 413 | F8 | <p>Minimum allowable deviation from the target weight of the dispense weight for the Dispense Weight Verification routine.</p> <p>Note that if the verification routine fails and the failed weight is required, the data variable "SCALEMEASUREMENT1" (if Valve 1) or "SCALEMEASUREMENT2" (if Valve 2) will have the last value read from the scale.</p> <p>Valid only after collection event "DispenseWeightComplete" occurs.</p> |
| DWVTARGETMAXLIMIT | 414 | F8 | <p>Maximum allowable deviation from the target weight of the dispense weight for the Dispense Weight Verification routine.</p> <p>Note that if the verification routine fails and the failed weight is required, the data variable "SCALEMEASUREMENT1" (if Valve 1) or "SCALEMEASUREMENT2" (if Valve 2) will have the last value read from the scale.</p> <p>Valid only after collection event "DispenseWeightComplete" occurs.</p> |

Table 6-2 Data Variables (continued)

| Variable Name | ID | Storage Type | Description |
|------------------|-----|--------------|--|
| DWVMEASUREDRANGE | 415 | F8 | <p>Dispense Weight Verification Measured Range: If range limit checking is enabled, this variable will be compared against DMVTARGETRANGE and used as one of the conditions for a pass/fail result. If limit checking is not enabled, this value will still be valid but not used in the pass/fail decision.</p> <p>If the routine fails to due limit checking or is interrupted before it completes, the variable will contain “-1”.</p> <p>Valid only after collection event “DispenseWeightComplete” occurs.</p> |
| DWVMEASUREDAVG | 416 | F8 | <p>Dispense Weight Verification Average: average weight of all dispenses after the dispense weight verification completes or “-1” if the routine fails or is interrupted before it completes.</p> <p>Valid only after collection event “DispenseWeightComplete” occurs.</p> |
| ECIDCHANGE | 46 | U4 | The ID of the last event to be reported to the Host. |
| FluidState1 | 306 | A[10] | <p>Fluid level of syringe on Valve 1 as reported by the low fluid sensor or fluid level monitoring software. This value is updated twice per board. Once when the board is loaded and ready for dispensing and again when dispensing is complete on that board. Possible values are:</p> <p>“FULL” – Fluid level is full.</p> <p>“LOW” – Fluid level has reached the low level.</p> <p>“EMPTY” – Fluid level is close to empty. This value is possible only with the two position hardware sensor.</p> <p>“NONE” – Fluid sensing sensors do not exist or software monitoring has not been turned on.</p> <p>“ERROR” – Error when using the two position hardware sensor. Signals indicate empty but not low.</p> |
| FluidState2 | 307 | A[10] | Same as FluidState1, but for Valve 2. |
| FlowRate1 | 400 | F8 | The most current fluid flow rate in mg. per second for Valve 1. |
| FlowRate2 | 403 | F8 | The most current fluid flow rate in mg. per second for Valve 2. |
| FlowRateMax1 | 402 | F8 | The maximum flow rate in mg./sec. allowed during this run for Valve 1. |

Table 6-2 Data Variables (continued)

| Variable Name | ID | Storage Type | Description |
|-----------------------------------|---------------|--------------|--|
| FlowRateMax2 | 405 | F8 | The maximum flow rate in mg./sec. allowed during this run for Valve 2. |
| FlowRateMin1 | 401 | F8 | The minimum flow rate in mg./sec. allowed during this run for Valve 1. |
| FlowRateMin2 | 404 | F8 | The minimum flow rate in mg./sec. allowed during this run for Valve 2. |
| GEMLIMITSVID | 57 | U4 | Contains the VID of the variable whose value crossed defined limits. |
| NumFailedBoards | 107 | U4 | The number of boards failed since PwrUp or since the Process State entered the Running state. |
| PPCHANGENAME | 40 | A[0..8] | The PPID of the Process Program most recently changed. |
| PPCHANGESTATUS | 41 | U1 | The last action performed on the Process Program. 1 – Created 2 – Changed 3 - Deleted |
| ScaleMeasurement1 | 406 | F8 | The actual value read from the scale during a Flow Rate Verification Procedure when Valve 1 is being used. |
| ScaleMeasurement2 | 407 | F8 | The actual value read from the scale during a Flow Rate Verification Procedure when Valve 2 is being used. |
| TEMPHTR1CHAN1 – TEMPHTR1CHAN17 | 801 to 817 | F8 | Heater 1 temperatures for channels 1-17 respectively (DV 801 = channel 1, DV 802 = channel 2, etc.). The units are in degrees. No other information is supplied such as the unit of degrees (Centigrade or Fahrenheit) or what device the channel is mapped to (ie, pre-dispense station, needle heater, etc.). A value of negative one (-1) indicates the channel is not monitored or not turned on. Note: These variables are only updated between boats and only when monitored by “Verify Temperature Before Initial Dispense”. |
| TEMPHTR2CHAN1 – TEMPHTR2CHAN17 | 818 to 834 | F8 | Identical to Data Variables 801-817 except that they refer to Heater 2 channels 1-17, respectively (DV 818 = channel 1 of heater 2, DV 819 = channel 2 of heater 2 etc.) |
| TEMPHTR3CHAN1 – TEMPHTR3CHAN17 | 835 to 851 | F8 | Identical to Data Variables 801-817 except that they refer to Heater 3 channels 1-17, respectively (DV 835 = channel 1 of heater 3, DV 836 = channel 2 of heater 3 etc.) |

6.3 Equipment Constants

Table 6-3 Equipment Constants

| Variable Name | ID | Storage Type | Description |
|------------------------------|-----|--------------|---|
| BOARDFREQUENCY | 610 | U4 | This value is set by the station controller to the board frequency it requires collection event 2010 to occur. The default is zero which prevents collection event 2010 from triggering. |
| CONFIGALARMS | 1 | U1 | This EC determines the type of alarm message which is sent following an alarm. 0 – S5F1, 1 – S5F71, 2 – S5F73. |
| CONFIGCONNECT | 2 | U1 | The EC which determines which message type the Equipment uses for Connection Request. 0 – S1F1, 1 – S1F65, 2 – S1F13 |
| CONFIGEVENTS | 3 | U1 | The EC which determines the choice of Event Report message. 0 – S6F9 or S6F3, 1 – S6F11, or S6F13. |
| CONFIGSPOOL | 63 | U4 | This variable defines the current Spooling State: 0 - Disabled 1 - Enabled |
| DEVICENAME | 29 | A[20] | This is the name chosen by the Host in its references to the machine. |
| ESTABLISHCOMMUNICATIONSTIMER | 6 | U2 | The delay in seconds between each attempt to reestablish communications. |
| GEMLIMITSDELAY | 60 | U2 | Determines how often the Equipment checks if variables are within the defined limits (seconds). |
| INITCOMMSTATE | 8 | U1 | Indicates weather Host communications should be enabled in the initial Communications State entered following Power Up. The two assignable values are: 1 - Enable Host Communications 2 - Disable |
| INITCONTROLSTATE | 9 | U1 | The initial Control State to be entered following Power Up. The two values are: 1 - Off-Line 2 - On-Line |
| HEARTBEAT | 10 | U2 | The time in seconds between each S1F1 “Are You There” message sent to the Host. These messages are sent to confirm that the communications link between the Host and the Equipment is still valid during light message traffic. |

Table 6-3 Equipment Constants (continued)

| Variable Name | ID | Storage Type | Description |
|---------------------|-----|--------------|---|
| MAXSPOOLTRANSMIT | 46 | U4 | This is the largest number of messages that may be read from the Spool file during a single read. This limits the number of messages sent to the Host in response to the S6F23 message and helps to prevent clogging of the communications link during a link recovery after a long communications failure. |
| MeasFlowEnabled | 601 | BOOL | This Boolean flag indicates whether periodic flow rate calibration operations are enabled. 1 – Enabled 0 - Disabled |
| OFFLINESUBSTATE | 42 | U1 | This variable determines the Control State that the Equipment enters when it enters the OffLine super-state. The allowable values are: 1 - Equipment Off-Line 2 - Attempt On-Line 3 - Host Off-Line |
| ONLINEFAILED | 43 | U1 | This variable controls the entry state resulting from a failed attempt to go On-Line. The two values are: 1 - Equipment Off-Line 3 - Host Off-Line |
| ONLINESUBSTATE | 44 | U1 | This variable controls the entry state resulting from a successful attempt to go On-Line. The two values are: 4 - On-Line – Local 5 - On-Line - Remote |
| OVERWRITESPOOL | 62 | BOOL | This variable enables overwriting the Spool when it becomes full. |
| PurgeEnabled | 600 | BOOL | The state of periodic purging operations. 1 – Enabled 0 - Disabled |
| RPTYPE | 17 | BOOL | This variable enables the Equipment to send annotated reports to the Host on request. |
| TEMPERATUREDVUPDATE | 611 | BOOL | Set by the station controller to turn heater temperature data variable updating on (TRUE) or off (FALSE). The default value is TRUE. |
| VisionFailures | 112 | U4 | The number of vision system failures counted by the Fluidmove software since the Power On event or latest Process Program change. The Host may clear this variable to measure failures during a run. |

Table 6-3 Equipment Constants (continued)

| Variable Name | ID | Storage Type | Description |
|---------------|----|--------------|--|
| WBITS10 | 18 | U1 | This variable determines the default state of the W bit for all messages in stream 10 sent from the Equipment to the Host. |
| WBITS5 | 19 | U1 | This variable determines the default state of the W bit for all messages in stream 5 sent from the Equipment to the Host. |
| WBITS6 | 20 | U1 | This variable determines the default state of the W bit for all messages in stream 6 sent from the Equipment to the Host. |

7 Host-to-Equipment Messages



NOTE In Table 7-1 “Primary” and “Reply” columns:

* = Fluidmove secondary message handlers

** = Fluidmove primary message handlers

Table 7-1 Host-to-Equipment Messages

| Primary | Reply | Cstate | Description | Notes |
|---------|--------|--------|-------------------------------------|---|
| S1F1 | S1F2 | 4,5 | Are You There | None |
| S1F3 | S1F4 | 4,5 | Selected Status | Possible variable access |
| S1F11 | S1F12 | 4,5 | Status Variable Namelist Request | None |
| S1F13 | S1F14 | All | Connect Request | None |
| S1F15 | S1F16* | 4,5 | Request Off-Line | None |
| S1F17 | S1F18* | 1,2,3 | Request On-Line | None |
| S1F65 | S1F66* | All | Connect Request | None N |
| S2F13 | S2F14 | 4,5 | Equipment Constant Request | Possible variable access (only if non-ECs requested). |
| S2F15 | S2F16* | 4,5 | New Equipment Constant Send | Possible EC validation routines. EC-Changed processing routine. Disk write occurs. |
| S2F17 | S2F18* | 4,5 | Date and Time Request | None |
| S2F21 | S2F22 | 5 | Remote Command | Primary message handler N (for Non GEM Hosts). |
| S2F23 | S2F24 | 4,5 | Trace Initialize | None |
| S2F25 | S2F26 | 4,5 | Loopback Diagnostic | None E |
| S2F27 | S2F28* | 5 | Initiate Processing Request | Primary Message Handler N |
| S2F29** | S2F30 | 4,5 | Equipment Constant Namelist Request | None E |

Table 7-1 Host-to-Equipment Messages (continued)

| Primary | Reply | Cstate | Description | Notes |
|---------|--------|--------|--------------------------------------|---|
| S2F31 | S2F32 | 4,5 | Date and Time Send | None |
| S2F33 | S2F34 | 4,5 | Define Report | None Disk write occurs. |
| S2F35 | S2F36 | 4,5 | Link Event Report | None Disk write occurs. |
| S2F37 | S2F38 | 4,5 | Enable/Disable Event Report | None. Disk write occurs. |
| S2F39 | S2F40 | 4,5 | Multi-Block Inquire/Grant | None |
| S2F41** | S2F42* | 5 | Remote Command with Parameters | Primary Message Handler |
| S2F43 | S2F44 | 4,5 | Reset Spooling Streams and Functions | None |
| S2F45 | S2F46 | 4,5 | Define Variable Limits Attributes | None |
| S2F47 | S2F48 | 4,5 | Variable Limit Attribute Request | None |
| S5F3 | S5F4 | 4,5 | Enable/Disable Alarm | None Disk write occurs. |
| S5F5** | S5F6* | 4,5 | List Alarms | None |
| S5F7 | S5F8* | 4,5 | List Enabled Alarms | None E |
| S6F15 | S6F16 | 4,5 | Request Event Report | Possible variable access routines. |
| S6F17 | S6F18 | 4,5 | Request Annotated Event Report | Possible variable access routines. E |
| S6F19 | S6F20 | 4,5 | Request Report | Possible variable access routines. |
| S6F21 | S6F22 | 4,5 | Request Annotated Report | Possible variable access routines. E |
| S6F23 | S6F24 | 4,5 | Request Spooled Data | None |
| S7F1 | S7F2 | 4,5 | Process Program Inquire/Grant | None |

Table 7-1 Host-to-Equipment Messages (continued)

| Primary | Reply | Cstate | Description | Notes |
|---------|--------|--------|-------------------------------------|-----------------------------------|
| S7F3 | S7F4 | 4,5 | Unformatted Process Program Send | UFPP verify Disk write occurs. |
| S7F5** | S7F6* | 4,5 | Unformatted Process Program Request | None Disk read occurs. |
| S7F17** | S7F18 | 4,5 | Process Program Delete | None Disk write occurs. |
| S7F19 | S7F20* | 4,5 | Process Program Directory | None Disk read occurs. |
| S10F3** | S10F4 | 4,5 | Terminal Display, Single | Terminal display |
| S10F5** | S10F6 | 4,5 | Terminal Display, Multiple | Terminal display |
| S10F9** | S10F10 | 4,5 | Broadcast | Terminal display E |

8 Equipment-to-Host Messages



NOTE In Table 8-1 “Reply” column:

* = Fluidmove secondary message handlers

Table 8-1 Equipment-to-Host Messages

| Primary | Reply | Description | Notes |
|----------|-------|-------------------------------------|--|
| -- (any) | SnF0 | Primary rejected while Off-Line | None |
| S1F1 | S1F2 | Are You There | None (heartbeat) GemGoAOnline (Attempt Online) |
| S1F13 | S1F14 | Connect Request | None |
| S1F65 | S1F66 | Connect Request | None N |
| S2F17 | S2F18 | Date and Time Request | GemHostTimeReq |
| S5F1 | S5F2* | Alarm Report | GemNoteAlarmEvent N |
| S5F71 | S5F72 | Alarm Report Block Send | GemNoteAlarmEvent |
| S5F73 | S7F74 | Alarm Notification Send | GemNoteAlarmEvent |
| S6F1 | S6F2 | Trace Data Send | Possible variable access routines. |
| S6F3 | S6F4 | Annotated Event Report Send | GemNoteEvent Possible variable access routines. N |
| S6F5 | S6F6 | Multi-Block Data Send Inquire/Grant | None |
| S6F9 | S6F10 | Event Report Send | GemNoteEvent Possible variable access routines. N |
| S6F11 | S6F12 | Event Report Send | GemNoteEvent Possible variable access routines. |

Table 8-1 Equipment-to-Host Messages (continued)

| Primary | Reply | Description | Notes |
|---------|-------|-------------------------------------|---|
| S6F13 | S6F14 | Annotated Event Report Send | GemNoteEvent Possible variable access routines. N |
| S7F1 | S7F2 | Process Program Inquire/Grant | GemUFPPSend or GEMFPPSend |
| S7F3 | S7F4* | Unformatted Process Program Send | GemUFPPSend Disk Read occurs |
| S7F5 | S7F6 | Unformatted Process Program Request | GemUFPPLoad UFPPVerify Disk write occurs. |
| S9F1 | -- | Error, Device ID | None |
| S9F3 | -- | Error, Stream | None |
| S9F5 | -- | Error, Function | None |
| S9F7 | -- | Error, Data | None |
| S9F9 | -- | Error, Transaction Timeout | None |
| S9F11 | -- | Error, Data Too Long | None |
| S9F13 | -- | Error, Conversation timeout | Sent by application only if required. |
| S10F1 | S10F2 | Terminal Request | GemTerminalRequest |
| S13F1 | S13F2 | Send Data Set Send | GemDSNameSend |

Appendix A All Variables

A.1 Overview

This appendix provides an explanation summary of the machine variables described in [Section 6 – Machine Variable Definitions](#).

A.2 Data Formats

The data formats are as follows:

| | |
|--------------------|--|
| A[nn] | ASCII text of length nn. Where two numbers are indicated, they specify a range of acceptable lengths. |
| Boolean | A boolean flag indicating TRUE or FALSE. |
| F4,F8 | A floating point number in four bytes. |
| I1,I2,I4,I8 | Signed integers of the indicated length in bytes. |
| U1,U2,U4,U8 | Unsigned integers of the indicated length in bytes. |
| List | An array of similar structures or primitive elements, as above. The list format is specified in the description field. |

A.3 Variables

Table A-1 lists all variables by ID number and contains details of the content of each variable.



NOTE See [Appendix D – FmConfig.ini File Variables](#) for Variable ID's 6000-6768.

Table A-1 All Variables

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------------------|-----------|----|-----------|---------------------------|--|
| GemAlarmFileName | EC | 0 | A | None | Gem alarm file name |
| ConfigAlarms | EC | 1 | U1 | None | An EC which controls which Alarm Report message this Equipment will send. 0 = S5F1 default 1 = S5F71 2 = S5F73 |
| ConfigConnect | EC | 2 | U1 | None | An EC which controls which SECS message this Equipment will use for Connect Request. 0 = S1F1 1 = S1F65 2 = S1F13 default |
| ConfigEvents | EC | 3 | U1 | None | An EC which controls some aspects of the Event Reports sent by this Equipment. 0 = S6F9 or S6F3 1 = S6F11 or S6F13 default |
| GemConstantFileName | EC | 4 | A | None | Gem constant filename |
| DeviceName | EC | 5 | A[80] | None | The Host can change this EC to define a meaningful name for the equipment. |
| EstablishCommunicationsTimeout | EC | 6 | U2 | None | Time in seconds of how long the equipment will delay after an unsuccessful Connect Request before sending another. Valid values are 0-32000. |
| InitCommState | EC | 8 | U1 | None | Initial (power-up) Communications State. 0 = Disabled 1 = Enabled |
| InitControlState | EC | 9 | U1 | None | Initial (power-up) control super-state. 1 = Off-Line 2 = On-Line |
| Heartbeat | EC | 10 | U2 | None | The time in seconds that the equipment will delay before sending S1F1 to test the link. Units are seconds. Valid values are 0-3200 (a setting of zero will disable the heartbeat). |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------|-----------|----|-----------|---------------------------|--|
| RpType | EC | 17 | Boolean | None | This EC controls some aspects of the format of Event Reports sent by this Equipment. FALSE = Normal Event Reports TRUE = Annotated Event Reports |
| WBitS10 | EC | 18 | U1 | None | An EC which controls the W-Bit setting used when sending S10F1. 0 = W-Bit not set 1 = W-Bit set |
| WBitS5 | EC | 19 | U1 | None | An EC which controls the W-Bit setting used when sending Alarm Reports (S5F1, S5F71, or S5F73). 0 = W-Bit not set 1 = W-Bit set |
| WBitS6 | EC | 20 | U1 | None | An EC which controls the W-Bit setting used when sending stream six messages (events, trace) 0 = W-Bit not set 1 = W-Bit set |
| AbortLevel | SV | 21 | U1 | None | The AbortLevel of the most recent ABORT command. |
| AlarmID | DV | 22 | U1 | None | The ALID of the most recent Alarm transition. |
| AlarmsEnabled | SV | 23 | L | None | A list of all Alarms which are currently enabled. Format as follows: <L,n 1.<U4 ALID> ... n.<U4 ALID> > |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------|-----------|----|-----------|---------------------------|--|
| AlarmsSet | SV | 24 | L | None | A list of all Alarms which are currently in the SET (on) state. Format as follows: <L 1.<U4 ALID> ... n.<U4 ALID> > |
| AlarmState | SV | 25 | U1 | None | The Alarm State now in effect for the most recently transitioned alarm. 0 = Alarm transitioned OFF 1 = Alarm transitioned ON |
| AlarmSerial | SV | 26 | U4 | None | The sequence number of the most recent alarm change (going on or going off). This number starts at zero at power-up and increments by one for each alarm transition which occurs. |
| Clock | SV | 27 | A | None | The Equipment's current Date and Time in the following format: YYYYMMDDhhmmsscc. YYYY = year from 0000 to 9999 MM = month from 01 to 12 DD = day from 01 to 31 hh = hours from 00 to 59 mm = minutes from 00 to 59 ss = seconds from 00 to 59 cc = centiseconds from 00 to 99 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------------|-----------|----|-----------|---------------------------|---|
| ControlState | SV | 28 | U1 | None | The current Control State. 1 = Off-Line/Equipment Off-Line 2 = Off-Line/Attempt On-Line 3 = Off-Line/Host Off-Line 4 = On-Line/Local 5 = On-Line/Remote |
| DataID | SV | 29 | U4 | None | Gem data ID |
| EventsEnabled | SV | 30 | L | None | A list of all events which are currently enabled. Format as follows: <L,n 1.<U4 CEID> ... n.<U4 CEID> > |
| MDLN | SV | 31 | A | None | Model number. The format is a one to six letters, left-justified acronym with blank fill on the right. |
| PPExecName | SV | 32 | A[80] | None | The PPID of the currently selected Process Program. This PPID is the DOS 8.3 file name of the recipe. It includes the extension RCP. |
| PreviousCeid | SV | 33 | U4 | None | The CEID of the most recent collection event which has occurred. |
| PreviousCommand | SV | 34 | A | None | The name of the most recent command. |
| PreviousControlState | SV | 35 | U1 | None | The Control State in effect before the most recent transition to the current Control State. 1 = Off-Line/Equipment Off-Line 2 = Off-Line/Attempt On-Line 3 = Off-Line/Host Off-Line 4 = On-Line/Local 5 = On-Line/Remote |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------------|-----------|----|-----------|---------------------------|---|
| PreviousProcessState | SV | 36 | U1 | None | The Process State in effect before the most recent transition to the current Process State. 0 = Idle (Boot-up) 1 = Idle 2 = Running 3 = Paused 4 = Aborting 5 = Error |
| ProcessState | SV | 37 | U1 | None | The current Process State. 0 = Idle (Boot-up) 1 = Idle 2 = Running 3 = Paused 4 = Aborting 5 = Error |
| SOFTREV | SV | 38 | A | None | Software revision number with Major and minor parts. Example: "1.02 " The revision is in <u>M</u> ajor and <u>m</u> inor format with a period separating the parts. |
| Time | SV | 39 | A[16] | None | Time format depends on VID 71 "TIMEFORMAT". If TIMEFORMAT = 0, then: A[12] = YYMMDDHHMMSS If TIMEFORMAT = 1, then: A[16] = YYYYMMDDHHMMSSCC |
| PPChangeName | DV | 40 | A[80] | (GEM) | PPID of the Process Program most recently created, changed, or deleted. This variable is the DOS 8.3 file name of the recipe changed. It includes the extension RCP. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|----|-----------|---------------------------|--|
| PPChangeStatus | DV | 41 | U1 | (GEM) | The action (create, change, delete) taken on a Process Program. 1 = Created 2 = Changed 3 = Deleted |
| OfflineSubstate | EC | 42 | U1 | None | The default (power-up) offline substate of the Control State Model. 1 = Equipment Off-Line 2 = Attempt On-Line 3 = Host Off-Line |
| OnlineFailed | EC | 43 | U1 | None | The default Control State transition when Attempt On-Line fails. 1 = Equipment Off-Line 2 = Host Off-Line |
| OnlineSubstate | EC | 44 | U1 | None | The default (power-up) online substate of the Control State Model. 4 = Local 5 = Remote |
| MaxSpoolTransmit | EC | 46 | U4 | None | The maximum number of spooled messages the equipment will send each time the Host reads the spool. A setting of zero indicates that all spooled messages should be sent. Refer to the description of S6F23 in the "SECS Message Detail" section for further information. |
| SpoolCountActual | SV | 48 | U4 | None | A count of the number of messages actually present on the spool disk, adjusted for any messages which have been overwritten or otherwise discarded. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------|-----------|----|-----------|---------------------------|---|
| SpoolCountTotal | SV | 49 | U4 | None | A count of the number of messages the equipment attempted to write to the spool disk. This number includes messages actually present on the spool disk, and also any messages which may have been overwritten or otherwise discarded. |
| SpoolFullTime | SV | 50 | A | None | The date and time at which the spool file became full. Format is: YYYYMMDDhhmmsscc. See description of CLOCK variable (VID 27) above for format details. |
| SpoolLoadSubstate | SV | 51 | U1 | None | The current state within the SPOOL LOAD super-state. 6 = Spool Not Full 7 = Spool Full |
| SpoolStartTime | SV | 52 | A | None | The date and time at which the first message was written to the current spool file. Format is: YYYYMMDDhhmmsscc. See description of CLOCK variable (VID 27) above for format details. |
| SpoolState | SV | 53 | U1 | None | The current spool state within the POWER ON super-state. 1 = Spool Active 2 = Spool Inactive |
| SpoolUnloadSubstate | SV | 54 | U1 | None | The current spool state within the SPOOL UNLOAD super-state. 3 = Purge Spool 4 = Transmit Spool 5 = No Spool Output |
| GemEventText | DV | 55 | A[5,24] | (GEM) | Gem event text (documentation states that GemEventText no longer used) |
| GemPPKeepSecsHeader | EC | 56 | Boolean | None | Gem PP keep secs header |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------|-----------|----|-----------|---------------------------|--|
| GemLimitsVID | DV | 57 | U4 | (GEM) | Contains the VID of the variable whose value crossed defined limits. |
| GemEventLimit | DV | 58 | Boolean | (GEM) | Gem event limit |
| GemTransType | DV | 59 | Boolean | (GEM) | Gem transaction type |
| GemLimitsDelay | EC | 60 | U2 | None | Determines how often the Equipment checks if variables are within the defined limits (seconds). |
| OverWriteSpool | EC | 62 | Boolean | None | This EC determines the action to be taken by the Equipment when the Spool file reaches its capacity. TRUE = Overwrite Spool FALSE = Do Not Overwrite Spool |
| ConfigSpool | EC | 63 | U1 | None | This EC determines whether spooling is enabled or disabled for this Equipment. 0 = Disabled 1 = Enabled |
| ECIDChanged | DV | 67 | U4 | (GEM) | The VID of the Equipment Constant most recently changed by the Operator. |
| LinkState | SV | 68 | U1 | None | Gem link state |
| None Defined | EC | 69 | I4 | None | Gem terminal request send max |
| TimeFormat | EC | 71 | U1 | None | Determines whether STIME is sent in 12-byte or 16-byte format. 0 = 12-byte data format 1 = 16-byte data format |
| StartUpDelay | EC | 72 | I2 | None | Gem startup delay |
| MinimumInterval | EC | 80 | U4 | None | Gem minimum interval |
| None Defined | SV | 82 | L | None | Gem VID list |
| None Defined | SV | 83 | L | None | Gem AL ID list |
| None Defined | SV | 84 | L | None | Gem collection event ID list |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------|-----------|-----|-----------|---------------------------|---|
| WBitS6F1 | EC | 85 | U1 | None | Gem WBIT S6F1 |
| SoftwareID | SV | 101 | A[20] | None | The Fluidmove software name and version code. The version is in Major and minor format with a period separating the parts. Up to seven letters in an alphanumeric suffix follow the capitol A and hyphen in the name as shown. Spaces pack any remaining space to the right of the software ID. |
| MachineID | SV | 102 | A[30] | None | The machines Model number and Serial number. The MachineID format is: "Model SNXXXXX ". The Model field is fixed at twenty characters. The Serial Number field is fixed at ten characters and contains up to five characters in the serial number. Spaces pack any remaining space to the right of both fields. |
| PPDirectory | SV | 103 | A[30] | None | The directory path holding the Process Programs. The format is: "vol:\dir1[\dir2[\dir3]]". Brackets indicate optional directory levels. The volume indicator is a single letter. |
| EventLogFilename | SV | 104 | A[12] | None | The name of the file holding the event records log. |
| ProductionStartTime | SV | 105 | A[14] | None | The time stamp when production started. The format is: YYYYMMDDhhmmss . Similar to the TIME(39) variable format. YYYY = year from 0000 to 9999 MM = month from 01 to 12 DD = day from 01 to 31 hh = hours from 00 to 59 mm = minutes from 00 to 59 ss = seconds from 00 to 59 |
| BoardCount | SV | 106 | U4 | None | The number of boards processed since the Power On event or since the last Process entry into the Running state. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|-----|-----------|---------------------------|---|
| NumFailedBoards | DV | 107 | U4 | 9000 9001 | The number of boards failed during this run. |
| GCP_BuildVersion | SV | 108 | U4 | None | GCP file build number |
| RunMode | SV | 110 | U1 | None | The various types of run operations: 0 = Standby 1 = Production Dry 2 = Production Wet 3 = Pass-through 4 = Lane 1 Continuous/Lane 2 Pass-through 5 = Lane 1 Pass-through /Lane 2 Continuous 6 = Manual Wet 7 = Manual Dry 8 = Not Ready 9 = Invalid |
| VisionFailures | EC | 112 | U4 | None | The count of vision system failures counted by the Fluidmove software since the Power On event or since the last change of Process Programs. The Host may clear this variable to measure failures during a run. |
| BoardCycleTime | DV | 114 | U2 | 2002 2004 | The time in seconds needed to complete dispensing a board. |
| DeviceID | SV | 115 | A[12] | None | The SECS Device ID. |
| FluidFileName1 | SV | 300 | A[40] | None | This is the name of the file containing the dispensing fluid data for Valve1. The file extension is ".flu". The DOS 8.3 file name format is used. There are up to eight characters reserved for the name and up to three characters for the extension. The name and extension are thus separated by a period: "name.ext". The file name is left justified within the character string, and spaces pack any remaining space to the right of the file name. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------|-----------|-----|-----------|---------------------------|---|
| FluidLotNumber1 | SV | 301 | A[20] | None | This is the dispensing fluid lot number recorded by the Operator when the syringe was reloaded. The format is a twenty character ASCII alphanumeric string containing the lot number from the fluid syringe. The number is left justified and blanks fill the remaining space. |
| FluidThawTime1 | SV | 302 | A[14] | None | This is the time stamp in the YYYYMMDDhhmmss format, at which the fluid was removed from the refrigerator and began to warm up. Similar to the TIME(39) variable format. YYYY = year from 0000 to 9999 MM = month from 01 to 12 DD = day from 01 to 31 hh = hours from 00 to 59 mm = minutes from 00 to 59 ss = seconds from 00 to 59 |
| FluidFileName2 | SV | 303 | A[40] | None | This is the name of the file containing the dispensing fluid data for Valve 2. See FluidFileName1 (VID 300) for a detailed description. |
| FluidLotNumber2 | SV | 304 | A[20] | None | This is the dispensing fluid lot number for Valve 2. See FluidLotNumber1 (VID 301) for a detailed description. |
| FluidThawTime2 | SV | 305 | A[14] | None | This is the time stamp for the fluid for Valve 2. See FluidThawTime1 (VID 302) for a detailed description. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------|-----------|-----|-----------|---------------------------|--|
| FluidState1 | DV | 306 | A[10] | 2001 | <p>Fluid level of syringe on Valve 1 as reported by the low fluid sensor or fluid level monitoring software. This value is updated twice per board. Once when the board is loaded and ready for dispensing and again when dispensing is complete on that board. Possible values are:</p> <p>“FULL” – Fluid level is full.</p> <p>“LOW” – Fluid level has reached the low level.</p> <p>“EMPTY” – Fluid level is close to empty. This value is possible only with the two position hardware sensor.</p> <p>“NONE” – Fluid sensing sensors do not exist or software monitoring has not been turned on.</p> <p>“ERROR” – Error when using the two position hardware sensor. Signals indicate empty but not low.</p> |
| FluidState2 | DV | 307 | A[10] | 2003 | Same as FluidState1 but for Valve 2. |
| OperatorLoginID | SV | 340 | A[100] | None | Operator login ID |
| BarcodeRaw | DV | 350 | A[30] | 2050 | The barcode string exactly as it is read by the scanner from the barcode tag on the board at the dispense station. |
| BarcodeFiltered | DV | 351 | A[30] | 2050 | The barcode string read in from the scanner after unwanted characters are filtered out as specified by the Operator. |
| FlowRate1 | DV | 400 | F8 | 4012 | The most current fluid flow rate for Valve 1 in mg./sec. |
| FlowRateMin1 | DV | 401 | F8 | 4012 | The minimum flow rate for Valve 1 in mg./sec. allowed during this run. |
| FlowRateMax1 | DV | 402 | F8 | 4012 | The maximum flow rate for Valve 1 in mg./sec. allowed during this run. |
| FlowRate2 | DV | 403 | F8 | 4013 | The most current fluid flow rate for Valve 2 in mg/sec. |
| FlowRateMin2 | DV | 404 | F8 | 4013 | The minimum flow rate for Valve 2 in mg./sec. allowed during this run. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------|-----------|-----|-----------|---------------------------|---|
| FlowRateMax2 | DV | 405 | F8 | 4013 | The maximum flow rate for Valve 2 in mg./sec. allowed during this run. |
| ScaleMeasurement1 | DV | 406 | F8 | 4010 | The actual value read from the scale during a Dispense Weight Verification Procedure when Valve 1 is being used. |
| ScaleMeasurement2 | DV | 407 | F8 | 4011 | The actual value read from the scale during a Dispense Weight Verification Procedure when Valve 2 is being used. |
| DWVResult | DV | 408 | U2 | 4020 | Result of Dispense Weight Verification Routine: 0 = Pass 1 = Fail: Setup error (scale not ready, limits out of range, etc.) 2 = Fail: Out of Range 3 = Fail: Weight measured below min deviation 4 = Fail: Weight measured above max deviation 5 = Fail: User abort 6 = Fail: Other reason than listed above |
| DWVValve | DV | 409 | U2 | 4020 | Valve used during Dispense Weight Verification: 1 = Valve 1 2 = Valve 2 3 = Valve 3 Valid only after collection event "DispenseWeightComplete" occurs. |
| DWVTarget | DV | 410 | F8 | 4020 | Dispense Weight Verification target weight. Valid only after collection event "DispenseWeightComplete" occurs. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------|-----------|-----|-----------|---------------------------|---|
| DWVDispenses | DV | 411 | U4 | 4020 | Dispense Weight Verification: number of dispenses that will be performed. Valid only after collection event "DispenseWeightComplete" occurs. |
| DWVTargetRange | DV | 412 | F8 | 4020 | Dispense Weight Verification Target Range: If range limit checking is enabled, this variable will contain the maximum allowable range for the dispense weight verification routine. If limit checking is not enabled, this variable will contain "-1". Valid only after collection event "DispenseWeightComplete" occurs. |
| DWVTargetMinLimit | DV | 413 | F8 | 4020 | Minimum allowable deviation from the target weight of the dispense weight for the Dispense Weight Verification routine. Note: If the verification routine fails and the failed weight is required, the data variable "SCALEMEASUREMENT1" (if valve 1) or "SCALEMEASUREMENT2" (if valve 2) will have the last value read from the scale. Valid only after collection event "DispenseWeightComplete" occurs. |
| DWVTargetMaxLimit | DV | 414 | F8 | 4020 | Maximum allowable deviation from the target weight of the dispense weight for the Dispense Weight Verification routine. Note: If the verification routine fails and the failed weight is required, the data variable "SCALEMEASUREMENT1" (if valve 1) or "SCALEMEASUREMENT2" (if valve 2) will have the last value read from the scale. Valid only after collection event "DispenseWeightComplete" occurs. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------------|-----------|-----|-----------|---------------------------|---|
| DWVMeasuredRange | DV | 415 | F8 | 4020 | <p>This is the dispense weight verification measured range. If range limit checking is enabled, this variable will be compared against DMVTARGETRANGE and used as one of the conditions for a pass/fail result. If limit checking is not enabled, this value will still be valid but not used in the pass/fail decision.</p> <p>If the routine fails to due limit checking or is interrupted before it completes, the variable will contain "-1".</p> <p>Valid only after collection event "DispenseWeightComplete" occurs.</p> |
| DWVMeasuredAvg | DV | 416 | F8 | 4020 | <p>Dispense Weight Verification Average: average weight of all dispenses after the dispense weight verification completes or "-1" if the routine fails or is interrupted before it completes.</p> <p>Valid only after collection event "DispenseWeightComplete" occurs.</p> |
| DWVValveOnTime | DV | 417 | F8 | 4020 | Dispense Weight Verification valve on time |
| RefillRate1 | DV | 418 | A[40] | 3672 | DP refill rate for valve 1 |
| RefillRate2 | DV | 419 | A[100] | 3672 | DP refill rate for valve 2 |
| CPJCheckResultStatus | DV | 420 | U2 | 3701 3702 | CPJ check result status bytes |
| ValvePressure_V1 | SV | 421 | F8 | 3703 | Valve pressure on valve 1 |
| FluidPressure_V1 | SV | 422 | F8 | 3704 | Fluid pressure on valve 1 |
| CoolingPressure_V1 | SV | 423 | F8 | 3705 | Cooling pressure on valve 1 |
| ValvePressure_V2 | SV | 424 | F8 | 3706 | Valve pressure on valve 2 |
| FluidPressure_V2 | SV | 425 | F8 | 3707 | Valve pressure on valve 2 |
| CoolingPressure_V2 | SV | 426 | F8 | 3708 | Cooling pressure on valve 2 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------------|-----------|-----|-----------|------------------------------|--|
| CarrierLoadTime_L1 | DV | 428 | A[100] | 8403 | Carrier load time on lane 1 |
| CarrierUnloadTime_L1 | DV | 429 | A[100] | 8404 | Carrier unload time on lane 2 |
| ValvePressureSetPt_V1 | SV | 430 | F8 | 3789 | Valve pressure set point valve 1 |
| FluidPressureSetPt_V1 | SV | 431 | F8 | 3790 | Fluid pressure set point valve 1 |
| CoolingPressureSetPt_V1 | SV | 432 | F8 | 3791 | Cooling pressure set point valve 1 |
| ValvePressureSetPt_V2 | SV | 433 | F8 | 3792 | Valve pressure set point valve 2 |
| FluidPressureSetPt_V2 | SV | 434 | F8 | 3793 | Fluid pressure set point valve 2 |
| CoolingPressureSetPt_V2 | SV | 435 | F8 | 3794 | Cooling pressure set point valve 2 |
| ParameterChangedVid | DV | 450 | I4 | 3638 3639 3651 3652 | Parameter changed VID. Set to the variable ID of the configuration, fluid or heater file parameter changed by operator |
| NewParameterString | DV | 451 | A[100] | 3638 3651 | New "string" value of a configuration, fluid or heater parameter changed by operator. |
| NewParameterInt | DV | 452 | I4 | 3639 3652 | New "integer" value of a configuration, fluid, or heater parameter changed by operator. |
| OldParameterString | DV | 453 | A[100] | 3638 3651 | Old "string" value of configuration, fluid or heater parameter before changed by operator. |
| OldParameterInt | DV | 454 | I4 | 3639 3652 | Old "integer" value of a configuration, fluid, or heater parameter before changed by operator. |
| FluidFilenameChanged | DV | 455 | A[100] | 3651 3652 | Fluid filename changed |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------------------|-----------|-----|-----------|--|--|
| FluidTypeChanged | DV | 456 | I2 | 3651 3652 | Fluid type changed 0 = Characteristic 1 = Dot/Line Type 1 2 = Dot/Line Type2 ... 10 = Dot/Line Type 10 |
| FluidFileChangedValveNumber | DV | 457 | I2 | 3651 3652 | Fluid file changed valve number 1 = Valve 1 2 = Valve 2 |
| HeaterFilename | DV | 458 | A[100] | 3653 3654 3655 3656 3657 3658 3659 3660 | Heater filename. Name of the heater file being modified, manually saved, manually uploaded (depending on collection event). |
| HeaterLoopChanged | DV | 459 | I2 | 3653 3654 | Heater loop changed |
| HeaterFilenameOld | DV | 460 | A[100] | 3655 3657 | Heater filename old. Only valid during collection events 3655 and 3657. Name of heater file replaced when the heater file is saved (ce 3657) or a heater file is manually downloaded (ce 3655). The new (current) heater filename is stored in "HeaterFilename" (VID 458). Note that the old and new heater filename may be the same. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------------|-----------|-----|-----------|--------------------------------------|--|
| ProgramName | DV | 461 | A[100] | 3663 3664 3669 3670 3671 | Currently loaded program name |
| PatternName | DV | 462 | A[100] | 3663 3670 3671 | Name of pattern being edited. |
| PattInstructionChangeType | DV | 463 | I4 | 3663 | Pattern instruction change type. 1 = Line Inserted 2 = Line Deleted 3 = Line Modified |
| PattInstructionNew | DV | 464 | A[200] | 3663 3669 | Modified or new pattern instruction |
| PattInstructionOld | DV | 465 | A[200] | 3663 3669 | Original instruction before modification or deleted instruction. |
| PattInstructionLineNum | DV | 466 | I4 | 3663 | Pattern instruction line number modified. |
| PatternNameAddedOrDeleted | DV | 467 | A[100] | 3664 3665 | Name of pattern created (CE 3664) or deleted (CE 3665). |
| RecipeFilename | DV | 468 | A[100] | 3 3667 3668 | Recipe name for related collection event. |
| CarrierLoadTime_L2 | DV | 469 | A[100] | 8405 | Carrier load time lane 2 |
| CarrierUnloadTime_L2 | DV | 470 | A[100] | 8405 8406 | Carrier unload time lane 2 |
| SizeOfCanister | DV | 499 | A[100] | 3700 | Size of BFS canister (BFS system is not used) |
| ConveyorSpeed1 | DV | 500 | F4 | None | This is the Conveyor 1 belt speed in in./sec. when it is moving a board to the next dispensing position. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------|-----------|-----|-----------|--|--|
| ConveyorSpeed2 | DV | 501 | F4 | None | This is the Conveyor 2 belt speed in in./sec. when it is moving a board to the next dispensing position. |
| ImageFilename | DV | 520 | A[100] | 8002 8003 8004 | Image filename. Name of image file saved after related collection event is triggered. Name contains entire path and name of image. The name will reflect the current date and time to make each file name unique. |
| LaneNumber | DV | 521 | I4 | 2001 2002 2003 2004 8000 8400 | Active lane number. Lane number specifying what lane report data applies to when certain collection events are triggered. |
| ScaleNumber | DV | 522 | I4 | None | Active scale number |
| RunningPatternName | DV | 523 | A[50] | None | Name of pattern when a pattern image is saved. |
| HSAtTactileZ | DV | 524 | F8 | 3732 | Captured Z value when height sensor trips on tactile surface during needle to height sensor offsets. NOTE: This value is now in user units (as of FmXP 5.3a85). |
| NdIAtTactileZ_V1 | DV | 525 | F8 | 3733 | Captured Z value when valve 1 needle (nozzle) touches tactile during needle to height sensor offsets. NOTE: This value is now in user units (as of FmXP 5.3a85). |
| HSAtScaleLidZ | DV | 526 | F8 | 3734 | Captured Z value when height sensor detects scale lid. "ScaleNumber" vid 522 denotes which scale. NOTE: This value is now in user units (as of FmXP 5.3a85). |
| NdIAtTactileZ_V2 | DV | 527 | F8 | 3747 | Height sense at tactile Z position valve 2 |
| HSAtPurgeLidZ | DV | 528 | F8 | 3748 | Height sense at purge lid Z position valve 1 (user units) |
| SubstrateCornerTL | DV | 529 | A[40] | 3800 | Substrate top left corner location |
| SubstrateCornerBR | DV | 530 | A[40] | 3800 | Substrate bottom left corner location |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------|-----------|-----|-----------|--|---|
| HSAtScale2LidZ | DV | 531 | F8 | 3734 | Height sense at scale 2 lid Z position (user units) |
| TactileCenter | DV | 532 | A[40] | 3802 | Tactile center (user units) |
| SSPinXY | DV | 533 | A[40] | 8005 8006 | Service Station pin XY location |
| SSPinScore | DV | 534 | I2 | 8005 | Service Station pin fiducial score |
| XYDotOffsetXY | DV | 535 | A[40] | 8015 8016 8017 8018 8019 8020 8021 | XY dot offset location |
| XYDotOffsetScore | DV | 536 | I2 | 8015 8016 8017 8018 8019 8020 8021 | XY dot offset fiducial score |
| WaferCount | DV | 550 | U4 | 3632 | Wafer count |
| WaferStatus | DV | 551 | U4 | 3635 | Wafer status |
| WaferSlotNumber | DV | 552 | U4 | 3633 | Wafer slot number |
| MultiFlowrates_V1 | DV | 560 | F8[50] | 4014 | Multiple Flow Rates for valve 1 |
| MultiFlowrates_V2 | DV | 561 | F8[50] | 4015 | Multiple Flow Rates for valve 2 |
| CarrierSeqAtDisp_L1 | DV | 571 | I4 | 2001 2002 8404 | Carrier sequence at dispense station lane 1 |
| CarrierSeqAtDisp_L2 | DV | 572 | I4 | 2003 2004 8406 | Carrier sequence at dispense station lane 2 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------------------|-----------|-----|-----------|------------------------------|--|
| PromptedSetupScriptFilename | DV | 573 | A[100] | 4001 4002 4022 4023 | Prompted setup script filename |
| NewParameterDouble | DV | 574 | F8 | 8033 | New parameter (double) |
| OldParameterDouble | DV | 575 | F8 | 8033 | Old parameter (double) |
| PurgeEnabled1 | EC | 600 | Boolean | None | This Boolean flag indicates whether periodic purging operations are enabled for Valve 1. |
| MeasFlowEnabled1 | EC | 601 | Boolean | None | This Boolean flag indicates whether periodic flow rate calibration operations are enabled for Valve 1. |
| PurgeEnabled2 | EC | 602 | Boolean | None | This Boolean flag indicates whether periodic purging operations are enabled for Valve 2. |
| MeasFlowEnabled2 | EC | 603 | Boolean | None | This Boolean flag indicates whether periodic flow rate calibration operations are enabled for Valve 2. |
| BoardFrequency | EC | 610 | U4 | None | This value is set by the station controller to the board frequency it requires collection event 2010 to occur. The default is zero which prevents collection event 2010 from triggering. |
| TemperatureDVUpdate | EC | 611 | Boolean | None | Set by the station controller to turn heater temperature data variable updating on (TRUE) or off (FALSE). The default value is TRUE. |
| FidLocTol | EC | 620 | U2 | None | Fiducial location tolerance |
| DiagDistTol | EC | 621 | U2 | None | Diagnostic distance tolerance (Vision – fiducials) |
| OperatorID | EC | 630 | A[6] | None | Operator ID |
| WaferLotNumber | EC | 631 | A[7] | None | Wafer lot number |
| WaferScribeNumber | EC | 632 | A[20] | None | Wafer scribe number |
| RecipeSelectionStatus | EC | 633 | I2 | None | Recipe selection status |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------------------|-----------|-----|-----------|---------------------------|---|
| NumberOfRuns | EC | 634 | A[6] | None | Number of program runs (production) |
| NumberOfRunsEnabled | EC | 635 | Boolean | None | Number of program runs enabled (production) |
| LotID | EC | 636 | A[100] | None | Lot ID |
| ProgramProcessID | EC | 637 | A[100] | None | Program process ID |
| PPSelectStatus | SV | 638 | U2 | None | PP select status |
| DWVCalibStatus | SV | 639 | U2 | None | Dispense Weight Calibration status code |
| FlowRateCalibStatus | SV | 640 | U2 | None | Flow Rate Calibration status code |
| DWCA_MaxPressure | DV | 641 | F8 | 5040 5042 5043 | DWCA max fluid pressure |
| DWCA_DotWeightAtMaxPressure | DV | 642 | F8 | 5042 5043 | DWCA dot weight at maximum pressure |
| DWCA_MinPressure | DV | 643 | F8 | 5040 5041 5043 | DWCA minimum pressure |
| DWCA_DotWeightAtMinPressure | DV | 644 | F8 | 5041 5043 | DWCA dot weight at minimum pressure |
| DWCA_DesiredDotWeight | DV | 645 | F8 | 5040 5043 | DWCA desired dot weight |
| DWCA_FinalDotWeight | DV | 646 | F8 | 5043 | DWCA final dot weight |
| DWCA_PressureAtFinalDotWeight | DV | 647 | F8 | 5043 | DWCA pressure at final dot weight |
| DWCA_DeviationMaxPC | DV | 648 | F8 | 5040 5043 | DWCA deviation max percent |
| DWCA_IntermediateDotWeight | DV | 649 | F8 | 5044 | DWCA intermediate dot weight |
| DWCA_IntermediatePressure | DV | 650 | F8 | 5044 | DWCA intermediate pressure |
| DWCA_StartingPressure | DV | 651 | F8 | 5046 | DWCA starting pressure |
| DWCA_StartingDotWeight | DV | 652 | F8 | 5046 | DWCA starting dot weight |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|-----|-----------|---------------------------|---|
| CameraXFieldMils | SV | 700 | U2 | None | The size in mils of the X coordinate axis field of view seen by the camera. |
| CameraYFieldMils | SV | 701 | U2 | None | The size in mils of the Y coordinate axis field of view seen by the camera. |
| TempHtr1Chan1 | DV | 801 | F8 | 5014 | Temperature heater 1, channel 1 |
| TempHtr1Chan2 | DV | 802 | F8 | 5014 | Temperature heater 1, channel 2 |
| TempHtr1Chan3 | DV | 803 | F8 | 5014 | Temperature heater 1, channel 3 |
| TempHtr1Chan4 | DV | 804 | F8 | 5014 | Temperature heater 1, channel 4 |
| TempHtr1Chan5 | DV | 805 | F8 | 5014 | Temperature heater 1, channel 5 |
| TempHtr1Chan6 | DV | 806 | F8 | 5014 | Temperature heater 1, channel 6 |
| TempHtr1Chan7 | DV | 807 | F8 | 5014 | Temperature heater 1, channel 7 |
| TempHtr1Chan8 | DV | 808 | F8 | 5014 | Temperature heater 1, channel 8 |
| TempHtr1Chan9 | DV | 809 | F8 | 5014 | Temperature heater 1, channel 9 |
| TempHtr1Chan10 | DV | 810 | F8 | 5014 | Temperature heater 1, channel 10 |
| TempHtr1Chan11 | DV | 811 | F8 | 5014 | Temperature heater 1, channel 11 |
| TempHtr1Chan12 | DV | 812 | F8 | 5014 | Temperature heater 1, channel 12 |
| TempHtr1Chan13 | DV | 813 | F8 | 5014 | Temperature heater 1, channel 13 |
| TempHtr1Chan14 | DV | 814 | F8 | 5014 | Temperature heater 1, channel 14 |
| TempHtr1Chan15 | DV | 815 | F8 | 5014 | Temperature heater 1, channel 15 |
| TempHtr1Chan16 | DV | 816 | F8 | 5014 | Temperature heater 1, channel 16 |
| TempHtr1Chan17 | DV | 817 | F8 | 5014 | Temperature heater 1, channel 17 |
| TempHtr2Chan1 | DV | 818 | F8 | 5014 | Temperature heater 2, channel 1 |
| TempHtr2Chan2 | DV | 819 | F8 | 5014 | Temperature heater 2, channel 2 |
| TempHtr2Chan3 | DV | 820 | F8 | 5014 | Temperature heater 2, channel 3 |
| TempHtr2Chan4 | DV | 821 | F8 | 5014 | Temperature heater 2, channel 4 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------|-----------|-----|-----------|---------------------------|----------------------------------|
| TempHtr2Chan5 | DV | 822 | F8 | 5014 | Temperature heater 2, channel 5 |
| TempHtr2Chan6 | DV | 823 | F8 | 5014 | Temperature heater 2, channel 6 |
| TempHtr2Chan7 | DV | 824 | F8 | 5014 | Temperature heater 2, channel 7 |
| TempHtr2Chan8 | DV | 825 | F8 | 5014 | Temperature heater 2, channel 8 |
| TempHtr2Chan9 | DV | 826 | F8 | 5014 | Temperature heater 2, channel 9 |
| TempHtr2Chan10 | DV | 827 | F8 | 5014 | Temperature heater 2, channel 10 |
| TempHtr2Chan11 | DV | 828 | F8 | 5014 | Temperature heater 2, channel 11 |
| TempHtr2Chan12 | DV | 829 | F8 | 5014 | Temperature heater 2, channel 12 |
| TempHtr2Chan13 | DV | 830 | F8 | 5014 | Temperature heater 2, channel 13 |
| TempHtr2Chan14 | DV | 831 | F8 | 5014 | Temperature heater 2, channel 14 |
| TempHtr2Chan15 | DV | 832 | F8 | 5014 | Temperature heater 2, channel 15 |
| TempHtr2Chan16 | DV | 833 | F8 | 5014 | Temperature heater 2, channel 16 |
| TempHtr2Chan17 | DV | 834 | F8 | 5014 | Temperature heater 2, channel 17 |
| TempHtr3Chan1 | DV | 835 | F8 | 5014 | Temperature heater 3, channel 1 |
| TempHtr3Chan2 | DV | 836 | F8 | 5014 | Temperature heater 3, channel 2 |
| TempHtr3Chan3 | DV | 837 | F8 | 5014 | Temperature heater 3, channel 3 |
| TempHtr3Chan4 | DV | 838 | F8 | 5014 | Temperature heater 3, channel 4 |
| TempHtr3Chan5 | DV | 839 | F8 | 5014 | Temperature heater 3, channel 5 |
| TempHtr3Chan6 | DV | 840 | F8 | 5014 | Temperature heater 3, channel 6 |
| TempHtr3Chan7 | DV | 841 | F8 | 5014 | Temperature heater 3, channel 7 |
| TempHtr3Chan8 | DV | 842 | F8 | 5014 | Temperature heater 3, channel 8 |
| TempHtr3Chan9 | DV | 843 | F8 | 5014 | Temperature heater 3, channel 9 |
| TempHtr3Chan10 | DV | 844 | F8 | 5014 | Temperature heater 3, channel 10 |
| TempHtr3Chan11 | DV | 845 | F8 | 5014 | Temperature heater 3, channel 11 |
| TempHtr3Chan12 | DV | 846 | F8 | 5014 | Temperature heater 3, channel 12 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------|-----------|------|-----------|---------------------------|---|
| TempHtr3Chan13 | DV | 847 | F8 | 5014 | Temperature heater 3, channel 13 |
| TempHtr3Chan14 | DV | 848 | F8 | 5014 | Temperature heater 3, channel 14 |
| TempHtr3Chan15 | DV | 849 | F8 | 5014 | Temperature heater 3, channel 15 |
| TempHtr3Chan16 | DV | 850 | F8 | 5014 | Temperature heater 3, channel 16 |
| TempHtr3Chan17 | DV | 851 | F8 | 5014 | Temperature heater 3, channel 17 |
| TempHtr4Chan1 | DV | 852 | F8 | 5014 | Temperature heater 4, channel 1 |
| TempHtr4Chan2 | DV | 853 | F8 | 5014 | Temperature heater 4, channel 2 |
| TempHtr4Chan3 | DV | 854 | F8 | 5014 | Temperature heater 4, channel 3 |
| TempHtr4Chan4 | DV | 855 | F8 | 5014 | Temperature heater 4, channel 4 |
| TempHtr4Chan5 | DV | 856 | F8 | 5014 | Temperature heater 4, channel 5 |
| TempHtr4Chan6 | DV | 857 | F8 | 5014 | Temperature heater 4, channel 6 |
| TempHtr4Chan7 | DV | 858 | F8 | 5014 | Temperature heater 4, channel 7 |
| TempHtr4Chan8 | DV | 859 | F8 | 5014 | Temperature heater 4, channel 8 |
| TempHtr4Chan9 | DV | 860 | F8 | 5014 | Temperature heater 4, channel 9 |
| TempHtr4Chan10 | DV | 861 | F8 | 5014 | Temperature heater 4, channel 10 |
| TempHtr4Chan11 | DV | 862 | F8 | 5014 | Temperature heater 4, channel 11 |
| TempHtr4Chan12 | DV | 863 | F8 | 5014 | Temperature heater 4, channel 12 |
| TempHtr4Chan13 | DV | 864 | F8 | 5014 | Temperature heater 4, channel 13 |
| TempHtr4Chan14 | DV | 865 | F8 | 5014 | Temperature heater 4, channel 14 |
| TempHtr4Chan15 | DV | 866 | F8 | 5014 | Temperature heater 4, channel 15 |
| TempHtr4Chan16 | DV | 867 | F8 | 5014 | Temperature heater 4, channel 16 |
| TempHtr4Chan17 | DV | 868 | F8 | 5014 | Temperature heater 4, channel 17 |
| ALARMTEXT | DV | 1000 | A[40] | None | The Alarm Text (ALTX) for the most recently transitioned Alarm. |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------|-----------|------|-----------|---------------------------|---|
| ALARMSEVERITYCODE | DV | 1001 | U1 | None | The Severity Code (ALCD low-order 7 bits) for the most recently transitioned alarm. |
| FMWMostRecentError | DV | 1002 | U2 | None | FMW most recent error |
| SpHtr1Chan1 | SV | 1101 | F8 | None | Set point heater 1 channel 1 |
| SpHtr1Chan2 | SV | 1102 | F8 | None | Set point heater 1 channel 2 |
| SpHtr1Chan3 | SV | 1103 | F8 | None | Set point heater 1 channel 3 |
| SpHtr1Chan4 | SV | 1104 | F8 | None | Set point heater 1 channel 4 |
| SpHtr1Chan5 | SV | 1105 | F8 | None | Set point heater 1 channel 5 |
| SpHtr1Chan6 | SV | 1106 | F8 | None | Set point heater 1 channel 6 |
| SpHtr1Chan7 | SV | 1107 | F8 | None | Set point heater 1 channel 7 |
| SpHtr1Chan8 | SV | 1108 | F8 | None | Set point heater 1 channel 8 |
| SpHtr1Chan9 | SV | 1109 | F8 | None | Set point heater 1 channel 9 |
| SpHtr1Chan10 | SV | 1110 | F8 | None | Set point heater 1 channel 10 |
| SpHtr1Chan11 | SV | 1111 | F8 | None | Set point heater 1 channel 11 |
| SpHtr1Chan12 | SV | 1112 | F8 | None | Set point heater 1 channel 12 |
| SpHtr1Chan13 | SV | 1113 | F8 | None | Set point heater 1 channel 13 |
| SpHtr1Chan14 | SV | 1114 | F8 | None | Set point heater 1 channel 14 |
| SpHtr1Chan15 | SV | 1115 | F8 | None | Set point heater 1 channel 15 |
| SpHtr1Chan16 | SV | 1116 | F8 | None | Set point heater 1 channel 16 |
| SpHtr1Chan17 | SV | 1117 | F8 | None | Set point heater 1 channel 17 |
| SpHtr2Chan1 | SV | 1118 | F8 | None | Set point heater 2 channel 1 |
| SpHtr2Chan2 | SV | 1119 | F8 | None | Set point heater 2 channel 2 |
| SpHtr2Chan3 | SV | 1120 | F8 | None | Set point heater 2 channel 3 |
| SpHtr2Chan4 | SV | 1121 | F8 | None | Set point heater 2 channel 4 |
| SpHtr2Chan5 | SV | 1122 | F8 | None | Set point heater 2 channel 5 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------|-----------|------|-----------|---------------------------|-------------------------------|
| SpHtr2Chan6 | SV | 1123 | F8 | None | Set point heater 2 channel 6 |
| SpHtr2Chan7 | SV | 1124 | F8 | None | Set point heater 2 channel 7 |
| SpHtr2Chan8 | SV | 1125 | F8 | None | Set point heater 2 channel 8 |
| SpHtr2Chan9 | SV | 1126 | F8 | None | Set point heater 2 channel 9 |
| SpHtr2Chan10 | SV | 1127 | F8 | None | Set point heater 2 channel 10 |
| SpHtr2Chan11 | SV | 1128 | F8 | None | Set point heater 2 channel 11 |
| SpHtr2Chan12 | SV | 1129 | F8 | None | Set point heater 2 channel 12 |
| SpHtr2Chan13 | SV | 1130 | F8 | None | Set point heater 2 channel 13 |
| SpHtr2Chan14 | SV | 1131 | F8 | None | Set point heater 2 channel 14 |
| SpHtr2Chan15 | SV | 1132 | F8 | None | Set point heater 2 channel 15 |
| SpHtr2Chan16 | SV | 1133 | F8 | None | Set point heater 2 channel 16 |
| SpHtr2Chan17 | SV | 1134 | F8 | None | Set point heater 2 channel 17 |
| SpHtr3Chan1 | SV | 1135 | F8 | None | Set point heater 3 channel 1 |
| SpHtr3Chan2 | SV | 1136 | F8 | None | Set point heater 3 channel 2 |
| SpHtr3Chan3 | SV | 1137 | F8 | None | Set point heater 3 channel 3 |
| SpHtr3Chan4 | SV | 1138 | F8 | None | Set point heater 3 channel 4 |
| SpHtr3Chan5 | SV | 1139 | F8 | None | Set point heater 3 channel 5 |
| SpHtr3Chan6 | SV | 1140 | F8 | None | Set point heater 3 channel 6 |
| SpHtr3Chan7 | SV | 1141 | F8 | None | Set point heater 3 channel 7 |
| SpHtr3Chan8 | SV | 1142 | F8 | None | Set point heater 3 channel 8 |
| SpHtr3Chan9 | SV | 1143 | F8 | None | Set point heater 3 channel 9 |
| SpHtr3Chan10 | SV | 1144 | F8 | None | Set point heater 3 channel 10 |
| SpHtr3Chan11 | SV | 1145 | F8 | None | Set point heater 3 channel 11 |
| SpHtr3Chan12 | SV | 1146 | F8 | None | Set point heater 3 channel 12 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------|-----------|------|-----------|---------------------------|-------------------------------|
| SpHtr3Chan13 | SV | 1147 | F8 | None | Set point heater 3 channel 13 |
| SpHtr3Chan14 | SV | 1148 | F8 | None | Set point heater 3 channel 14 |
| SpHtr3Chan15 | SV | 1149 | F8 | None | Set point heater 3 channel 15 |
| SpHtr3Chan16 | SV | 1150 | F8 | None | Set point heater 3 channel 16 |
| SpHtr3Chan17 | SV | 1151 | F8 | None | Set point heater 3 channel 17 |
| SpHtr4Chan1 | SV | 1152 | F8 | None | Set point heater 4 channel 1 |
| SpHtr4Chan2 | SV | 1153 | F8 | None | Set point heater 4 channel 2 |
| SpHtr4Chan3 | SV | 1154 | F8 | None | Set point heater 4 channel 3 |
| SpHtr4Chan4 | SV | 1155 | F8 | None | Set point heater 4 channel 4 |
| SpHtr4Chan5 | SV | 1156 | F8 | None | Set point heater 4 channel 5 |
| SpHtr4Chan6 | SV | 1157 | F8 | None | Set point heater 4 channel 6 |
| SpHtr4Chan7 | SV | 1158 | F8 | None | Set point heater 4 channel 7 |
| SpHtr4Chan8 | SV | 1159 | F8 | None | Set point heater 4 channel 8 |
| SpHtr4Chan9 | SV | 1160 | F8 | None | Set point heater 4 channel 9 |
| SpHtr4Chan10 | SV | 1161 | F8 | None | Set point heater 4 channel 10 |
| SpHtr4Chan11 | SV | 1162 | F8 | None | Set point heater 4 channel 11 |
| SpHtr4Chan12 | SV | 1163 | F8 | None | Set point heater 4 channel 12 |
| SpHtr4Chan13 | SV | 1164 | F8 | None | Set point heater 4 channel 13 |
| SpHtr4Chan14 | SV | 1165 | F8 | None | Set point heater 4 channel 14 |
| SpHtr4Chan15 | SV | 1166 | F8 | None | Set point heater 4 channel 15 |
| SpHtr4Chan16 | SV | 1167 | F8 | None | Set point heater 4 channel 16 |
| SpHtr4Chan17 | SV | 1168 | F8 | None | Set point heater 4 channel 17 |
| OffsetHtr1Chan1 | SV | 1201 | F8 | None | Offset heater 1 channel 1 |
| OffsetHtr1Chan2 | SV | 1202 | F8 | None | Offset heater 1 channel 2 |
| OffsetHtr1Chan3 | SV | 1203 | F8 | None | Offset heater 1 channel 3 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|----------------------------|
| OffsetHtr1Chan4 | SV | 1204 | F8 | None | Offset heater 1 channel 4 |
| OffsetHtr1Chan5 | SV | 1205 | F8 | None | Offset heater 1 channel 5 |
| OffsetHtr1Chan6 | SV | 1206 | F8 | None | Offset heater 1 channel 6 |
| OffsetHtr1Chan7 | SV | 1207 | F8 | None | Offset heater 1 channel 7 |
| OffsetHtr1Chan8 | SV | 1208 | F8 | None | Offset heater 1 channel 8 |
| OffsetHtr1Chan9 | SV | 1209 | F8 | None | Offset heater 1 channel 9 |
| OffsetHtr1Chan10 | SV | 1210 | F8 | None | Offset heater 1 channel 10 |
| OffsetHtr1Chan11 | SV | 1211 | F8 | None | Offset heater 1 channel 11 |
| OffsetHtr1Chan12 | SV | 1212 | F8 | None | Offset heater 1 channel 12 |
| OffsetHtr1Chan13 | SV | 1213 | F8 | None | Offset heater 1 channel 13 |
| OffsetHtr1Chan14 | SV | 1214 | F8 | None | Offset heater 1 channel 14 |
| OffsetHtr1Chan15 | SV | 1215 | F8 | None | Offset heater 1 channel 15 |
| OffsetHtr1Chan16 | SV | 1216 | F8 | None | Offset heater 1 channel 16 |
| OffsetHtr1Chan17 | SV | 1217 | F8 | None | Offset heater 1 channel 17 |
| OffsetHtr2Chan1 | SV | 1218 | F8 | None | Offset heater 2 channel 1 |
| OffsetHtr2Chan2 | SV | 1219 | F8 | None | Offset heater 2 channel 2 |
| OffsetHtr2Chan3 | SV | 1220 | F8 | None | Offset heater 2 channel 3 |
| OffsetHtr2Chan4 | SV | 1221 | F8 | None | Offset heater 2 channel 4 |
| OffsetHtr2Chan5 | SV | 1222 | F8 | None | Offset heater 2 channel 5 |
| OffsetHtr2Chan6 | SV | 1223 | F8 | None | Offset heater 2 channel 6 |
| OffsetHtr2Chan7 | SV | 1224 | F8 | None | Offset heater 2 channel 7 |
| OffsetHtr2Chan8 | SV | 1225 | F8 | None | Offset heater 2 channel 8 |
| OffsetHtr2Chan9 | SV | 1226 | F8 | None | Offset heater 2 channel 9 |
| OffsetHtr2Chan10 | SV | 1227 | F8 | None | Offset heater 2 channel 10 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|----------------------------|
| OffsetHtr2Chan11 | SV | 1228 | F8 | None | Offset heater 2 channel 11 |
| OffsetHtr2Chan12 | SV | 1229 | F8 | None | Offset heater 2 channel 12 |
| OffsetHtr2Chan13 | SV | 1230 | F8 | None | Offset heater 2 channel 13 |
| OffsetHtr2Chan14 | SV | 1231 | F8 | None | Offset heater 2 channel 14 |
| OffsetHtr2Chan15 | SV | 1232 | F8 | None | Offset heater 2 channel 15 |
| OffsetHtr2Chan16 | SV | 1233 | F8 | None | Offset heater 2 channel 16 |
| OffsetHtr2Chan17 | SV | 1234 | F8 | None | Offset heater 2 channel 17 |
| OffsetHtr3Chan1 | SV | 1235 | F8 | None | Offset heater 3 channel 1 |
| OffsetHtr3Chan2 | SV | 1236 | F8 | None | Offset heater 3 channel 2 |
| OffsetHtr3Chan3 | SV | 1237 | F8 | None | Offset heater 3 channel 3 |
| OffsetHtr3Chan4 | SV | 1238 | F8 | None | Offset heater 3 channel 4 |
| OffsetHtr3Chan5 | SV | 1239 | F8 | None | Offset heater 3 channel 5 |
| OffsetHtr3Chan6 | SV | 1240 | F8 | None | Offset heater 3 channel 6 |
| OffsetHtr3Chan7 | SV | 1241 | F8 | None | Offset heater 3 channel 7 |
| OffsetHtr3Chan8 | SV | 1242 | F8 | None | Offset heater 3 channel 8 |
| OffsetHtr3Chan9 | SV | 1243 | F8 | None | Offset heater 3 channel 9 |
| OffsetHtr3Chan10 | SV | 1244 | F8 | None | Offset heater 3 channel 10 |
| OffsetHtr3Chan11 | SV | 1245 | F8 | None | Offset heater 3 channel 11 |
| OffsetHtr3Chan12 | SV | 1246 | F8 | None | Offset heater 3 channel 12 |
| OffsetHtr3Chan13 | SV | 1247 | F8 | None | Offset heater 3 channel 13 |
| OffsetHtr3Chan14 | SV | 1248 | F8 | None | Offset heater 3 channel 14 |
| OffsetHtr3Chan15 | SV | 1249 | F8 | None | Offset heater 3 channel 15 |
| OffsetHtr3Chan16 | SV | 1250 | F8 | None | Offset heater 3 channel 16 |
| OffsetHtr3Chan17 | SV | 1251 | F8 | None | Offset heater 3 channel 17 |
| OffsetHtr4Chan1 | SV | 1252 | F8 | None | Offset heater 4 channel 1 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------------|-----------|------|-----------|---------------------------|---|
| OffsetHtr4Chan2 | SV | 1253 | F8 | None | Offset heater 4 channel 2 |
| OffsetHtr4Chan3 | SV | 1254 | F8 | None | Offset heater 4 channel 3 |
| OffsetHtr4Chan4 | SV | 1255 | F8 | None | Offset heater 4 channel 4 |
| OffsetHtr4Chan5 | SV | 1256 | F8 | None | Offset heater 4 channel 5 |
| OffsetHtr4Chan6 | SV | 1257 | F8 | None | Offset heater 4 channel 6 |
| OffsetHtr4Chan7 | SV | 1258 | F8 | None | Offset heater 4 channel 7 |
| OffsetHtr4Chan8 | SV | 1259 | F8 | None | Offset heater 4 channel 8 |
| OffsetHtr4Chan9 | SV | 1260 | F8 | None | Offset heater 4 channel 9 |
| OffsetHtr4Chan10 | SV | 1261 | F8 | None | Offset heater 4 channel 10 |
| OffsetHtr4Chan11 | SV | 1262 | F8 | None | Offset heater 4 channel 11 |
| OffsetHtr4Chan12 | SV | 1263 | F8 | None | Offset heater 4 channel 12 |
| OffsetHtr4Chan13 | SV | 1264 | F8 | None | Offset heater 4 channel 13 |
| OffsetHtr4Chan14 | SV | 1265 | F8 | None | Offset heater 4 channel 14 |
| OffsetHtr4Chan15 | SV | 1266 | F8 | None | Offset heater 4 channel 15 |
| OffsetHtr4Chan16 | SV | 1267 | F8 | None | Offset heater 4 channel 16 |
| OffsetHtr4Chan17 | SV | 1268 | F8 | None | Offset heater 4 channel 17 |
| AF_L1S1 | SV | 1269 | F8 | None | Airflow lane 1 station 1 |
| AF_L1S2 | SV | 1270 | F8 | None | Airflow lane 1 station 2 |
| AF_L1S3 | SV | 1271 | F8 | None | Airflow lane 1 station 3 |
| AF_L2S1 | SV | 1272 | F8 | None | Airflow lane 2 station 1 |
| AF_L2S2 | SV | 1273 | F8 | None | Airflow lane 2 station 2 |
| AF_L2S3 | SV | 1274 | F8 | None | Airflow lane 2 station 3 |
| AF_L1S1_Limits_Enabled | SV | 1275 | A[4] | None | Airflow lane 1 station 1 limits enabled |
| AF_L1S1_UpperLimitOffset | SV | 1276 | F8 | None | Airflow lane 1 station 1 upper limit offset |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------------|-----------|------|-----------|---------------------------|--|
| AF_L1S1_LowerLimitOffset | SV | 1277 | F8 | None | Airflow lane 1 station 1 lower limit offset |
| AF_L1S2_Limits_Enabled | SV | 1278 | A[4] | None | Airflow lane 1 station 2 limits enabled |
| AF_L1S2_UpperLimitOffset | SV | 1279 | F8 | None | Airflow lane 1 station 2 upper limit offset |
| AF_L1S2_LowerLimitOffset | SV | 1280 | F8 | None | Airflow lane 1 station 2 lower limit offset |
| AF_L1S3_Limits_Enabled | SV | 1281 | A[4] | None | Airflow lane 1 station 3 limits enabled |
| AF_L1S3_UpperLimitOffset | SV | 1282 | F8 | None | Airflow lane 1 station 3 upper limit offset |
| AF_L1S3_LowerLimitOffset | SV | 1283 | F8 | None | Airflow lane 1 station 3 lower limit offset |
| AF_L2S1_Limits_Enabled | SV | 1284 | A[4] | None | Airflow lane 2 station 1 limits enabled |
| AF_L2S1_UpperLimitOffset | SV | 1285 | F8 | None | Airflow lane 2 station 1 upper limit offset |
| AF_L2S1_LowerLimitOffset | SV | 1286 | F8 | None | Airflow lane 2 station 1 lower limit offset |
| AF_L2S2_Limits_Enabled | SV | 1287 | A[4] | None | Airflow lane 2 station 2 limits enabled |
| AF_L2S2_UpperLimitOffset | SV | 1288 | F8 | None | Airflow lane 2 station 2 upper limit offset |
| AF_L2S2_LowerLimitOffset | SV | 1289 | F8 | None | Airflow lane 2 station 2 lower limit offset |
| AF_L2S3_Limits_Enabled | SV | 1290 | A[4] | None | Airflow lane 2 station 3 limits enabled |
| AF_L2S3_UpperLimitOffset | SV | 1291 | F8 | None | Airflow lane 2 station 3 upper limit offset |
| AF_L2S3_LowerLimitOffset | SV | 1292 | F8 | None | Airflow lane 2 station 3 lower limit offset |
| AF_L1S1_SetPoint | SV | 1293 | F8 | None | Airflow lane 1 station 1 set point |
| AF_L1S2_SetPoint | SV | 1294 | F8 | None | Airflow lane 1 station 2 set point |
| AF_L1S3_SetPoint | SV | 1295 | F8 | None | Airflow lane 1 station 3 set point |
| AF_L2S1_SetPoint | SV | 1296 | F8 | None | Airflow lane 2 station 1 set point |
| AF_L2S2_SetPoint | SV | 1297 | F8 | None | Airflow lane 2 station 2 set point |
| AF_L2S3_SetPoint | SV | 1298 | F8 | None | Airflow lane 2 station 3 set point |
| AF_L1S1_StandbyEnabled | SV | 1300 | A[4] | None | Airflow lane 1 station 1 standby enabled |
| AF_L1S1_StandbyTime | SV | 1301 | I4 | None | Airflow lane 1 station 1 standby time |
| AF_L1S1_StandbyTemp | SV | 1302 | F8 | None | Airflow lane 1 station 1 standby temperature |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------------|-----------|------|-----------|---------------------------|---|
| AF_L1S1_StandbyAF | SV | 1303 | F8 | None | Airflow lane 1 station 1 standby airflow |
| AF_L1S1_RampEnabled | SV | 1304 | A[4] | None | Airflow lane 1 station 1 ramp enabled |
| AF_L1S1_RampTime | SV | 1305 | I4 | None | Airflow lane 1 station 1 ramp time |
| AF_L1S1_RampTemp | SV | 1306 | F8 | None | Airflow lane 1 station 1 ramp temperature |
| AF_L1S1_RampAF | SV | 1307 | F8 | None | Airflow lane 1 station 1 ramp airflow |
| AF_L1S1_NonProdEnabled | SV | 1308 | A[4] | None | Airflow lane 1 station 1 non-production enabled |
| AF_L1S1_NonProdTemp | SV | 1309 | F8 | None | Airflow lane 1 station 1 non-production temperature |
| AF_L1S1_NonProdAF | SV | 1310 | F8 | None | Airflow lane 1 station 1 non-production airflow |
| AF_L1S2_StandbyEnabled | SV | 1311 | A[4] | None | Airflow lane 1 station 2 standby enabled |
| AF_L1S2_StandbyTime | SV | 1312 | I4 | None | Airflow lane 1 station 2 standby time |
| AF_L1S2_StandbyTemp | SV | 1313 | F8 | None | Airflow lane 1 station 2 standby temperature |
| AF_L1S2_StandbyAF | SV | 1314 | F8 | None | Airflow lane 1 station 2 standby airflow |
| AF_L1S2_RampEnabled | SV | 1315 | A[4] | None | Airflow lane 1 station 2 ramp enabled |
| AF_L1S2_RampTime | SV | 1316 | I4 | None | Airflow lane 1 station 2 ramp time |
| AF_L1S2_RampTemp | SV | 1317 | F8 | None | Airflow lane 1 station 2 ramp temperature |
| AF_L1S2_RampAF | SV | 1318 | F8 | None | Airflow lane 1 station 2 ramp airflow |
| AF_L1S2_NonProdEnabled | SV | 1319 | A[4] | None | Airflow lane 1 station 2 non-production enabled |
| AF_L1S2_NonProdTemp | SV | 1320 | F8 | None | Airflow lane 1 station 2 non-production temperature |
| AF_L1S2_NonProdAF | SV | 1321 | F8 | None | Airflow lane 1 station 2 non-production airflow |
| AF_L1S3_StandbyEnabled | SV | 1322 | A[4] | None | Airflow lane 1 station 3 standby enabled |
| AF_L1S3_StandbyTime | SV | 1323 | I4 | None | Airflow lane 1 station 3 standby time |
| AF_L1S3_StandbyTemp | SV | 1324 | F8 | None | Airflow lane 1 station 3 standby temperature |
| AF_L1S3_StandbyAF | SV | 1325 | F8 | None | Airflow lane 1 station 3 standby airflow |
| AF_L1S3_RampEnabled | SV | 1326 | A[4] | None | Airflow lane 1 station 3 ramp enabled |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------------|-----------|------|-----------|---------------------------|---|
| AF_L1S3_RampTime | SV | 1327 | I4 | None | Airflow lane 1 station 3 ramp time |
| AF_L1S3_RampTemp | SV | 1328 | F8 | None | Airflow lane 1 station 3 ramp temperature |
| AF_L1S3_RampAF | SV | 1329 | F8 | None | Airflow lane 1 station 3 ramp airflow |
| AF_L1S3_NonProdEnabled | SV | 1330 | A[4] | None | Airflow lane 1 station 3 non-production enabled |
| AF_L1S3_NonProdTemp | SV | 1331 | F8 | None | Airflow lane 1 station 3 non-production temperature |
| AF_L1S3_NonProdAF | SV | 1332 | F8 | None | Airflow lane 1 station 3 non-production airflow |
| AF_L2S1_StandbyEnabled | SV | 1333 | A[4] | None | Airflow lane 2 station 1 standby enabled |
| AF_L2S1_StandbyTime | SV | 1334 | I4 | None | Airflow lane 2 station 1 standby time |
| AF_L2S1_StandbyTemp | SV | 1335 | F8 | None | Airflow lane 2 station 1 standby temperature |
| AF_L2S1_StandbyAF | SV | 1336 | F8 | None | Airflow lane 2 station 1 standby airflow |
| AF_L2S1_RampEnabled | SV | 1337 | A[4] | None | Airflow lane 2 station 1 ramp enabled |
| AF_L2S1_RampTime | SV | 1338 | I4 | None | Airflow lane 2 station 1 ramp time |
| AF_L2S1_RampTemp | SV | 1339 | F8 | None | Airflow lane 2 station 1 ramp temperature |
| AF_L2S1_RampAF | SV | 1340 | F8 | None | Airflow lane 2 station 1 ramp airflow |
| AF_L2S1_NonProdEnabled | SV | 1341 | A[4] | None | Airflow lane 2 station 1 non-production enabled |
| AF_L2S1_NonProdTemp | SV | 1342 | F8 | None | Airflow lane 2 station 1 non-production temperature |
| AF_L2S1_NonProdAF | SV | 1343 | F8 | None | Airflow lane 2 station 1 non-production airflow |
| AF_L2S2_StandbyEnabled | SV | 1344 | A[4] | None | Airflow lane 2 station 2 standby enabled |
| AF_L2S2_StandbyTime | SV | 1345 | I4 | None | Airflow lane 2 station 2 standby time |
| AF_L2S2_StandbyTemp | SV | 1346 | F8 | None | Airflow lane 2 station 2 standby temperature |
| AF_L2S2_StandbyAF | SV | 1347 | F8 | None | Airflow lane 2 station 2 standby airflow |
| AF_L2S2_RampEnabled | SV | 1348 | A[4] | None | Airflow lane 2 station 2 ramp enabled |
| AF_L2S2_RampTime | SV | 1349 | I4 | None | Airflow lane 2 station 2 ramp time |
| AF_L2S2_RampTemp | SV | 1350 | F8 | None | Airflow lane 2 station 2 ramp temperature |
| AF_L2S2_RampAF | SV | 1351 | F8 | None | Airflow lane 2 station 2 ramp airflow |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------------|-----------|------|-----------|---------------------------|---|
| AF_L2S2_NonProdEnabled | SV | 1352 | A[4] | None | Airflow lane 2 station 2 non-production enabled |
| AF_L2S2_NonProdTemp | SV | 1353 | F8 | None | Airflow lane 2 station 2 non-production temperature |
| AF_L2S2_NonProdAF | SV | 1354 | F8 | None | Airflow lane 2 station 2 non-production airflow |
| AF_L2S3_StandbyEnabled | SV | 1355 | A[4] | None | Airflow lane 2 station 3 standby enabled |
| AF_L2S3_StandbyTime | SV | 1356 | I4 | None | Airflow lane 2 station 3 standby time |
| AF_L2S3_StandbyTemp | SV | 1357 | F8 | None | Airflow lane 2 station 3 standby temperature |
| AF_L2S3_StandbyAF | SV | 1358 | F8 | None | Airflow lane 2 station 3 standby airflow |
| AF_L2S3_RampEnabled | SV | 1359 | A[4] | None | Airflow lane 2 station 3 ramp enabled |
| AF_L2S3_RampTime | SV | 1360 | I4 | None | Airflow lane 2 station 3 ramp time |
| AF_L2S3_RampTemp | SV | 1361 | F8 | None | Airflow lane 2 station 3 ramp temperature |
| AF_L2S3_RampAF | SV | 1362 | F8 | None | Airflow lane 2 station 3 ramp airflow |
| AF_L2S3_NonProdEnabled | SV | 1363 | A[4] | None | Airflow lane 2 station 3 non-production enabled |
| AF_L2S3_NonProdTemp | SV | 1364 | F8 | None | Airflow lane 2 station 3 non-production temperature |
| AF_L2S3_NonProdAF | SV | 1365 | F8 | None | Airflow lane 2 station 3 non-production airflow |
| ULimitHtr1Chan1 | SV | 1401 | F8 | None | Heater 1 channel 1 airflow upper limit |
| ULimitHtr1Chan2 | SV | 1402 | F8 | None | Heater 1 channel 2 airflow upper limit |
| ULimitHtr1Chan3 | SV | 1403 | F8 | None | Heater 1 channel 3 airflow upper limit |
| ULimitHtr1Chan4 | SV | 1404 | F8 | None | Heater 1 channel 4 airflow upper limit |
| ULimitHtr1Chan5 | SV | 1405 | F8 | None | Heater 1 channel 5 airflow upper limit |
| ULimitHtr1Chan6 | SV | 1406 | F8 | None | Heater 1 channel 6 airflow upper limit |
| ULimitHtr1Chan7 | SV | 1407 | F8 | None | Heater 1 channel 7 airflow upper limit |
| ULimitHtr1Chan8 | SV | 1408 | F8 | None | Heater 1 channel 8 airflow upper limit |
| ULimitHtr1Chan9 | SV | 1409 | F8 | None | Heater 1 channel 9 airflow upper limit |
| ULimitHtr1Chan10 | SV | 1410 | F8 | None | Heater 1 channel 10 airflow upper limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|---|
| ULimitHtr1Chan11 | SV | 1411 | F8 | None | Heater 1 channel 11 airflow upper limit |
| ULimitHtr1Chan12 | SV | 1412 | F8 | None | Heater 1 channel 12 airflow upper limit |
| ULimitHtr1Chan13 | SV | 1413 | F8 | None | Heater 1 channel 13 airflow upper limit |
| ULimitHtr1Chan14 | SV | 1414 | F8 | None | Heater 1 channel 14 airflow upper limit |
| ULimitHtr1Chan15 | SV | 1415 | F8 | None | Heater 1 channel 15 airflow upper limit |
| ULimitHtr1Chan16 | SV | 1416 | F8 | None | Heater 1 channel 16 airflow upper limit |
| ULimitHtr1Chan17 | SV | 1417 | F8 | None | Heater 1 channel 17 airflow upper limit |
| ULimitHtr2Chan1 | SV | 1418 | F8 | None | Heater 2 channel 1 airflow upper limit |
| ULimitHtr2Chan2 | SV | 1419 | F8 | None | Heater 2 channel 2 airflow upper limit |
| ULimitHtr2Chan3 | SV | 1420 | F8 | None | Heater 2 channel 3 airflow upper limit |
| ULimitHtr2Chan4 | SV | 1421 | F8 | None | Heater 2 channel 4 airflow upper limit |
| ULimitHtr2Chan5 | SV | 1422 | F8 | None | Heater 2 channel 5 airflow upper limit |
| ULimitHtr2Chan6 | SV | 1423 | F8 | None | Heater 2 channel 6 airflow upper limit |
| ULimitHtr2Chan7 | SV | 1424 | F8 | None | Heater 2 channel 7 airflow upper limit |
| ULimitHtr2Chan8 | SV | 1425 | F8 | None | Heater 2 channel 8 airflow upper limit |
| ULimitHtr2Chan9 | SV | 1426 | F8 | None | Heater 2 channel 9 airflow upper limit |
| ULimitHtr2Chan10 | SV | 1427 | F8 | None | Heater 2 channel 10 airflow upper limit |
| ULimitHtr2Chan11 | SV | 1428 | F8 | None | Heater 2 channel 11 airflow upper limit |
| ULimitHtr2Chan12 | SV | 1429 | F8 | None | Heater 2 channel 12 airflow upper limit |
| ULimitHtr2Chan13 | SV | 1430 | F8 | None | Heater 2 channel 13 airflow upper limit |
| ULimitHtr2Chan14 | SV | 1431 | F8 | None | Heater 2 channel 14 airflow upper limit |
| ULimitHtr2Chan15 | SV | 1432 | F8 | None | Heater 2 channel 15 airflow upper limit |
| ULimitHtr2Chan16 | SV | 1433 | F8 | None | Heater 2 channel 16 airflow upper limit |
| ULimitHtr2Chan17 | SV | 1434 | F8 | None | Heater 2 channel 17 airflow upper limit |
| ULimitHtr3Chan1 | SV | 1435 | F8 | None | Heater 3 channel 1 airflow upper limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|---|
| ULimitHtr3Chan2 | SV | 1436 | F8 | None | Heater 3 channel 2 airflow upper limit |
| ULimitHtr3Chan3 | SV | 1437 | F8 | None | Heater 3 channel 3 airflow upper limit |
| ULimitHtr3Chan4 | SV | 1438 | F8 | None | Heater 3 channel 4 airflow upper limit |
| ULimitHtr3Chan5 | SV | 1439 | F8 | None | Heater 3 channel 5 airflow upper limit |
| ULimitHtr3Chan6 | SV | 1440 | F8 | None | Heater 3 channel 6 airflow upper limit |
| ULimitHtr3Chan7 | SV | 1441 | F8 | None | Heater 3 channel 7 airflow upper limit |
| ULimitHtr3Chan8 | SV | 1442 | F8 | None | Heater 3 channel 8 airflow upper limit |
| ULimitHtr3Chan9 | SV | 1443 | F8 | None | Heater 3 channel 9 airflow upper limit |
| ULimitHtr3Chan10 | SV | 1444 | F8 | None | Heater 3 channel 10 airflow upper limit |
| ULimitHtr3Chan11 | SV | 1445 | F8 | None | Heater 3 channel 11 airflow upper limit |
| ULimitHtr3Chan12 | SV | 1446 | F8 | None | Heater 3 channel 12 airflow upper limit |
| ULimitHtr3Chan13 | SV | 1447 | F8 | None | Heater 3 channel 13 airflow upper limit |
| ULimitHtr3Chan14 | SV | 1448 | F8 | None | Heater 3 channel 14 airflow upper limit |
| ULimitHtr3Chan15 | SV | 1449 | F8 | None | Heater 3 channel 15 airflow upper limit |
| ULimitHtr3Chan16 | SV | 1450 | F8 | None | Heater 3 channel 16 airflow upper limit |
| ULimitHtr3Chan17 | SV | 1451 | F8 | None | Heater 3 channel 17 airflow upper limit |
| ULimitHtr4Chan1 | SV | 1452 | F8 | None | Heater 4 channel 1 airflow upper limit |
| ULimitHtr4Chan2 | SV | 1453 | F8 | None | Heater 4 channel 2 airflow upper limit |
| ULimitHtr4Chan3 | SV | 1454 | F8 | None | Heater 4 channel 3 airflow upper limit |
| ULimitHtr4Chan4 | SV | 1455 | F8 | None | Heater 4 channel 4 airflow upper limit |
| ULimitHtr4Chan5 | SV | 1456 | F8 | None | Heater 4 channel 5 airflow upper limit |
| ULimitHtr4Chan6 | SV | 1457 | F8 | None | Heater 4 channel 6 airflow upper limit |
| ULimitHtr4Chan7 | SV | 1458 | F8 | None | Heater 4 channel 7 airflow upper limit |
| ULimitHtr4Chan8 | SV | 1459 | F8 | None | Heater 4 channel 8 airflow upper limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|---|
| ULimitHtr4Chan9 | SV | 1460 | F8 | None | Heater 4 channel 9 airflow upper limit |
| ULimitHtr4Chan10 | SV | 1461 | F8 | None | Heater 4 channel 10 airflow upper limit |
| ULimitHtr4Chan11 | SV | 1462 | F8 | None | Heater 4 channel 11 airflow upper limit |
| ULimitHtr4Chan12 | SV | 1463 | F8 | None | Heater 4 channel 12 airflow upper limit |
| ULimitHtr4Chan13 | SV | 1464 | F8 | None | Heater 4 channel 13 airflow upper limit |
| ULimitHtr4Chan14 | SV | 1465 | F8 | None | Heater 4 channel 14 airflow upper limit |
| ULimitHtr4Chan15 | SV | 1466 | F8 | None | Heater 4 channel 15 airflow upper limit |
| ULimitHtr4Chan16 | SV | 1467 | F8 | None | Heater 4 channel 16 airflow upper limit |
| ULimitHtr4Chan17 | SV | 1468 | F8 | None | Heater 4 channel 17 airflow upper limit |
| LLimitHtr1Chan1 | SV | 1469 | F8 | None | Heater 1 channel 1 airflow lower limit |
| LLimitHtr1Chan2 | SV | 1470 | F8 | None | Heater 1 channel 2 airflow lower limit |
| LLimitHtr1Chan3 | SV | 1471 | F8 | None | Heater 1 channel 3 airflow lower limit |
| LLimitHtr1Chan4 | SV | 1472 | F8 | None | Heater 1 channel 4 airflow lower limit |
| LLimitHtr1Chan5 | SV | 1473 | F8 | None | Heater 1 channel 5 airflow lower limit |
| LLimitHtr1Chan6 | SV | 1474 | F8 | None | Heater 1 channel 6 airflow lower limit |
| LLimitHtr1Chan7 | SV | 1475 | F8 | None | Heater 1 channel 7 airflow lower limit |
| LLimitHtr1Chan8 | SV | 1476 | F8 | None | Heater 1 channel 8 airflow lower limit |
| LLimitHtr1Chan9 | SV | 1477 | F8 | None | Heater 1 channel 9 airflow lower limit |
| LLimitHtr1Chan10 | SV | 1478 | F8 | None | Heater 1 channel 10 airflow lower limit |
| LLimitHtr1Chan11 | SV | 1479 | F8 | None | Heater 1 channel 11 airflow lower limit |
| LLimitHtr1Chan12 | SV | 1480 | F8 | None | Heater 1 channel 12 airflow lower limit |
| LLimitHtr1Chan13 | SV | 1481 | F8 | None | Heater 1 channel 13 airflow lower limit |
| LLimitHtr1Chan14 | SV | 1482 | F8 | None | Heater 1 channel 14 airflow lower limit |
| LLimitHtr1Chan15 | SV | 1483 | F8 | None | Heater 1 channel 15 airflow lower limit |
| LLimitHtr1Chan16 | SV | 1484 | F8 | None | Heater 1 channel 16 airflow lower limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|---|
| LLimitHtr1Chan17 | SV | 1485 | F8 | None | Heater 1 channel 17 airflow lower limit |
| LLimitHtr2Chan1 | SV | 1486 | F8 | None | Heater 2 channel 1 airflow lower limit |
| LLimitHtr2Chan2 | SV | 1487 | F8 | None | Heater 2 channel 2 airflow lower limit |
| LLimitHtr2Chan3 | SV | 1488 | F8 | None | Heater 2 channel 3 airflow lower limit |
| LLimitHtr2Chan4 | SV | 1489 | F8 | None | Heater 2 channel 4 airflow lower limit |
| LLimitHtr2Chan5 | SV | 1490 | F8 | None | Heater 2 channel 5 airflow lower limit |
| LLimitHtr2Chan6 | SV | 1491 | F8 | None | Heater 2 channel 6 airflow lower limit |
| LLimitHtr2Chan7 | SV | 1492 | F8 | None | Heater 2 channel 7 airflow lower limit |
| LLimitHtr2Chan8 | SV | 1493 | F8 | None | Heater 2 channel 8 airflow lower limit |
| LLimitHtr2Chan9 | SV | 1494 | F8 | None | Heater 2 channel 9 airflow lower limit |
| LLimitHtr2Chan10 | SV | 1495 | F8 | None | Heater 2 channel 10 airflow lower limit |
| LLimitHtr2Chan11 | SV | 1496 | F8 | None | Heater 2 channel 11 airflow lower limit |
| LLimitHtr2Chan12 | SV | 1497 | F8 | None | Heater 2 channel 12 airflow lower limit |
| LLimitHtr2Chan13 | SV | 1498 | F8 | None | Heater 2 channel 13 airflow lower limit |
| LLimitHtr2Chan14 | SV | 1499 | F8 | None | Heater 2 channel 14 airflow lower limit |
| LLimitHtr2Chan15 | SV | 1500 | F8 | None | Heater 2 channel 15 airflow lower limit |
| LLimitHtr2Chan16 | SV | 1501 | F8 | None | Heater 2 channel 16 airflow lower limit |
| LLimitHtr2Chan17 | SV | 1502 | F8 | None | Heater 2 channel 17 airflow lower limit |
| LLimitHtr3Chan1 | SV | 1503 | F8 | None | Heater 3 channel 1 airflow lower limit |
| LLimitHtr3Chan2 | SV | 1504 | F8 | None | Heater 3 channel 2 airflow lower limit |
| LLimitHtr3Chan3 | SV | 1505 | F8 | None | Heater 3 channel 3 airflow lower limit |
| LLimitHtr3Chan4 | SV | 1506 | F8 | None | Heater 3 channel 4 airflow lower limit |
| LLimitHtr3Chan5 | SV | 1507 | F8 | None | Heater 3 channel 5 airflow lower limit |
| LLimitHtr3Chan6 | SV | 1508 | F8 | None | Heater 3 channel 6 airflow lower limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|------|-----------|---------------------------|---|
| LLimitHtr3Chan7 | SV | 1509 | F8 | None | Heater 3 channel 7 airflow lower limit |
| LLimitHtr3Chan8 | SV | 1510 | F8 | None | Heater 3 channel 8 airflow lower limit |
| LLimitHtr3Chan9 | SV | 1511 | F8 | None | Heater 3 channel 9 airflow lower limit |
| LLimitHtr3Chan10 | SV | 1512 | F8 | None | Heater 3 channel 10 airflow lower limit |
| LLimitHtr3Chan11 | SV | 1513 | F8 | None | Heater 3 channel 11 airflow lower limit |
| LLimitHtr3Chan12 | SV | 1514 | F8 | None | Heater 3 channel 12 airflow lower limit |
| LLimitHtr3Chan13 | SV | 1515 | F8 | None | Heater 3 channel 13 airflow lower limit |
| LLimitHtr3Chan14 | SV | 1516 | F8 | None | Heater 3 channel 14 airflow lower limit |
| LLimitHtr3Chan15 | SV | 1517 | F8 | None | Heater 3 channel 15 airflow lower limit |
| LLimitHtr3Chan16 | SV | 1518 | F8 | None | Heater 3 channel 16 airflow lower limit |
| LLimitHtr3Chan17 | SV | 1519 | F8 | None | Heater 3 channel 17 airflow lower limit |
| LLimitHtr4Chan1 | SV | 1520 | F8 | None | Heater 4 channel 1 airflow lower limit |
| LLimitHtr4Chan2 | SV | 1521 | F8 | None | Heater 4 channel 2 airflow lower limit |
| LLimitHtr4Chan3 | SV | 1522 | F8 | None | Heater 4 channel 3 airflow lower limit |
| LLimitHtr4Chan4 | SV | 1523 | F8 | None | Heater 4 channel 4 airflow lower limit |
| LLimitHtr4Chan5 | SV | 1524 | F8 | None | Heater 4 channel 5 airflow lower limit |
| LLimitHtr4Chan6 | SV | 1525 | F8 | None | Heater 4 channel 6 airflow lower limit |
| LLimitHtr4Chan7 | SV | 1526 | F8 | None | Heater 4 channel 7 airflow lower limit |
| LLimitHtr4Chan8 | SV | 1527 | F8 | None | Heater 4 channel 8 airflow lower limit |
| LLimitHtr4Chan9 | SV | 1528 | F8 | None | Heater 4 channel 9 airflow lower limit |
| LLimitHtr4Chan10 | SV | 1529 | F8 | None | Heater 4 channel 10 airflow lower limit |
| LLimitHtr4Chan11 | SV | 1530 | F8 | None | Heater 4 channel 11 airflow lower limit |
| LLimitHtr4Chan12 | SV | 1531 | F8 | None | Heater 4 channel 12 airflow lower limit |
| LLimitHtr4Chan13 | SV | 1532 | F8 | None | Heater 4 channel 13 airflow lower limit |
| LLimitHtr4Chan14 | SV | 1533 | F8 | None | Heater 4 channel 14 airflow lower limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------------------|-----------|------|-----------|---------------------------|---|
| LLimitHtr4Chan15 | SV | 1534 | F8 | None | Heater 4 channel 15 airflow lower limit |
| LLimitHtr4Chan16 | SV | 1535 | F8 | None | Heater 4 channel 16 airflow lower limit |
| LLimitHtr4Chan17 | SV | 1536 | F8 | None | Heater 4 channel 17 airflow lower limit |
| FluidLevelState | SV | 1538 | I4 | None | Fluid syringe level sensor state |
| DHLinearFluidSensorPct | SV | 1539 | I4 | None | Dispense head linear fluid sensor level % |
| DHLinearFluidSensorState | SV | 1540 | I4 | None | Dispense head linear fluid sensor state |
| ActiveNozzleState | SV | 1541 | Boolean | None | Active Nozzle On/Off state |
| LibraryPatternFilename | SV | 1546 | A[100] | None | Library pattern filename |
| LibraryPatternPath | SV | 1547 | A[100] | None | Library pattern path |
| c_ScaleFMWPerUnit | SV | 1552 | A[30] | None | Scale of FMW units to machine units |
| FirmwareRev | SV | 1553 | F8 | None | Main board firmware revision |
| FirmwareBuild | SV | 1554 | A[40] | None | Main board firmware build |
| c_ModuleAutoMode | SV | 1555 | A[4] | None | Module skip auto mode |
| c_ModuleOutgoingFlowControl | SV | 1556 | I4 | None | Module skip outgoing flow control |
| c_ModuleIncomingFlowControl | SV | 1557 | I4 | None | Module skip incoming flow control |
| c_ModuleNumberOfRetries | SV | 1558 | I4 | None | Module skip number of retries |
| c_ModuleTeachWindowMode | SV | 1559 | I4 | None | Module skip teach window mode |
| OperatingSystem | SV | 1560 | A[20] | None | Computer operating system |
| Software | SV | 1561 | A[20] | None | Fluidmove FmXP/FmNT |
| SoftwareRev | SV | 1562 | A[20] | None | Fluidmove version |
| GemInstallVersion | SV | 1563 | A[20] | None | SECS/GEM software version |
| GemGCPFileVersion | SV | 1564 | A[20] | None | SECS/GEM .gcp file version |
| GemDriverVersion | SV | 1565 | A[20] | None | SECS/GEM software driver version |
| c_UILanguage | SV | 1566 | I4 | None | User interface language |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------------------------|-----------|-----------|-----------|---------------------------|---|
| ClearPinsMove | SV | 1567 | F8 | None | Clear stop pins move distance |
| S2RequestDelayMove | SV | 1568 | F8 | None | Station 2 request delay move time |
| S3RequestDelayMove | SV | 1569 | F8 | None | Station 3 request delay move time |
| ClearDownPinDelay | SV | 1570 | F8 | None | Clear down pin delay time |
| S3OutFirst | SV | 1571 | F8 | None | Station 3 out first |
| ec_ValvePressSetLmoOffsetUsr_V1 | EC | 1800 | F8 | None | Electronic Valve Pressure setting LMO for valve 1 |
| ec_CoolingPressSetLmoOffsetUsr_V1 | EC | 1801 | F8 | None | Electronic Cooling Pressure setting LMO for valve 1 |
| ec_FluidPressSetLmoOffsetUsr_V1 | EC | 1802 | F8 | None | Electronic Fluid Pressure setting LMO for valve 1 |
| ec_ValvePressReadLmoOffsetUsr_V1 | EC | 1803 | F8 | None | Electronic Valve Pressure reading LMO for valve 1 |
| ec_CoolingPressReadLmoOffsetUsr_V1 | EC | 1804 | F8 | None | Electronic Cooling Pressure reading LMO for valve 1 |
| ec_FluidPressReadLmoOffsetUsr_V1 | EC | 1805 | F8 | None | Electronic Fluid Pressure reading LMO for valve 1 |
| ec_ValvePressSetLmoOffsetUsr_V2 | EC | 1806 | F8 | None | Electronic Valve Pressure setting LMO for valve 2 |
| ec_CoolingPressSetLmoOffsetUsr_V2 | EC | 1807 | F8 | None | Electronic Cooling Pressure setting LMO for valve 2 |
| ec_FluidPressSetLmoOffsetUsr_V2 | EC | 1808 | F8 | None | Electronic Fluid Pressure setting LMO for valve 2 |
| ec_ValvePressReadLmoOffsetUsr_V2 | EC | 1809 | F8 | None | Electronic Valve Pressure reading LMO for valve 2 |
| ec_CoolingPressReadLmoOffsetUsr_V2 | EC | 1810 | F8 | None | Electronic Cooling Pressure reading LMO for valve 2 |
| ec_FluidPressReadLmoOffsetUsr_V2 | EC | 1811 | F8 | None | Electronic Fluid Pressure reading LMO for valve 2 |
| sv_PressLmoOffsetUserUnit_V1 | SV | 1830 | A[10] | None | Units that E/P LMO offsets are stored in for valve 1: “kPa” or “psi” |
| sv_PressLmoOffsetUserUnit_V2 | SV | 1831 | A[10] | None | Units that E/P LMO offsets are stored in for valve 2: “kPa” or “psi” |
| ConfigParmRejectedID | DV | 5999 | I4 | 3650 | This data variable contains the EC ID of the invalid configuration parameter rejected by the equipment. |
| FmConfig.ini File Variables | | 6000-6768 | | | See Appendix D – FmConfig.ini File Variables |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--|-----------|----------------|-----------|--|--|
| CurrentFidFoundXY | DV | 7000 | A[40] | 8000 8001 8801 8802 8803 8804 8805 8806 8807 8808 | XY location of currently found fiducials. As fiducials are found, this variable will be updated and either collection event 8000 (for pattern fiducials), 8001 (for workpiece 1 fiducials) or 8002 (for workpiece fiducials 2) will be triggered. By using this variable, fiducials can be collected at the moment they are found. The XY locations will also be stored in variables 7801 (for workpiece 1) or 7802 (for workpiece 2) or sequentially to variables 7001 to 7300 (for pattern fiducials) if it is more efficient to upload all Fiducial locations at once at the end of the program. |
| PATTFidFoundXY_1 – PATTFidFoundXY_300 | DV | 7001- 7300 | A[40] | 8000 8001 | Sequential XY location of found pattern fiducials in order dictated by program (300 max) Collection event 2002 is an existing event that is triggered when dispensing is done. A report can be created containing all or some of the Fiducial locations and then tied to CE 2002. |
| CurrentHsFoundXYZ | DV | 7400 | A[40] | 8400 | Current height sense location |
| HsFoundXYZ_1 - HsFoundXYZ_300 | DV | 7401 - 7700 | A[40] | 8400 | Sequential height sense XYZ locations found by program (300 max) |
| HeightSenseOriginConv1 | DV | 7701 | A[60] | 8401 | Height sense origin on conveyor 1 |
| HeightSenseOriginConv2 | EC | 7702 | F8 | 8402 | Height sense origin on conveyor 2 |
| LmoHeightSenseLane1UserUnits | EC | 7703 | F8 | 3717 | Local machine offsets lane 1 user units |
| LmoHeightSenseLane2UserUnits | EC | 7704 | A[30] | 3717 | Local machine offsets lane 2 user units |
| LmoWpFrame | EC | 7705 | A[30] | 3713 | Local machine offsets workpiece frame |
| LmoWpFidFoundXY_1 | DV | 7706 | A[50] | 3718 | Local machine offsets workpiece fid found XY location 1 |
| LmoWpFidFoundXY_2 | DV | 7707 | A[40] | 3719 | Local machine offsets workpiece fid found XY location 2 |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------------|-----------|------|-----------|---------------------------|--|
| LmoWpFidFoundScore_1 | DV | 7708 | A[40] | 3718 | Local machine offsets workpiece fid found XY location 1 score |
| LmoWpFidFoundScore_2 | DV | 7709 | I2 | 3761 | Local machine offsets workpiece fid found XY location 2 score |
| LuclImageXY | DV | 7710 | I2 | 8002 8003 | Lookup camera image XY location |
| LuclImageScore | DV | 7711 | A[40] | 8002 8003 | Lookup camera image XY location score |
| BoardSequenceNumber | EC | 7800 | Boolean | None | Carrier Sequence # (sequential) This number is reset each time "GO" is pressed. For a running board count processed since power up, see existing SV 106 (BoardCount). |
| WPFidFoundXY_1 | DV | 7801 | U4 | 8800 | Workpiece fiducial #1 XY (actual found) |
| WPFidFoundXY_2 | DV | 7802 | A[40] | 8801 | Workpiece fiducial #2 XY (actual found) |
| WPFidFoundScore_1 | DV | 7803 | A[40] | 8802 | Workpiece fiducial #1 image score |
| WPFidFoundScore_2 | DV | 7804 | I2 | 8802 | Workpiece fiducial #2 image score |
| UseKeepoutZones | EC | 7808 | Boolean | None | Enable keep out zones |
| TrcWriteToFile | EC | 7809 | Boolean | None | Trace write to file enable |
| TrcWriteToDbgWindow | EC | 7810 | Boolean | None | Trace write to debug window enable |
| TrcBufferedWrite | EC | 7811 | Boolean | None | Trace buffered write enable |
| DbgWriteToFile | EC | 7812 | Boolean | None | Debug write to file enable |
| DbgWriteToDbgWindow | EC | 7813 | Boolean | None | Debug write to debug window enable |
| DbgBufferedWrite | EC | 7814 | Boolean | None | Debug buffered write enable |
| DbgSuppressFileCreation | EC | 7815 | Boolean | None | Debug suppress file creation enable |
| DbgEnableAllLogs | EC | 7816 | Boolean | None | Debug enable all logs (enable) |
| TrcEnableAllLogs | EC | 7817 | Boolean | None | Trace enable all logs (enable) |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--|-----------|-------------------|-----------|--|--|
| CurrentFidFoundScore | DV | 10000 | I2 | 8000 8001 8801 8802 8803 8804 8805 8806 8807 8808 | Current fiducial found image score. This can be a workpiece or pattern image. |
| PattFidFoundScore_1 – PattFidFoundScore_300 | DV | 10001 to 10300 | I2 | 2002 | Sequential fiducial scores of found pattern fiducials in order dictated by program (300 max) |
| fd_OnTime | DV | 11000 | I2 | 3002 3004 3005 3009 3010 3011 | Fluid on time |
| fd_DwellSecs | DV | 11001 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid dwell time |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|-------|-----------|--|-------------------------------|
| fd_DispenseGap | DV | 11002 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid dispense gap |
| fd_Notes | DV | 11003 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid file notes |
| fd_MidmoveCount1 | DV | 11004 | A[100] | 3002 3004 3005 | Fluid mid-move count1 |
| fd_MidmoveCount2 | DV | 11005 | A[30] | 3009 3010 3011 | Fluid mid-move count2 |
| fd_DownSpeed | DV | 11006 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve down speed |
| fd_DownAccel | DV | 11007 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve down acceleration |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------|-----------|-------|-----------|--|------------------------------------|
| fd_SettleSecs | DV | 11008 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve dispense settling time |
| fd_OnVectorMode | DV | 11009 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid On vector mode |
| fd_OffVectorMode | DV | 11010 | I4 | 3002 3004 3005 3009 3010 3011 | Fluid Off vector mode |
| fd_NumShots | DV | 11011 | I4 | 3002 3004 3005 3009 3010 3011 | Fluid number of shots (Jet Valve) |
| fd_MultishotZDelta | DV | 11012 | I4 | 3002 3004 3005 3009 3010 3011 | Fluid multi-shot Z delta |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------|-----------|-------|-----------|--|-------------------------------|
| fd_UpSpeed | DV | 11013 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve up speed |
| fd_UpAccel | DV | 11014 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve up acceleration |
| fd_RetractDistance | DV | 11015 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve retract distance |
| fd_Suckback | DV | 11016 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid suck-back time |
| fd_PostRetractDwell | DV | 11017 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid post retract dwell time |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------|-----------|-------|-----------|--|-----------------------------|
| fd_AssistDelay | DV | 11018 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid assist delay |
| fd_AssistDuration | DV | 11019 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid assist duration |
| fd_ValveOnTime | DV | 11020 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve on time |
| fd_DotSpacing | DV | 11021 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid dispensed dot spacing |
| fd_Acceleration | DV | 11022 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid acceleration |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------|-----------|-------|-----------|--|-----------------------------------|
| fd_EncEnable | DV | 11023 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder acceleration |
| fd_EncForwardSpd | DV | 11024 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder forward speed |
| fd_EncReverseSpd | DV | 11025 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder reverse speed |
| fd_EncAccel | DV | 11026 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder acceleration |
| fd_EncDecel | DV | 11027 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder deceleration |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------|-----------|-------|-----------|--|-------------------------------|
| fd_EncCounts | DV | 11028 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder counts |
| fd_EncSuckback | DV | 11029 | I4 | 3002 3004 3005 3009 3010 3011 | Fluid valve encoder suck-back |
| fl_PremoveDelay | DV | 11100 | I4 | 3002 3004 3005 3009 3010 3011 | Fluid 1 pre-move delay |
| fl_ShutoffDistance | DV | 11101 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 shut off distance |
| fl_DispenseGap | DV | 11102 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 dispense gap |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------------|-----------|-------|-----------|--|-----------------------------------|
| fl_Speed | DV | 11103 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 line speed |
| fl_Weightcontrollinespeed | DV | 11104 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 weight control line speed |
| fl_DwellTime | DV | 11105 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 dwell time |
| fl_RetractDistance | DV | 11106 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 retract distance |
| fl_BacktrackGap | DV | 11107 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 back track gap |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|--------------------|-----------|-------|-----------|--|---------------------------------|
| fl_BacktrackLength | DV | 11108 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 back track length |
| fl_BacktrackSpeed | DV | 11109 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 back track speed |
| fl_Notes | DV | 11110 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 notes |
| fl_DownSpeed | DV | 11111 | A[100] | 3002 3004 3005 3009 3010 3011 | Fluid 1 valve down speed |
| fl_DownAccel | DV | 11112 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 valve down acceleration |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-----------------------------|-----------|-------|-----------|--|------------------------------------|
| fl_UpSpeed | DV | 11113 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 valve up speed |
| fl_UpAccel | DV | 11114 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 valve up acceleration |
| fl_Suckback | DV | 11115 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 suck back time |
| fl_VelocityAdjustmentFactor | DV | 11116 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 velocity adjustment factor |
| fl_FluidOnResponseTime | DV | 11117 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 On response time |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------------|-----------|-------|-----------|--|-----------------------------------|
| fl_FluidOffResponseTime | DV | 11118 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 Off response time |
| fl_Assist1OnResponseTime | DV | 11119 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 assist On response time |
| fl_Assist1OffResponseTime | DV | 11120 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 assist Off response time |
| fl_Assist2OnResponseTime | DV | 11121 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 assist 2 On response time |
| fl_Assist2OffResponseTime | DV | 11122 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 assist 2Off response time |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|-------------------------------------|-----------|-------|-----------|--|---|
| fl_DispenseHeight | DV | 11123 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 dispense height |
| fl_DispenseWidth | DV | 11124 | A[30] | 3002 3004 3005 3009 3010 3011 | Fluid 1 dispense width |
| fc_PurgeEnabled | DV | 11200 | A[30] | 3652 | Fluid purge enabled |
| fc_PurgeDuration | DV | 11201 | A[4] | 3652 | Fluid purge duration |
| fc_PurgeInterval | DV | 11202 | A[30] | 3652 | Fluid purge interval |
| fc_FlowRateEnabled | DV | 11203 | A[30] | 3652 | Fluid flow rate enabled |
| fc_FlowCalibrationInterval | DV | 11204 | A[4] | 3652 | Fluid flow rate calibration interval |
| fc_FlowCalibrationDuration | DV | 11205 | A[30] | 3652 | Fluid flow rate calibration duration |
| fc_DJFlowCalibrationMinWeight | DV | 11206 | A[30] | 3652 | Fluid DJ flow rate calibration minimum weight |
| fc_PercentofMaxDJWeightControlSpeed | DV | 11207 | A[30] | 3652 | Percent of maximum DJ weight control speed |
| fc_SetPurgeOnTimer | DV | 11208 | A[30] | 3652 | Fluid set purge on timer |
| fc_SetFlowRateOnTimer | DV | 11209 | I4 | 3651 | Fluid set flow rate on timer |
| fc_PurgeonRunCount | DV | 11210 | I4 | 3651 | Purge on run count # |
| fc_FlowRateCalibrationonRunCount | DV | 11211 | I4 | 3651 | Do flow rate calibration on run count # |
| fc_FlowCalibrationDispenses | DV | 11212 | I4 | 3651 | Flow rate calibration number of dispenses |
| fc_FlowCalibrationIntervalDelay | DV | 11213 | I4 | 3651 | Flow rate calibration interval delay |
| fc_MinimumFlowRate | DV | 11214 | A[30] | 3652 | Fluid minimum flow rate limit |
| fc_MaximumFlowRate | DV | 11215 | A[30] | 3652 | Fluid maximum flow rate limit |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------------------------|-----------|-------|-----------|---------------------------|--|
| fc_Fluidname | DV | 11216 | A[30] | 3652 | Fluid name |
| fc_PotLifeEnabled | DV | 11217 | A[100] | 3652 | Pot life check enabled |
| fc_Potlife | DV | 11218 | A[4] | 3652 | Pot life time (hours) |
| fc_Potlifefotify | DV | 11219 | A[30] | 3652 | Pot life notify when time is below (hours) |
| fc_ScaleBias | DV | 11220 | A[30] | 3652 | Scale bias |
| fc_ZeroScaleXOffset | DV | 11221 | A[30] | 3652 | Zero scale X offset |
| fc_ZeroScaleYOffset | DV | 11222 | A[30] | 3652 | Zero scale Y offset |
| fc_ZeroScaleZOffset | DV | 11223 | A[30] | 3652 | Zero scale Z offset |
| fc_FlowCalibrationPreMove | DV | 11224 | A[30] | 3652 | Flow rate calibration pre-move |
| fc_FlowCalibrationPostMove | DV | 11225 | A[100] | 3652 | Flow rate calibration post-move |
| fc_FilletBias | DV | 11226 | A[100] | 3652 | Fluid fillet bias |
| fc_BoardsafterLowFluidSensed | DV | 11227 | A[30] | 3652 | Boards to dispense after low fluid sensed |
| fc_LowFluidBoardsToGo | DV | 11228 | I4 | 3651 | Low fluid detected – boards to go until stop |
| fc_EnableLowFluidCheck | DV | 11229 | I4 | 3651 | Enable low fluid check |
| fc_LowFluidCheck | DV | 11230 | A[4] | 3652 | Low fluid check mode |
| fc_DefaultWeightofPrimedFluid | DV | 11231 | I4 | 3651 | Default weight of primed fluid |
| fc_Initialsyringeweight | DV | 11232 | A[30] | 3652 | Initial syringe weight |
| fc_Warningsyringeweight | DV | 11233 | A[30] | 3652 | Warning level syringe weight |
| fc_Criticalsyringeweight | DV | 11234 | A[30] | 3652 | Critical syringe weight |
| fc_AllowFutureThawTime | DV | 11235 | A[30] | 3652 | Allow future thaw time |
| fc_DisplaywarningonlowFluidSense | DV | 11236 | A[4] | 3652 | Display warning on low fluid sense |
| fc_VacuumShutoffDelayTime | DV | 11237 | A[4] | 3652 | Vacuum shutoff delay time |
| fc_VacuumDelayEnabled | DV | 11238 | A[30] | 3652 | Vacuum delay enable |
| fc_VacuumPreShutoffTime | DV | 11239 | A[4] | 3652 | Vacuum pre-shutoff time |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------------------------|-----------|-------|-----------|---------------------------|---|
| fc_VacuumPreShutoffEnabled | DV | 11240 | A[30] | 3652 | Vacuum pre-shutoff enable |
| fc_MultiFlowRateCalibrationEnable | DV | 11241 | A[4] | 3652 | Multi flow rate calibration enable |
| fc_MultiFlowRateCalibrationCount | DV | 11242 | A[4] | 3652 | Multi flow rate calibration enable |
| fc_ResetFlowRateTimer | DV | 11243 | I4 | 3651 | Reset flow rate timer |
| fc_ResetPurgeTimer | DV | 11244 | A[4] | 3652 | Reset purge timer |
| fc_ResetDispenseWeightVerifyTimer | DV | 11245 | A[4] | 3652 | Reset dispense weight verification timer |
| fc_DispenseWeightBlockProduction | DV | 11246 | A[4] | 3652 | Disable dispense weigh calibration if block production active |
| fc_DispenseWeightTarget | DV | 11247 | A[4] | 3652 | Dispense weight calibration target |
| fc_DispenseWeightTimeBetweenDispenses | DV | 11248 | A[30] | 3652 | Dispense weight time between dispenses |
| fc_DispenseWeightMaximumLimit | DV | 11249 | A[30] | 3652 | Dispense weight calibration maximum limit |
| fc_DispenseWeightMinimumLimit | DV | 11250 | A[30] | 3652 | Dispense weight calibration minimum limit |
| fc_DispenseWeightNumberOfDispenses | DV | 11251 | A[30] | 3652 | Dispense weight verification number of dispenses |
| fc_DispenseWeightCheckMaxRange | DV | 11252 | I4 | 3651 | Dispense weight check maximum range enable |
| fc_DispenseWeightMaxRange | DV | 11253 | A[4] | 3652 | Dispense weight maximum range |
| fc_DispenseWeightPurgeBeforeVerify | DV | 11254 | A[30] | 3652 | Dispense weight purge before verify |
| fc_FlowRateBlockProduction | DV | 11255 | A[4] | 3652 | Disable flow rate calibration if block production active |
| fc_ValveAutoBiasBlockProduction | DV | 11256 | A[4] | 3652 | Disable valve auto bias if block production active |
| fc_ValveAutoBiasTargetWeight | DV | 11257 | A[4] | 3652 | Valve auto bias target weight |
| fc_LastComputedValveAutoBias | DV | 11258 | A[30] | 3652 | Last computed valve auto bias value |
| fc_ValveAutoBiasMaximumLimit | DV | 11259 | A[30] | 3652 | Valve auto bias maximum limit |
| fc_ValveAutoBiasMinimumLimit | DV | 11260 | A[30] | 3652 | Valve auto bias minimum limit |
| fc_ValveAutoBiasNumberOfDispenses | DV | 11261 | A[30] | 3652 | Valve auto bias number of dispenses |
| fc_ValveAutoBiasTimeBetweenDispenses | DV | 11262 | I4 | 3651 | Valve auto bias time between dispenses |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------------------------|-----------|-------|-----------|---------------------------|--|
| fc_SkipFirstShotinMFR | DV | 11263 | A[30] | 3652 | Skip first shot in measured flow rate |
| fc_LoadPromptedSetupPSS | DV | 11264 | A[4] | 3652 | Load prompted setup PSS file |
| fc_LoadChangeSyringePSS | DV | 11265 | A[4] | 3652 | Load change syringe PSS file |
| fc_LoadLowFluidPSS | DV | 11266 | A[4] | 3652 | Load low fluid PSS file |
| fc_PromptedSetupPSSFilename | DV | 11267 | A[4] | 3652 | Prompted setup PSS filename |
| fc_ChangeSyringePSSFilename | DV | 11268 | A[100] | 3652 | Change syringe PSS filename |
| fc_LowFluidPSSFilename | DV | 11269 | A[100] | 3652 | Low fluid PSS filename |
| fc_FluxWtBlockProduction | DV | 11270 | A[100] | 3652 | Disable flux weight verification if block production active (enable) |
| fc_FluxWtValveOnTime | DV | 11271 | A[4] | 3652 | Flux weight verification valve on time |
| fc_FluxWtTarget | DV | 11272 | A[30] | 3652 | Flux weight verification target weight |
| fc_FluxWtTimeBetweenDispenses | DV | 11273 | A[30] | 3652 | Flux weight verification time between dispenses |
| fc_FluxWtMaxLimit | DV | 11274 | A[30] | 3652 | Flux weight verification maximum limit |
| fc_FluxWtMinLimit | DV | 11275 | A[30] | 3652 | Flux weight verification minimum limit |
| fc_FluxWtNumberOfDispenses | DV | 11276 | A[30] | 3652 | Flux weight verification number of dispenses |
| fc_FluxWtCheckMaxRange | DV | 11277 | I4 | 3651 | Flux weight verification check max range |
| fc_FluxWtMaxRange | DV | 11278 | A[4] | 3652 | Flux weight verification maximum range |
| fc_FluxWtCheckLimits | DV | 11279 | A[30] | 3652 | Flux weight verification check limits |
| fc_FluxWtPurgeBeforeVerify | DV | 11280 | A[4] | 3652 | Flux weight verification purge before verify |
| fc_FluxWtPurgeBetweenDispenses | DV | 11281 | A[4] | 3652 | Flux weight verification purge between dispenses |
| fc_DJvalveontime | DV | 11282 | A[4] | 3652 | DJ valve on time |
| fc_DJvalveofftime | DV | 11283 | A[30] | 3652 | DJ valve off time |
| fc_Numberofdotsininitialdispense | DV | 11284 | A[30] | 3652 | DJ valve – number of shots in initial dispense |
| fc_Fluxvalveontime | DV | 11285 | I4 | 3651 | Flux valve on time |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---|-----------|-------|-----------|---------------------------|---|
| fc_RuntimeDispenseWeightVerificationEnabled | DV | 11286 | A[30] | 3652 | Runtime dispense weight verification |
| fc_DispenseWeightVerificationInterval | DV | 11287 | A[4] | 3652 | Dispense weight verification interval time |
| fc_DispenseWeightVerificationonRunCount | DV | 11288 | A[30] | 3652 | Dispense weight verification run count |
| fc_DoDispenseWeightVerificationonTimer | DV | 11289 | I4 | 3651 | Do dispense weight verification on timer |
| fc_MaxDeviationAbovePreviousFlowrate | DV | 11290 | I4 | 3651 | Maximum deviation above previous flow rate |
| fc_MaxDeviationBelowPreviousFlowrate | DV | 11291 | A[30] | 3652 | Maximum deviation below previous flow rate |
| fc_PressureSettingUnits_V1 | DV | 11292 | A[30] | 3652 | Pressure setting user units valve 1 |
| fc_FluidPressureSetting_V1 | DV | 11293 | A[10] | 3652 | Fluid pressure setting valve 1 |
| fc_ValvePressureSetting_V1 | DV | 11294 | A[30] | 3652 | Valve pressure setting valve 1 |
| fc_CoolingPressureSetting_V1 | DV | 11295 | A[30] | 3652 | Cooling pressure setting valve 1 |
| fc_FluidPressureTol_V1 | DV | 11296 | A[30] | 3652 | Fluid pressure tolerance valve 1 |
| fc_ValvePressureTol_V1 | DV | 11297 | A[30] | 3652 | Valve pressure tolerance valve 1 |
| fc_CoolingPressureTol_V1 | DV | 11298 | A[30] | 3652 | Cooling pressure tolerance valve 1 |
| fc_DotWeightPressureControlled_V1 | DV | 11299 | A[30] | 3652 | Dot weight is pressure controlled |
| fc_DesiredDotWeight_V1 | SV | 11300 | A[4] | None | Desired dot weight (pressure controlled) |
| fc_MinFluidPressure_V1 | SV | 11301 | A[30] | None | Minimum fluid pressure (pressure controlled dot weight) |
| fc_MaxFluidPressure_V1 | SV | 11302 | A[30] | None | Maximum fluid pressure (pressure controlled dot weight) |
| f_CBoolParm | DV | 11387 | A[4] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CIntParm | DV | 11389 | I4 | 3652 | Generic secs/gem variable when adding new fluid file parameters |
| f_CUIntParm | DV | 11390 | I4 | 3652 | Generic secs/gem variable when adding new fluid file parameters |
| f_CLongParm | DV | 11391 | I4 | 3652 | Generic secs/gem variable when adding new fluid file parameters |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------------|-----------|-------|-----------|---------------------------|---|
| f_CDbIParm | DV | 11392 | A[30] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CStrParm | DV | 11393 | A[100] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CStrParmBlankOK | DV | 11394 | A[100] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CXYFMWBaseParm | DV | 11395 | A[40] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CXYFMWLocalParm | DV | 11396 | A[40] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CXYZFMWLocalParm | DV | 11397 | A[50] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| f_CVariableParm | DV | 11398 | A[40] | 3651 | Generic secs/gem variable when adding new fluid file parameters |
| LastFluidFileParm | DV | 11399 | I2 | 3652 | Generic secs/gem variable when adding new fluid file parameters |
| h_VerifyTimeout | DV | 11400 | I4 | 3654 | Heater verify timeout |
| h_Numberofloops | DV | 11401 | I4 | 3654 | Heater number of loops |
| h_Name | DV | 11410 | A[100] | 3653 | Heater name |
| h_TurnOffDuringFids | DV | 11411 | I4 | 3654 | Turn heater off during fid search |
| h_OutputDuringFids | DV | 11412 | I4 | 3654 | Report heater output during fid finding |
| h_VerifyBeforeDispense | DV | 11413 | I4 | 3654 | Verify heater temp before dispensing |
| h_VerifyUpperLimit | DV | 11414 | I4 | 3654 | Verify heater temp upper limit |
| h_VerifyLowerLimit | DV | 11415 | I4 | 3654 | Verify heater temp lower limit |
| h_SetOffWhenIdle | DV | 11416 | I4 | 3654 | Turn heater off when idle |
| h_WarnBeforeHeaterOff | DV | 11417 | I4 | 3654 | Warn user before turning off heater |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|---------------------------|-----------|-------|-----------|---------------------------|--|
| h_PreventFlowRateIfHtrOff | DV | 11418 | I4 | 3654 | Prevent flow rate calibration if heater is off |
| h_PreventPurgeIfHtrOff | DV | 11419 | I4 | 3654 | Prevent purge if heater is off |
| h_OnOff | DV | 11420 | I4 | 3654 | Heater ON/OFF |
| h_AutoManual | DV | 11421 | I4 | 3654 | Heater auto/manual temperature |
| h_ManualOutputLevel | DV | 11422 | A[30] | 3653 | Heater manual output level |
| h_ScaleUnits | DV | 11423 | I4 | 3654 | Temp scale units (Fahrenheit /Celsius) |
| h_SetPoint | DV | 11424 | A[30] | 3653 | Heater set point |
| h_ProportionalBand | DV | 11425 | I4 | 3654 | Heater proportional band |
| h_Integral | DV | 11426 | I4 | 3654 | Heater integral |
| h_Derivative | DV | 11427 | I4 | 3654 | Heater derivative |
| h_OutputFilter | DV | 11428 | I4 | 3654 | Heater output filter |
| h_HotColdSpread | DV | 11429 | A[30] | 3653 | Heater hot – cold spread |
| h_InputType | DV | 11430 | I4 | 3654 | Heater input type |
| h_InputReadingOffsetBias | DV | 11431 | I4 | 3654 | Heater input reading offset bias |
| h_InputFilter | DV | 11432 | I4 | 3654 | Heater input filter |
| h_OutputEnable | DV | 11433 | I4 | 3654 | Heater output enable |
| h_OutputControlType | DV | 11434 | I4 | 3654 | Heater output control type |
| h_OutputAction | DV | 11435 | I4 | 3654 | Heater output action |
| h_OutputHeatCycleTime | DV | 11436 | I4 | 3654 | Heater output heat cycle time |
| h_OutputHeatLimitPC | DV | 11437 | I4 | 3654 | Heater output heat limit percent |
| h_OutputHeatLimitTime | DV | 11438 | I4 | 3654 | Heater output heat limit time |
| h_Deadband | DV | 11439 | A[30] | 3653 | Heater temp dead band |
| h_Deviation | DV | 11440 | I4 | 3654 | Heater temp deviation |
| h_ProcAlarmDelay | DV | 11441 | I4 | 3654 | Heater process alarm delay |
| h_HighProcAlarmOutput | DV | 11442 | I4 | 3654 | Heater high process alarm output |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|----------------------------|-----------|-------|-----------|---------------------------|-------------------------------------|
| h_HighProcAlarmSetPoint | DV | 11443 | A[30] | 3653 | Heater high process alarm set point |
| h_HighProcAlarmMode | DV | 11444 | I4 | 3654 | Heater high process alarm mode |
| h_LowProcAlarmOutput | DV | 11445 | I4 | 3654 | Heater low process alarm output |
| h_LowProcAlarmSetPoint | DV | 11446 | A[30] | 3653 | Heater low process alarm set point |
| h_LowProcAlarmMode | DV | 11447 | I4 | 3654 | Heater low process alarm mode |
| h_HighDevOutput | DV | 11448 | I4 | 3654 | Heater high device output |
| h_HighDevMode | DV | 11449 | I4 | 3654 | Heater high device mode |
| h_LowDevOutput | DV | 11450 | I4 | 3654 | Heater low device output |
| h_LowDevMode | DV | 11451 | I4 | 3654 | Heater low device mode |
| h_LocalMachineHeaterOffset | DV | 11452 | I4 | 3654 | Heater local machine offset |
| LastHeaterFileParm | DV | 11599 | I2 | 3654 | Last heater file parameter |
| p_version | DV | 11600 | A[30] | 3672 | First program header VID |
| p_units | DV | 11601 | A[30] | 3672 | User units |
| p_fluid1Filename | DV | 11602 | A[100] | 3672 | Fluid filename #1 |
| p_fluid2Filename | DV | 11603 | A[100] | 3672 | Fluid filename #2 |
| p_heater1Filename | DV | 11604 | A[100] | 3672 | Heater filename #1 |
| p_heater2Filename | DV | 11605 | A[100] | 3672 | Heater filename #2 |
| p_heater3Filename | DV | 11606 | A[100] | 3672 | Heater filename #3 |
| p_heater4Filename | DV | 11607 | A[100] | 3672 | Heater filename #4 |
| p_AttachFluidFile | DV | 11608 | A[4] | 3672 | Is fluid file attached |
| p_AttachHeaterFile | DV | 11609 | A[4] | 3672 | Is heater file attached |
| p_MovetoFirstFidLocation | DV | 11610 | A[4] | 3672 | Move to first fid location |
| p_MoveToSystemLocation | DV | 11611 | A[4] | 3672 | Move to system location |
| p_SystemLocationName | DV | 11612 | A[100] | 3672 | System location name |

Table A-1 All Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Related Collection Events | Description |
|------------------------------------|-----------|-------|-----------|---------------------------|--|
| p_SetActiveValve | DV | 11613 | I4 | 3673 | Set active valve |
| p_BatchFids | DV | 11614 | A[4] | 3672 | Use batch fids |
| p_PipelineVision | DV | 11615 | A[4] | 3672 | Use pipeline vision |
| p_AutomaticConveyorWidth | DV | 11616 | A[30] | 3672 | Automatic conveyor width |
| p_AutomaticConveyorWidthTolerance | DV | 11617 | A[30] | 3672 | Automatic conveyor width tolerance |
| p_AutomaticConveyorWidthEnabled | DV | 11618 | A[4] | 3672 | Automatic conveyor width enable |
| p_AutomaticConveyor2Width | DV | 11619 | A[30] | 3672 | Automatic conveyor width conveyor #2 |
| p_AutomaticConveyor2WidthTolerance | DV | 11620 | A[30] | 3672 | Automatic conveyor width tolerance #2 |
| p_AutomaticConveyor2WidthEnabled | DV | 11621 | A[4] | 3672 | Automatic conveyor width enable #2 |
| p_CADImportGeneratedFile | DV | 11622 | A[4] | 3672 | CAD import generated file |
| p_ForceHSONnewpattern | DV | 11623 | A[4] | 3672 | Force height sense on new pattern |
| p_FidSearchAtSafeZ | DV | 11624 | A[4] | 3672 | Fiducial search at safe Z |
| p_BatchHeightSenseCommands | DV | 11625 | A[4] | 3672 | Use batch height sense commands |
| p_BatchHeightSenseProbeDown | DV | 11626 | A[4] | 3672 | Batch height sense with probe down |
| p_PreHeatTime | DV | 11627 | I4 | 3673 | Pre heat time |
| p_ApplyCameraRotationCorrection | DV | 11628 | A[4] | 3672 | Apply camera rotation correction |
| p_Maxtimeboardremainsatdispense | DV | 11629 | I4 | 3673 | Maximum time board remains at dispense station |
| p_DualDispenseMFCTolerance | DV | 11630 | A[30] | 3672 | Dual dispense Measured Flow Rate Calibration tolerance |
| LastProgHeaderParm | DV | 11799 | I2 | 3673 | Last program header VID |

Appendix B Collection Events

B.1 Overview

This appendix lists the collection events that exist at the Equipment.

B.2 Collection Events

Table B-1 contains a list of collection events, related data variables, and a brief description of each event, sorted by CEID number.



NOTE CEID 1 – 65 are standard GEM.

Table B-1 Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|--|
| ControlStateChange | 1 | None | Collection event when there is a change in control state. |
| ProcessStateChange | 2 | None | Collection event when there is a change in process state. |
| GemPPChangeEvent | 3 | None | Collection event when the Operator creates, changes, or deletes a process program. |
| OperatorCommand | 4 | None | Collection event whenever the Operator attempts to control the machine while in the Online - REMOTE state. |
| AbortStarted | 5 | None | Collection event when an abort request was acknowledged and the abort process begins. |
| AbortCompleted | 6 | None | Collection event when the abort process is complete. |
| GemBadDownloadEvent | 7 | None | Collection event after the host downloads a recipe to the equipment upon the equipment's request, the equipment checks the recipe for accuracy. If the process program is invalid, the Collection event. |
| GemControlStateLOCAL | 8 | None | Collection event when Control State changes to LOCAL. |
| GemControlStateREMOTE | 9 | None | Collection event when Control State changes to REMOTE. |
| StartCmd | 14 | None | Collection event when the Operator clicks the GO button from Teach Window or Run Window. |
| StopCmd | 15 | None | Collection event when the Operator clicks the STOP button from Teach Window or Run Window. |
| PauseCmd | 16 | None | Collection event when the Operator clicks the PAUSE button from Teach Window or Run Window and the equipment is in RUNNING state. |
| ResumeCmd | 17 | None | Collection event when the Operator clicks the PAUSE button from Teach Window or Run Window and the equipment is in PAUSED state. |
| AbortCmd | 18 | None | Collection event when the Operator clicks the ABORT button from Teach Window or Run Window. |
| EqConstChange | 20 | None | Collection event to the Host when the Operator changes an Equipment Constant. |
| S10Ack | 21 | None | Collection event to acknowledge the reception of a Host text message. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|--------------------------|------|------------------------|--|
| GemEquipmentOFFLINE | 22 | None | Collection event when Control State changes to Off-Line. |
| GemSpoolingActivated | 23 | None | Collection event when Equipment attempts to send a primary message to the Host and gets a transmit failure while Spooling is enabled. |
| GemSpoolingDeactivated | 24 | None | Collection event after the entire spool file has been read by the Host. |
| GemSpoolTransmitFailure | 25 | None | Collection event if a transmission failure occurs during the period in which the Host is reading the Spooling file. |
| BoardAtDispenseLoc1 | 2001 | 521, 571 | Collection event when the board is at the dispensing location for Conveyor 1 and ready for dispensing. |
| DispensingDone1 | 2002 | 521 | Collection event when dispensing is completed for Conveyor 1. The board is ready to leave the dispensing location. |
| BoardAtDispenseLoc2 | 2003 | 521, 572 | Collection event when the board is at the dispensing location for Conveyor 2 and ready for dispensing. |
| DispensingDone2 | 2004 | 521 | Collection event when dispensing is completed for Conveyor 2. The board is ready to leave the dispensing location. |
| BoardFrequencyDataUpload | 2010 | 106 | Collection event per boat count during a production run. The boat count is specified by equipment constant 610. |
| BarcodeRead | 2050 | 306, 307 | Collection event after a barcode has been successfully read. This event will occur after events BoardAtDispenseLoc1 and BoardAtDispenseLoc2. |
| MachineEmpty | 2051 | None | Collection event when the machine has set idle waiting for a board after a user configurable timeout. |
| NewProgramLoaded | 3001 | 461 | Collection event when a new program is loaded. |
| NewFluidFileLoaded1 | 3002 | SV300 | Collection event when a new fluid parameter file for Valve 1 is loaded. |
| NewHeaterFileLoaded | 3003 | 458 | Collection event when a new heater parameter file is loaded. |
| FluidParametersModified1 | 3004 | SV 300 | Collection event when the fluid parameters for Valve 1 have been changed by an operator. |
| FluidParametersSaved1 | 3005 | SV 300 | Collection event when the fluid parameters for Valve 1 have been saved onto the local mass storage. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------------|------|------------------------------|--|
| ConveyorCodeDownloaded1 | 3008 | None | Collection event when a new conveyor control code (atom) has been downloaded into the Conveyor 1 controller. |
| NewFluidFileLoaded2 | 3009 | SV303 | Collection event when a new fluid parameter file for Valve 2 is loaded by an operator. |
| FluidParametersModified2 | 3010 | SV 303 | Collection event when the fluid parameters for Valve 2 have been changed by an operator. |
| FluidParametersSaved2 | 3011 | SV 303 | Collection event when the fluid parameters for Valve 2 have been saved onto the local mass storage. |
| ConveyorCodeDownloaded2 | 3012 | None | Collection event when a new conveyor control code (atom) has been downloaded into the Conveyor 2 controller. |
| ce_NewOperatorIDNeedsValidation | 3630 | 630 | Collection event after operator ID is entered. |
| ce_WaferLotNumberNeedsValidation | 3631 | 552, 631 | Collection event when verifying wafer lot number entered by operator. |
| ce_WaferCountUpdated | 3632 | 550 | Collection event when wafer count is updated. |
| ce_WaferScribeNeedsValidation | 3633 | 552 | Collection event when verifying each wafer scribe number sent from loader. |
| ce_WaferStart | 3634 | 552, 631 | Collection event when wafer processing is started. |
| ce_WaferComplete | 3635 | None | Collection event when wafer processing is complete. |
| ce_WaferLotComplete | 3636 | None | Collection event when wafer lot is complete. |
| ce_StartRecipeSelection | 3637 | None | Collection event to signal host that recipe download/selection may start. |
| ce_ConfigParmChangedString | 3638 | 450, 451, 453 | Collection event when a string configuration parameter is changed. |
| ce_ConfigParmChangedInt | 3639 | 450, 452, 454 | Collection event when an integer configuration parameter is changed. |
| ce_ConfigParmRejected | 3650 | 5999 | Collection event when a bad configuration parameter has been downloaded from the host |
| ce_FluidParmChangedString | 3651 | 450, 451, 453, 455, 456, 457 | Collection event when a string fluid file parameter is changed. |
| ce_FluidParmChangedInt | 3652 | 450, 452, 454, 455, 456, 457 | Collection event when a fluid file integer parameter is changed. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|--------------------------------|------|------------------------------|--|
| ce_HeaterParmChangedString | 3653 | 458, 460 | Collection event when a heater file string parameter is changed. |
| ce_HeaterParmChangedInt | 3654 | 459 | Collection event when a heater file integer parameter is changed. |
| ce_HeaterFileManualDownload | 3655 | 458, 460 | Collection event when a heater file is downloaded. |
| ce_HeaterFileManualUpload | 3656 | 458 | Collection event when a heater file is uploaded. |
| ce_HeaterFileSave | 3657 | 458, 460 | Collection event when a heater file is saved. |
| ce_HeaterFileLMOSave | 3658 | 458 | Collection event when heater local machine offsets are saved. |
| ce_HeaterLMODownload | 3659 | 458 | Collection event when heater local machine offsets are downloaded. |
| ce_HeaterLMORemoved | 3660 | 458 | Collection event when heater local machine offsets are removed. |
| ce_HeaterFileNotSaved | 3661 | 458, 460 | Collection event when heater file is not saved successfully. |
| ce_HeaterFileLMONotSaved | 3662 | 458 | Collection event when heater local machine offsets are not saved successfully. |
| ce_ProgInstructionChange | 3663 | 461, 462, 463, 464, 465, 466 | Collection event when a program line instruction is changed. |
| ce_ProgPatternCreated | 3664 | 461, 467 | Collection event when a program pattern is created. |
| ce_ProgPatternDeleted | 3665 | 461, 467 | Collection event when a program pattern is deleted. |
| ce_ProgSaved | 3666 | 461 | Collection event when the program is saved. |
| ce_RecipeLoadComplete | 3667 | 468 | Collection event when a recipe file is loaded successfully. |
| ce_RecipeLoadFailed | 3668 | 468 | Collection event when a recipe file fails to load successfully. |
| ce_ProgWorkpieceRealigned | 3669 | 464, 465 | Collection event when workpiece alignment is changed. |
| ce_ProgFiducialEdit | 3670 | None | Collection event when a program fiducial is edited. |
| ce_ProgSkipMarkEdit | 3671 | None | Collection event when a program skip mark is edited. |
| ce_ProgHeaderParmChangedString | 3672 | 450, 451, 453 | Collection event when a program header string parameter is changed. |
| ce_ProgHeaderParmChangedInt | 3673 | 450, 452, 454 | Collection event when a program header integer parameter is changed. |
| ce_LowFluid_V1 | 3696 | None | Collection event when a low fluid alarm condition occurs on valve 1. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------|------|------------------------|--|
| ce_LowFluid_V2 | 3697 | None | Collection event when a low fluid alarm condition occurs on valve 2. |
| ce_LowFluidCleared_V1 | 3698 | None | Collection event when a low fluid alarm condition is cleared on valve 1. |
| ce_LowFluidCleared_V2 | 3699 | None | Collection event when a low fluid alarm condition is cleared on valve 2. |
| ce_SizeOfCanister | 3700 | 499 | BFS system not used. Collection event when the bulk feed canister size is detected. |
| ce_CPJCheckComplete_V1Pass | 3701 | None | Collection event when CPJ check is complete on valve 1 |
| ce_CPJCheckComplete_V2Pass | 3702 | None | Collection event when CPJ check is complete on valve 2 |
| ce_ValvePressure_V1 | 3703 | 421 | Collection event when valve pressure on valve 1 changes. |
| ce_FluidPressure_V1 | 3704 | 422 | Collection event when fluid pressure on valve 1 changes. |
| ce_CoolingPressure_V1 | 3705 | 423 | Collection event when cooling pressure on valve 1 changes. |
| ce_ValvePressure_V2 | 3706 | 424 | Collection event when valve pressure on valve 2 changes. (Valve 2 EP hardware not installed) |
| ce_FluidPressure_V2 | 3707 | 425 | Collection event when fluid pressure on valve 2 changes. (Valve 2 EP hardware not installed) |
| ce_CoolingPressure_V2 | 3708 | 426 | Collection event when cooling pressure on valve 2 changes. (Valve 2 EP hardware not installed) |
| ce_LmoWpEnabled | 3710 | None | Collection event when local machine offsets workpiece is enabled. |
| ce_LmoWpDisabled | 3711 | None | Collection event when local machine offsets workpiece is disabled. |
| ce_LmoWpModified | 3712 | None | Collection event when local machine offsets workpiece is modified. |
| ce_LmoWpAlignSuccessful | 3713 | None | Collection event when local machine offsets workpiece alignment is successful. |
| ce_LmoWpAlignFailed | 3714 | None | Collection event when local machine offsets workpiece alignment failed. |
| ce_LmoHsEnabled | 3715 | None | Collection event when local machine offsets for height sensor are enabled. |
| ce_LmoHsDisabled | 3716 | None | Collection event when local machine offsets for height sensor are disabled. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|---------------------------------|------|------------------------|--|
| ce_LmoHsModified | 3717 | None | Collection event when local machine offsets for height sensor are modified. |
| ce_LmoWpFidFound_1 | 3718 | 7706, 7708 | Collection event when local machine offsets workpiece fids #1 are set. |
| ce_LmoWpFidFound_2 | 3719 | 7707, 7709 | Collection event when local machine offsets workpiece fids #2 are set. |
| ce_PPSelectCompletePass | 3720 | 468 | Collection event when Program Process file (Recipe) selection is completed successfully. |
| ce_DWVCalibComplete_V1Pass | 3721 | 408, 416, 639 | Collection event when DWV calibration on valve 1 is completed successfully. |
| ce_DWVCalibComplete_V2Pass | 3722 | 408, 416, 639 | Collection event when DWV calibration on valve 2 is completed successfully. |
| ce_DWVCheckComplete_V1 | 3723 | None | Collection event when DWV check on valve 1 is completed successfully. |
| ce_DWVCheckComplete_V2 | 3724 | None | Collection event when DWV check on valve 1 is completed successfully. |
| ce_FlowRateCalibComplete_V1Pass | 3730 | None | Collection event after flow rate calibration on valve 1 is completed successfully. |
| ce_FlowRateCalibComplete_V2Pass | 3731 | None | Collection event after flow rate calibration on valve 2 is completed successfully. |
| ce_HSAAtTactileZ | 3732 | 524 | Collection event when height sense at tactile Z position is set. |
| ce_NdlAtTactileZ_V1 | 3733 | 525 | Collection event when needle at tactile Z position is set. |
| ce_HSAAtScaleLidZ | 3734 | 526 | Collection event when height sense at scale lid Z position is set. |
| ce_HSXYOffsetsPass | 3735 | None | Collection event when height sense XY offsets are completed successfully. |
| ce_NeedleXYOffsetsPass | 3736 | None | Collection event when needle XY offsets is completed successfully. |
| ce_TeachScalePass | 3737 | None | Collection event when teach scale SECS/GEM remote command ran successfully. |
| ce_NeedleZOffsetsPass | 3738 | None | Collection event when needle XY offset SECS/GEM remote command ran successfully. |
| ce_PurgePass | 3740 | None | Collection event when purge is completed successfully. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------------|------|------------------------|--|
| ce_PrimePass | 3741 | None | Collection event when prime SECS/GEM remote command completes successfully. |
| ce_LocateServiceStationPass | 3742 | None | Collection event when locate service station SECS/GEM remote command completes successfully. |
| ce_MoveHomeLocationPass | 3743 | None | Collection event when move home location SECS/GEM remote command completes successfully. |
| ce_MovePurgeLocationPass | 3744 | None | Not used. |
| ce_PrelimNeedleToCameraPass | 3745 | None | Collection event when preliminary needle to camera offsets SECS/GEM remote command completes successfully. |
| ce_DJ9KVAPrimePass | 3746 | None | Collection event when DJ9000 vacuum assisted prime SECS/GEM remote command completes successfully. |
| ce_NdlAtTactileZ_V2 | 3747 | 527 | Collection event when needle at tactile Z position is set. |
| ce_HSAtpurgeLidZ | 3748 | 528 | Collection event when height sense at purge lid Z position is set. |
| ce_DJOffsetCalibrationPass | 3749 | None | Collection event when DJ offset calibration SECS/GEM remote command completes successfully. |
| ce_LoadBoardConv1Pass | 3750 | None | Collection event when SECS/GEM remote command to load board on conveyor 1 completes successfully. |
| ce_LoadBoardConv2Pass | 3751 | None | Collection event when SECS/GEM remote command to load board on conveyor 2 completes successfully. |
| ce_MoveCenterLocationPass | 3752 | None | Collection event when SECS/GEM remote command "MOVE CENTER" completes successfully. |
| ce_MoveFrontLocationPass | 3753 | None | Collection event when SECS/GEM remote command "MOVE FRONT" completes successfully. |
| ce_ResetElapsedPurgeTime | 3754 | None | Not used. |
| ce_SetPurgeCupOverflowTime | 3755 | None | Not used. |
| ce_VacuumOnPass | 3756 | None | Collection event when SECS/GEM remote command "VACUUM ON" completes successfully. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------------|------|------------------------|---|
| ce_VacuumOffPass | 3757 | None | Collection event when SECS/GEM remote command "VACUUM OFF" completes successfully. |
| ce_NeedleXYOffsetsNoPurgePass | 3758 | None | Collection event when SECS/GEM remote command "NEEDLE XY OFFSETS NO PURGE" completes successfully. |
| ce_RestartApplication | 3759 | None | Collection event when SECS/GEM remote command "RESTART APPLICATION" completes successfully. |
| ce_LmoWpFidNotFound_1 | 3760 | 7706, 7708 | Collection event when fiducial 1 of Local Machine Workpiece is not found. |
| ce_LmoWpFidNotFound_2 | 3761 | 7707, 7709 | Collection event when fiducial 2 of Local Machine Workpiece is not found. |
| ce_DHLlinearFluidSensorLevel | 3762 | 1539, 1540 | Collection event when level is checked by Fluidmove (Before each board). Collection event 3709 is used for level percent and state variables. |
| ce_HSXYOffsetsFail | 3763 | None | Collection event when SECS/Gem remote command "HS XY OFFSETS" fails. |
| ce_TeachScaleFail | 3764 | None | Collection event when SECS/Gem remote command "TEACH SCALE" fails. |
| ce_NeedleXYOffsetsFail | 3765 | None | Collection event when SECS/Gem remote command "NEEDLE XY OFFSETS" fails. |
| ce_PurgeFail | 3766 | None | Collection event when SECS/GEM remote command "PURGE" fails. |
| ce_PrimeFail | 3767 | None | Collection event when SECS/GEM remote command "PRIME" fails. |
| ce_LocateServiceStationFail | 3768 | None | Collection event when SECS/GEM remote command "LOCATE SERVICE STATION" fails. |
| ce_MoveHomeLocationFail | 3769 | None | Collection event when SECS/GEM remote command "MOVE HOME" fails. |
| ce_MovePurgeLocationFail | 3770 | None | Not used. |
| ce_PrelimNeedleToCameraFail | 3771 | None | Collection event when SECS/GEM remote command "PRELIM NEEDLE TO CAMERA" completes successfully. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|---------------------------------|------|------------------------|---|
| ce_DJ9KVAPrimeFail | 3772 | None | Collection event when SECS/GEM remote command "DJ9K VACUUM ASSISTED PRIME" fails. |
| ce_DJOffsetCalibrationFail | 3773 | None | Collection event when SECS/GEM remote command "DJ OFFSET CALIBRATION" fails. |
| ce_LoadBoardConv1Fail | 3774 | None | Collection event when SECS/GEM remote command to load board on conveyor 1 fails. |
| ce_LoadBoardConv2Fail | 3775 | None | Collection event when SECS/GEM remote command "LOAD BOARD" on conveyor 2 fails. |
| ce_MoveCenterLocationFail | 3776 | None | Collection event when SECS/GEM remote command "MOVE TO CENTER" fails. |
| ce_MoveFrontLocationFail | 3777 | None | Collection event when SECS/GEM remote command "MOVE TO FRONT" fails. |
| ce_VacuumOnFail | 3778 | None | Collection event when SECS/GEM remote command "VACUUM ON" fails. |
| ce_VacuumOffFail | 3779 | None | Collection event when SECS/GEM remote command "VACUUM OFF" fails. |
| ce_CPJCheckComplete_V1Fail | 3780 | None | Collection event when SECS/GEM remote command "CHECKCPJ" on valve 1 fails. |
| ce_CPJCheckComplete_V2Fail | 3781 | None | Collection event when SECS/GEM remote command "CHECKCPJ" on valve 2 fails. |
| ce_DWVCalibComplete_V1Fail | 3782 | 639 | Collection event when SECS/GEM remote command "DWV" on valve 1 fails. |
| ce_DWVCalibComplete_V2Fail | 3783 | 639 | Collection event when SECS/GEM remote command "DWV" on valve 2 fails. |
| ce_FlowRateCalibComplete_V1Fail | 3784 | 400, 640 | Collection event when SECS/GEM remote command "FLOWRATECALIB" on valve 1 fails. |
| ce_FlowRateCalibComplete_V2Fail | 3785 | 403, 640 | Collection event when SECS/GEM remote command "FLOWRATECALIB" on valve 2 fails. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------------|------|------------------------|---|
| ce_NeedleZOffsetsFail | 3786 | 6294 | Collection event when SECS/GEM remote command "NEEDLE Z OFFSETS". |
| ce_NeedleXYOffsetsNoPurgeFail | 3787 | None | Collection event when SECS/GEM remote command "NEEDLE XY OFFSETS NO PURGE" fails. |
| ce_PPSelectCompleteFail | 3788 | None | Collection event when host process program select (recipe file) fails to load. |
| ce_ValvePressureSetPt_V1 | 3789 | 430 | Collection event when valve pressure set point changes on valve 1. |
| ce_FluidPressureSetPt_V1 | 3790 | 431 | Collection event when fluid pressure set point changes on valve 1. |
| ce_CoolingPressureSetPt_V1 | 3791 | 432 | Collection event when cooling pressure set point changes on valve 1. |
| ce_ValvePressureSetPt_V2 | 3792 | 433 | Collection event when valve pressure set point changes on valve 2. |
| ce_FluidPressureSetPt_V2 | 3793 | 434 | Collection event when fluid pressure set point changes on valve 2. |
| ce_CoolingPressureSetPt_V2 | 3794 | 435 | Collection event when cooling pressure set point changes on valve 2. |
| ce_ValidationStarted | 3795 | None | Collection event when SECS/GEM remote command "VALIDATION START" begins process. |
| ce_CarrierReceivedFromDownstream | 3796 | None | Collection event when carrier is received from downstream during validation. |
| ce_ValidationComplete | 3797 | None | Collection event when carrier validation is complete. |
| ce_ControlDotWeightON | 3798 | 11299 | Collection event when SECS/GEM remote command "CONTROL DOT WEIGHT" enables fluid control dot weight. |
| ce_ControlDotWeightOFF | 3799 | 11299 | Collection event when SECS/GEM remote command "CONTROL DOT WEIGHT" disables fluid control dot weight. |
| ce_SubstrateCornerLocs | 3800 | 530 | Collection event when substrate corner locations are saved. |
| ce_HSAAtScale2LidZ | 3801 | 531 | Collection event when height sense at scale 2 Z position is saved. |
| ce_TactileCenter | 3802 | 532 | Collection event when tactile center location is saved. |
| ce_SendCarrierDownstream | 3803 | None | Not used. |
| ce_SendCarrierUpstream | 3804 | None | No used |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|--|------|------------------------|--|
| ce_ValidationAbort | 3805 | None | Not used |
| ce_PurgePass_V2 | 3806 | None | Collection event when purge on valve 2 is completed successfully. |
| ce_PurgeFail_V2 | 3807 | None | Collection event when purge on valve 2 fails. |
| PromptedSetupStarted | 4001 | 573 | Collection event when scripted prompted setup has started either manually by the operator or remotely from a SECS/GEM host. |
| PromptedSetupCompleted | 4002 | 573 | Collection event when the Prompted Setup Process is completed. |
| FindNeedleXYZ (CE name incorrect) FindNeedle (gcd file name for 4003) | 4003 | None | Collection event when a needle XYZ calibration has been performed. |
| ManualMeasureFlowRate1 | 4004 | None | Collection event when a flow rate measurement for Valve 1 has been initiated by an operator. |
| ManualPurgeNeedle1 | 4005 | None | Collection event when a needle purging of Valve 1 has been initiated by an operator. |
| OperationLevelChanged | 4006 | None | Collection event when the system operation level has been changed from the dialog. |
| PasswordsModified | 4007 | None | Collection event when the system operation level passwords have been modified. |
| ManualMeasureFlowRate2 | 4008 | None | Collection event when a flow rate measurement for Valve 2 has been initiated by an operator. |
| ManualPurgeNeedle2 | 4009 | None | Collection event when a needle purging of Valve 2 has been initiated by an operator. |
| ScaleRead1 | 4010 | 406 | Collection event when the Scale has been read after Valve 1 has dispensed material during the Dispense Weight Verification Procedure. Data Variable ScaleMeasurement1 holds the scale measurement. |
| ScaleRead2 | 4011 | 407 | Collection event when the Scale has been read after Valve 2 has dispensed material during the Dispense Weight Verification Procedure. Data Variable ScaleMeasurement2 holds the scale measurement. |
| FlowRate1Updated | 4012 | 400 | Collection event when the Flow Rate for Valve 1 has been updated (Data Variable FlowRate1 has been modified). |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------------|------|--|---|
| FlowRate2Updated | 4013 | 403 | Collection event when the Flow Rate for Valve 2 has been updated (Data Variable FlowRate2 has been modified). |
| ce_MultiFlowrates_V1 | 4014 | 560 | Collection event when multiple flow rate variables are set for valve 1. |
| ce_MultiFlowrates_V2 | 4015 | 561 | Collection event when multiple flow rate variables are set for valve 2. |
| DispenseWeightComplete | 4020 | DWVResult DWVValve DWVTarget DWVDispenses DWVTargetRange DWVTargetMinLimit DWVTargetMaxLimit DWVMeasuredRange DWVMeasuredAvg | Collection event upon completion of all dispenses during the Dispense Weight Verification routine. See related data variables: |
| ce_ActiveNozzleState | 4021 | ActiveNozzleState | Collection event when the Active Nozzle is changes from ON to OFF or OFF to ON |
| PromptedSetupIncomplete | 4022 | 573 | Collection event when prompted setup does not complete successfully. |
| PromptedSetupScriptFileLoaded | 4023 | 573 | Collection event when a prompted setup script file is loaded successfully. |
| ce_ScaleOverflow_S1 | 4024 | 6703, 6705, 6707, 6709, 6711, 6713, 6715 | Collection event when scale 1 overflow condition has occurred. The operator has been notified that scale 1 has met or exceeded maximum weight capacity. |
| ce_ScaleOverflowWarning_S1 | 4025 | 6703, 6705, 6707, 6709, 6711, 6713, 6715 | Collection event when scale 1 overflow warning has been issued. The operator has been notified that scale 1 has reached the warning level weight capacity. |
| ce_ScaleOverflowReset_S1 | 4026 | 6703, 6705, 6707, 6709, 6711, 6713, 6715 | Collection event when operator has manually reset the overflow parameters from the scale configuration menu or has indicated that the cup has been replaced in response to a warning or overflow message. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|------------------------------|------|--|--|
| ce_ScaleOverflow_S2 | 4027 | 6704, 6706, 6708, 6710, 6712, 6714, 6716 | Collection event when scale 2 overflow condition has occurred. The operator has been notified that scale 2 has met or exceeded maximum weight capacity. |
| ce_ScaleOverflowWarning_S2 | 4028 | 6704, 6706, 6708, 6710, 6712, 6714, 6716 | Collection event when scale 2 overflow warning has been issued. The operator has been notified that scale 2 has reached the warning level weight capacity. |
| ce_ScaleOverflowReset_S2 | 4029 | 6704, 6706, 6708, 6710, 6712, 6714, 6716 | Collection event when an operator has manually reset the overflow parameters from the scale configuration menu or has indicated that the cup has been replaced in response to a warning or overflow message. |
| HeaterMonitorTimeout | 5001 | None | Collection event when the heaters at the dispensing location failed to reach the specified temperature range within the timeout period. |
| HeaterMonitorSkipped | 5002 | None | Collection event when the Operator has selected to skip the temperature monitoring and proceed to dispensing. |
| HeaterMonitorAborted | 5003 | None | Collection event when the Operator has selected to abort the temperature monitoring and aborted the run. |
| PeriodicPurge1 | 5004 | None | Collection event when a periodical purging of the needle for Valve 1 has been performed. |
| PeriodicFlowrateMeasurement1 | 5005 | None | Collection event when a periodical flow rate measurement for Valve 1 has been performed. |
| PotLifeWarning1 | 5006 | None | Collection event when the pot life of the dispensing material for Valve 1 has reached a warning level. |
| PotLifeExpire1 | 5007 | None | Collection event when the pot life of the dispensing material for Valve 1 has expired. |
| AwaitingRecoveryCommand | 5008 | None | Collection event when the system has queried the Operator to recover the previous run. |
| OperatorAkedTerminalMsg | 5009 | None | Used by GEM drivers Collection event when the Operator acknowledged a terminal message. |
| PeriodicPurge2 | 5010 | None | Collection event when a periodical purging of the needle for Valve 2 has been performed. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|------------------------------|------|---|--|
| PeriodicFlowrateMeasurement2 | 5011 | None | Collection event when a periodical flow rate measurement for Valve 2 has been performed. |
| PotLifeWarning2 | 5012 | None | Collection event when the pot life of the dispensing material for Valve 2 has reached a warning level. |
| PotLifeExpire2 | 5013 | None | Collection event when the pot life of the dispensing material for Valve 2 has expired. |
| ce_HeaterTempsUpdated | 5014 | 611, 801-868, SV 1101-1168 and SV 1201-1268 | Collection event when the heater temperatures are updated. |
| ce_DoorOpen | 5015 | None | Collection event when the door is opened. |
| ce_DoorClose | 5016 | None | Collection event when the door is closed. |
| ce_DWCA_SetupStarted | 5040 | 641, 643, 645, 648 | Initial collection event signaling start of DWCA setup (DJ9K Dot Weight Pressure Setup). |
| ce_DWCA_MinPressureCompleted | 5041 | 643, 644 | Intermediate collection event when dot weight at minimum pressure has been completed. |
| ce_DWCA_MaxPressureCompleted | 5042 | 641, 642 | Intermediate collection event when dot weight at maximum pressure has been completed. |
| ce_DWCA_SetupCompleted | 5043 | 641, 642, 643, 644, 645, 646, 647, 648 | Final collection event when final dot weight and pressure has been computed and DWCA setup has completed successfully. |
| ce_DWCA_IntermediateValues | 5044 | 649, 650 | Intermediate collection event when a fluid pressure / dot weight has failed calibration and the routine is adjusting pressure. The tool will retry unless retries exhausted. |
| ce_DWCA_SetupFailed | 5045 | None | Collection event if DWCA setup failed or was aborted by user or tool error. This collection event signals that the DWCA setup routine (DJ9K Dot Weight Pressure Setup) has completed unsuccessfully. |
| ce_DWCA_CPJStarted | 5046 | 645, 648, 651, 652 | Collection event signaling start of DWCA CPJ (FLOWRATECALIB). |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------|------|------------------------------|--|
| ce_DWCA_CPJCompleted | 5047 | 645, 646, 647, 648, 651, 652 | Final collection event when final dot weight and pressure has completed. This collection event signals that the DWCA CPJ routine has completed successfully. |
| ce_DWCA_CPJFailed | 5048 | None | Collection event if CPJ failed or was aborted by user or tool error. This collection event signals that the DWCA CPJ routine (FLOWRATECALIB) has completed unsuccessfully. |
| ce_CurrentFidFoundXY | 8000 | 7000, 10000 | Collection event when the program pattern fiducial location is found. |
| ce_CurrentFidNotFoundXY | 8001 | 7000, 10000 | Collection event when the program pattern fiducial location is not found. Related XY locations indicate "expected" location. |
| ce_LucImageFound | 8002 | 7000, 10000 | Collection event when program workpiece fiducial 2 has been found. |
| ce_LucImageNotFound | 8003 | 7710, 7711, 520 | Collection event after running the script instruction "LUC MODEL FIND" or the program instruction "LUC MODEL FIND" and the model for the LUC is not found. |
| ce_LucImageTaught | 8004 | 520 | Collection event an image is taught using the script instruction "LUC MODEL TEACH". |
| ce_SSPin1Found | 8005 | 553, 534 | Collection event when the Service Station Pin 1 is found. |
| ce_SSPin1NotFound | 8006 | None | Collection event when service station pin1 is not found. |
| ce_SSPin2Found | 8007 | 553, 554 | Collection event when service station pin 2 is found. |
| ce_SSPin2NotFound | 8008 | None | Collection event when service station pin 2 is not found. |
| ce_SSPin1ImageSaved | 8009 | 520 | Collection event when the Service Station Pin 1 is found (or not found) and saved as an image. |
| ce_SSPin2ImageSaved | 8010 | 520 | Collection event when the Service Station Pin 2 is found (or not found) and saved as an image. |
| ce_XYDot1ImageSaved | 8011 | 520 | Collection event when Needle to Camera XY offset is executed and the first dot is found (or not found) and saved as an image. |
| ce_XYDot2ImageSaved | 8012 | 520 | Collection event when Needle to Camera XY offset is executed and the second dot is found (or not found) and saved as an image. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------|------|------------------------|---|
| ce_XYDot3ImageSaved | 8013 | 520 | Collection event when Needle to Camera XY offset is executed and the third dot is found (or not found) and saved as an image. |
| ce_XYDot4ImageSaved | 8014 | 520 | Collection event when Needle to Camera XY offset is executed and the fourth dot is found (or not found) and saved as an image. |
| ce_XYDot1Found | 8015 | 535, 536 | Collection event when the Needle to Camera XY Offset Dot 1 is found. |
| ce_XYDot1NotFound | 8016 | None | Collection event when the Needle to Camera XY Offset Dot 1 is not found. |
| ce_XYDot2Found | 8017 | 535, 536 | Collection event when the Needle to Camera XY Offset Dot 2 is found. |
| ce_XYDot2NotFound | 8018 | none | Collection event when the Needle to Camera XY Offset Dot 2 is not found. |
| ce_XYDot3Found | 8019 | 535, 536 | Collection event when the Needle to Camera XY Offset Dot 3 is found. |
| ce_XYDot3NotFound | 8020 | None | Collection event when the Needle to Camera XY Offset Dot 3 is not found. |
| ce_XYDot4Found | 8021 | 535, 536 | Collection event when the Needle to Camera XY Offset Dot 4 is found. |
| ce_XYDot4NotFound | 8022 | None | Collection event when the Needle to Camera XY Offset Dot 4 is not found. |
| ce_LUCModelFindImageSaved | 8023 | 520 | Collection event when the Lookup Camera LUC MODEL FIND program or script instruction is executed and the image is saved. |
| ce_LUCModelTeachImageSaved | 8024 | 520 | Collection event when the Lookup Camera LUC MODEL TEACH script instruction is executed and the image is saved. |
| ce_LmoWpFid1ImageSaved | 8025 | 520 | Collection event when the Local Machine Offset Workpiece is re-aligned and the first fiducial is found (or not found) and saved as an image. |
| ce_LmoWpFid2ImageSaved | 8026 | 520 | Collection event when the Local Machine Offset Workpiece is re-aligned and the second fiducial is found (or not found) and saved as an image. |
| ce_WpFoundImageSaved | 8027 | 520 | Collection event when a program Workpiece fiducial is found and saved as an image. |
| ce_WpNotFoundImageSaved | 8028 | 520 | Collection event when a program Workpiece fiducial is NOT found and saved as an image. |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------------------|------|------------------------|--|
| ce_PattFoundImageSaved | 8029 | 520, 523 | Collection event when a program Pattern fiducial is found and saved as an image. |
| ce_PattNotFoundImageSaved | 8030 | 520, 523 | Collection event when a program Pattern fiducial is NOT found and saved as an image. |
| ce_ImageSaveInstructionImageSaved | 8031 | 520 | Collection event when the "IMAGE SAVE" instruction is executed and the image is saved. |
| ce_ImageSaveManualImageSaved | 8032 | 520 | Collection event when an image is manually saved from the video window. |
| ce_PressureOffsetChanged | 8033 | 450, 574, 575 | Collection event when operator changes an E/P LMO offset value. |
| ce_PressureOffsetUnitsChanged | 8034 | 450, 451, 453 | Collection event when the internal units of E/P LMO offset changes. This value will change when "Air Pressure" units are changed from the main configuration dialog and after the LMO offset dialog is visited and exited. |
| ce_CurrentHSFoundXYZ | 8400 | 7400 | Collection event when a program height sense has been performed. |
| ce_HeightSenseOriginConv1 | 8401 | 7701 | Collection event when Height Sense origin on conveyor 1 is changed. |
| ce_HeightSenseOriginConv2 | 8402 | 7702 | Collection event when Height Sense origin on conveyor 2 is changed. |
| ce_CarrierLoadTime_L1 | 8403 | 428 | Collection event when carrier on lane 1 is loaded. |
| ce_CarrierUnloadTime_L1 | 8404 | 429 | Collection event when carrier on lane 1 is unloaded. |
| ce_CarrierLoadTime_L2 | 8405 | 469 | Collection event when carrier on lane 2 is loaded. |
| ce_CarrierUnloadTime_L2 | 8406 | 470 | Collection event when carrier on lane 2 is unloaded. |
| ce_BoardSequenceNumber | 8800 | 7800 | Collection event when Carrier Sequence # (sequential) is changed. This number is reset each time "GO" is pressed. For a running board count processed since power up, see existing SV 106 (BoardCount). |
| ce_WPFidFoundXY_1 | 8801 | 7801 | Collection event when Workpiece Fiducial #1 XY in machine units (actual found). |
| ce_WPFidFoundXY_2 | 8802 | 7802 | Collection event Workpiece Fiducial #2 XY in machine units (actual found). |

Table B-1 Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------------|--|
| ce_WPFidNotFoundXY_1 | 8803 | None | Collection event when Workpiece Fiducial #1 XY in machine units not found. |
| ce_WPFidNotFoundXY_2 | 8804 | None | Collection event Workpiece Fiducial #2 XY in machine units not found. |
| FMWError | 9000 | 1002 | Used by GEM drivers Collection event when a Fluidmove error has occurred. Use status variable FMWMostRecentError (1002) to retrieve the error code. |
| FMWErrorCleared | 9001 | None | Used by GEM drivers Collection event when a Fluidmove error has been acknowledged by the Operator and the message cleared. |
| EPTStateChange | 9002 | 1542, 1543, 1544, 1545, 1546 | Collection event when the EPT state changes. |

Appendix C Alarms

C.1 Overview

Since the number of alarms that Fluidmove reports to SECS/GEM is constantly growing, each individual alarm will not be listed here. The alarm section of the GWGEM GCD file is automatically generated from the Fluidmove source code using a custom software tool. Use the SECS/GEM message S5F5 to retrieve a list of all alarms currently reported by your version of Fluidmove.

C.2 Alarm Format

The format for each alarm is described below:

- ALID** Alarm ID. This number is the same as the resource identification number used by Fluidmove.
- ALCD** Alarm Severity Code. The low-order 7-bits of ALCD specifies the severity code. The high-order bit (bit-8) shows the current alarm state (1=SET, 0=CLEAR). Currently all Fluidmove errors have a default severity code of 64.
- ALTX** Alarm Text. This is the actual string sent to the Host in the Alarm Report (S5F1) and is a truncated version (first 40 characters) of the resource item used by Fluidmove.
- ON CEID** This is the Collection Event that is signaled when the alarm state changes from CLEAR to SET ("going-on"). For all of the Fluidmove errors the event is FMWError.
- OFF CEID** This is the Collection Event that is signaled when the alarm state changes from SET to CLEAR ("going-off"). For all of the Fluidmove errors the event is FMWErrorCleared.

C.3 Alarms

Table C-1 provides some examples of common alarms and how the ALID, ALCD, ALTX, and ON/OFF CEIDs related to them.

Table C-1 Alarms

| ALID | ALCD | ALTX | Alarm Description | ON CEID | OFF CEID |
|-------|------|--------------------------------|--|---------|----------|
| 4 | 64 | Heater Temperature is Too Low | Current Temp < setpoint - band | 9000 | 9001 |
| 5 | 64 | Heater Temperature is Too High | Current Temp > setpoint + band. | 9000 | 9001 |
| 30002 | 64 | Run Aborted | The currently running program has been aborted. | 9000 | 9001 |
| 30167 | 64 | Error during fiducial finding | An error occurred during the fiducial finding process. | 9000 | 9001 |
| 30172 | 64 | Loss of air pressure detected | Fluidmove has detected low air pressure. | 9000 | 9001 |

Appendix D FmConfig.ini File Variables

D.1 Overview

The following variables are defined as Equipment Constants.



NOTE

Floating point variables in the FmConfig.ini file have been converted to and uploaded as ASCII strings to prevent rounding and truncation errors that would occur if uploaded as floating point values. This method guarantees an exact match to the FmConfig.ini entry.

Also, configuration parameters which contain more than one value, such as XY coordinates and light states, are converted to a single string with each value separated by a comma. This prevents having multiple ECs represent a single parameter as well as avoiding the rounding/truncation problem.

In the table below, these cases have been identified in the “Storage Type” column where:

- ASCII is ASCII
- INT is Integer
- FLT is Float

If an ASCII string represents more than one value, such as an XY coordinate that contains two floating point values separated by a comma, “FLT,FLT” will be added to the storage type.

Finally, “(none)” will be returned by the equipment for those integer, floats or arrays which have no value. For instance, light states, defined as A[30], may contain four integer values “INT,INT,INT,INT” but if the light state has not been defined the equipment will return a single string “(none)”.

D.2 FmConfig.ini File Variables

Table D-1 lists FmConfig.ini file variables sorted by ID number.

Table D-1 FmConfig.ini File

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------------|-----------|------|-----------|--------------|---|
| c_MachineSetupMode | EC | 6000 | A[20] | ASCII | [Misc Parms] Machine Setup Mode = |
| c_ScriptedVOFileName | EC | 6001 | A[60] | ASCII | [Misc Parms] Scripted VO File Name = |
| c_CameraAssistedScripts | EC | 6002 | A[4] | ASCII | [Misc Parms] Camera Assisted Scripts = |
| c_EnableFindTeachXYZ | EC | 6003 | A[4] | ASCII | [Misc Parms] Enable Find/Teach XYZ = |
| c_CheckLocalRecipeFiles | EC | 6004 | A[4] | ASCII | [Misc Parms] Check Local Recipe Files = |
| c_ChangeOperationLevel | EC | 6005 | A[4] | ASCII | [Misc Parms] Change operation level when program idle = |
| c_GemInstalled | EC | 6006 | A[4] | ASCII | [Gem Manager] Gem Installed = |
| c_GemEnabled | EC | 6007 | A[4] | ASCII | [Gem Manager] Gem Enabled = |
| c_DefaultCommState | EC | 6008 | I4 | INT | [Gem Manager] Default Comm State = |
| c_DefaultControlState | EC | 6009 | I4 | INT | [Gem Manager] Default Control State = |
| c_OnlineFailedState | EC | 6010 | I4 | INT | [Gem Manager] Online Failed State = |
| c_StartinProdOplevel | EC | 6011 | A[4] | ASCII | [Password] Start in Prod operation level = |
| c_PollInterval | EC | 6012 | I4 | INT | [Heater Manager] Poll Interval = |
| c_DisableAfterRun | EC | 6013 | A[4] | ASCII | [Heater Manager] Disable After Run = |
| c_EnabledPurgeBeforeResume | EC | 6014 | A[4] | ASCII | [Heater Manager] Enabled Purge Before Resume = |
| c_EnableSkipWhileWaitingforTemp | EC | 6015 | A[4] | ASCII | [Heater Manager] Enable Skip While Waiting for Temp = |
| c_TurnheatersoffwhenFmntexits | EC | 6016 | A[4] | ASCII | [Heater Manager] Turn heaters off when Fmnt exits = |
| c_Enabled_H1 | EC | 6017 | A[4] | ASCII | [Heater 1] Enabled = |
| c_ControlType_H1 | EC | 6018 | A[4] | ASCII | [Heater 1] Control Type = |
| c_PreRunPurgeTime | EC | 6019 | A[30] | FLT | [Runtime Preferences] Pre-Run Purge Time = |
| c_HomeZAxisatProd | EC | 6020 | A[4] | ASCII | [Runtime Preferences] Home Z Axis at Prod. Start = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-------------------------------|-----------|------|-----------|--------------|---|
| c_HomeAllAxesatProd | EC | 6021 | A[4] | ASCII | [Runtime Preferences] Home All Axes at Prod. Start = |
| c_MovetoLocationatProd | EC | 6022 | A[4] | ASCII | [Runtime Preferences] Move to Location at Prod. Start = |
| c_StartLocation | EC | 6023 | A[30] | ASCII | [Runtime Preferences] Start Location = |
| c_AudibleAlarmStatus | EC | 6024 | I4 | INT | [Beacon] Audible = |
| c_EnableRunSetupForProduction | EC | 6025 | A[4] | ASCII | [Runtime Preferences] Enable Run Setup For Production = |
| c_CheckSystemAirPressure | EC | 6026 | A[4] | ASCII | [Runtime Preferences] Check System Air Pressure = |
| c_DispenseMotionTimeout | EC | 6027 | I4 | INT | [Runtime Preferences] Dispense Motion Timeout = |
| c_DefaultMotionTimeout | EC | 6028 | I4 | INT | [Runtime Preferences] Default Motion Timeout = |
| c_MovetoFirstFidLocation | EC | 6029 | A[4] | ASCII | [Default Post Run Park] Move to First Fid Location = |
| c_MoveToSystemLocation | EC | 6030 | A[4] | ASCII | [Default Post Run Park] Move To System Location = |
| c_SystemLocationName | EC | 6031 | A[30] | ASCII | [Default Post Run Park] System Location Name = |
| c_SetValveNumber | EC | 6032 | I4 | INT | [Default Post Run Park] Set Valve Number = |
| c_HeightSensorType | EC | 6033 | A[30] | ASCII | [Height Sensor] Type = |
| c_HeightSensorControlType | EC | 6034 | A[30] | ASCII | [Height Sensor] Control Type = |
| c_DownSpeed | EC | 6035 | A[30] | FLT | [Height Sensor] Down Speed = |
| c_UpSpeed | EC | 6036 | A[30] | FLT | [Height Sensor] Up Speed = |
| c_Accel | EC | 6037 | A[30] | FLT | [Height Sensor] Accel = |
| c_MaxDist | EC | 6038 | A[30] | FLT | [Height Sensor] Max Dist = |
| c_RetractHt | EC | 6039 | A[30] | FLT | [Height Sensor] Retract Ht (FMW) = |
| c_ProbeInput | EC | 6040 | I4 | INT | [Height Sensor] Probe Input = |
| c_ProbePositionOverTactile | EC | 6041 | A[40] | FLT, FLT | [Height Sensor] Probe Position Over Tactile = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--------------------------------|-----------|------|-----------|--------------|---|
| c_ProbeToggleDelay | EC | 6042 | A[30] | FLT | [Height Sensor] Probe Toggle Delay (ms) = |
| c_MaximumVelocityforHStest | EC | 6043 | A[30] | FLT | [Height Sensor] Maximum Velocity for HS test(FMW) = |
| c_MinimumAccelforHStest | EC | 6044 | A[30] | FLT | [Height Sensor] Minimum Accel for HS test(FMW) = |
| c_MaximumAccelforHStest | EC | 6045 | A[30] | FLT | [Height Sensor] Maximum Accel for HS test(FMW) = |
| c_DownVelocityforSingleHStest | EC | 6046 | A[30] | FLT | [Height Sensor] Down Velocity for Single HS test(FMW) = |
| c_DownAccelforSingleHStest | EC | 6047 | A[30] | FLT | [Height Sensor] Down Accel for Single HS test(FMW) = |
| c_InitXPosforSingleHStest | EC | 6048 | A[30] | FLT | [Height Sensor] Init X Pos for Single HS test (FMW) = |
| c_InitYPosforSingleHStest | EC | 6049 | A[30] | FLT | [Height Sensor] Init Y Pos for Single HS test (FMW) = |
| c_MaxCycleCountforSingleHStest | EC | 6050 | I4 | INT | [Height Sensor] Max Cycle Count for Single HS test = |
| c_CycleCountforSingleHStest | EC | 6051 | I4 | INT | [Height Sensor] Cycle Count for Single HS test = |
| c_DownVelocityforMultHStest | EC | 6052 | A[30] | FLT | [Height Sensor] Down Velocity for Mult HS test(FMW) = |
| c_DownAccelforMultHStest | EC | 6053 | A[30] | FLT | [Height Sensor] Down Accel for Mult HS test(FMW) = |
| c_MotionControllerName | EC | 6054 | A[20] | ASCII | [Camera] Name = |
| c_CameraType | EC | 6055 | A[20] | ASCII | [Camera] Type = |
| c_CameraOffset | EC | 6056 | A[40] | FLT, FLT | [Camera] Offset = |
| c_MotionControllerType | EC | 6057 | A[20] | ASCII | [Motion Controller] Type = |
| c_MachineUnitsPerEncoderUnit | EC | 6058 | A[30] | FLT | [Motion Controller] Machine Units Per Encoder Unit = |
| c_XAxisSWLimitMin | EC | 6059 | A[30] | FLT | [Motion Controller] X Axis SW Limit Min = |
| c_XAxisSWLimitMax | EC | 6061 | A[30] | FLT | [Motion Controller] X Axis SW Limit Max = |
| c_YAxisSWLimitMin | EC | 6062 | A[30] | FLT | [Motion Controller] Y Axis SW Limit Min = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-------------------|-----------|------|-----------|--------------|---|
| c_YAxisSWLimitMax | EC | 6063 | A[30] | FLT | [Motion Controller] Y Axis SW Limit Max = |
| c_ZAxisSWLimitMin | EC | 6064 | A[30] | FLT | [Motion Controller] Z Axis SW Limit Min = |
| c_ZAxisSWLimitMax | EC | 6065 | A[30] | FLT | [Motion Controller] Z Axis SW Limit Max = |
| c_Jog1XYRate | EC | 6066 | A[30] | FLT | [Motion Controller] Jog 1 XY Rate = |
| c_Jog1XYAccel | EC | 6067 | A[30] | FLT | [Motion Controller] Jog 1 XY Accel = |
| c_Jog1XYDist | EC | 6068 | A[30] | FLT | [Motion Controller] Jog 1 XY Dist = |
| c_Jog2XYRate | EC | 6069 | A[30] | FLT | [Motion Controller] Jog 2 XY Rate = |
| c_Jog2XYAccel | EC | 6070 | A[30] | FLT | [Motion Controller] Jog 2 XY Accel = |
| c_Jog2XYDist | EC | 6071 | A[30] | FLT | [Motion Controller] Jog 2 XY Dist = |
| c_JogMaxXYRate | EC | 6072 | A[30] | FLT | [Motion Controller] Jog Max XY Rate = |
| c_JogMaxXYAccel | EC | 6073 | A[30] | FLT | [Motion Controller] Jog Max XY Accel = |
| c_JogMaxXYDist | EC | 6074 | A[30] | FLT | [Motion Controller] Jog Max XY Dist = |
| c_Jog1Zrate | EC | 6075 | A[30] | FLT | [Motion Controller] Jog 1 Z Rate = |
| c_Jog1Zaccel | EC | 6076 | A[30] | FLT | [Motion Controller] Jog 1 Z Accel = |
| c_Jog1Zdist | EC | 6077 | A[30] | FLT | [Motion Controller] Jog 1 Z Dist = |
| c_Jog2Zrate | EC | 6078 | A[30] | FLT | [Motion Controller] Jog 2 Z Rate = |
| c_Jog2Zaccel | EC | 6079 | A[30] | FLT | [Motion Controller] Jog 2 Z Accel = |
| c_Jog2Zdist | EC | 6080 | A[30] | FLT | [Motion Controller] Jog 2 Z Dist = |
| c_JogMaxZRate | EC | 6081 | A[30] | FLT | [Motion Controller] Jog Max Z Rate = |
| c_JogMaxZAccel | EC | 6082 | A[30] | FLT | [Motion Controller] Jog Max Z Accel = |
| c_JogMaxZDist | EC | 6083 | A[30] | FLT | [Motion Controller] Jog Max Z Dist = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--|-----------|------|-----------|--------------|---|
| c_StartupFileName | EC | 6084 | A[60] | ASCII | [Motion Controller] Startup File Name = |
| c_AtResetFileName | EC | 6085 | A[60] | ASCII | [Motion Controller] At Reset File Name = |
| c_PreBoardRunFileName | EC | 6086 | A[60] | ASCII | [Motion Controller] Pre-Board Run File Name = |
| c_AtAbortFileName | EC | 6087 | A[60] | ASCII | [Motion Controller] At Abort File Name = |
| c_ErrorMapEnabled | EC | 6088 | A[4] | ASCII | [Motion Controller] Error Map Enabled = |
| c_ErrorCorrectionDataFile | EC | 6089 | A[60] | ASCII | [Motion Controller] Error Correction Data File = |
| c_WeightCtrlCalWithAcceleration | EC | 6090 | A[4] | ASCII | [Motion Controller] Weight Ctrl Cal With Acceleration = |
| c_EnableXTravelLimitChecking | EC | 6091 | A[4] | ASCII | [Motion Controller] Enable X Travel Limit Checking = |
| c_EnableYTravelLimitChecking | EC | 6092 | A[4] | ASCII | [Motion Controller] Enable Y Travel Limit Checking = |
| c_EnableZTravelLimitChecking | EC | 6093 | A[4] | ASCII | [Motion Controller] Enable Z Travel Limit Checking = |
| c_TimedPurge | EC | 6094 | A[4] | ASCII | [Purge Station] Timed Purge = |
| c_EnablePurgeBeforeResume | EC | 6095 | A[4] | ASCII | [Purge Station] Enable Purge Before Resume = |
| c_VacuumOutput | EC | 6096 | I4 | I4 | [Purge Station] Vacuum Output = |
| c_FlowRate1 | EC | 6097 | A[30] | FLT | [Flow Rate Manager] Flow Rate 1 = |
| c_DispenseWeightVerificationOutOfRange | EC | 6098 | A[4] | ASCII | [Flow Rate Manager] Dispense Weight Verification Out Of Range = |
| c_ValveAutoBiasOutOfRange | EC | 6099 | A[4] | ASCII | [Flow Rate Manager] Valve Auto Bias Out Of Range = |
| c_ScaleType | EC | 6100 | A[20] | ASCII | [Scale Manager] Scale Type = |
| c_Enabled | EC | 6101 | A[4] | ASCII | [Scale Manager] Enabled = |
| c_ReadDelay | EC | 6102 | A[30] | FLT | [Scale Manager] Read Delay = |
| c_ScaleUnits | EC | 6103 | A[10] | ASCII | [Scale Manager] Units = |
| c_StabilityTimeout | EC | 6104 | A[30] | FLT | [Scale Manager] Stability Timeout = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------------|-----------|------|-----------|--------------|---|
| c_CheckScaleCup | EC | 6105 | A[4] | ASCII | [Scale Manager] Check Scale Cup = |
| c_ScaleCupBit | EC | 6106 | I4 | INT | [Scale Manager] Scale Cup Bit = |
| c_NumberofConveyors | EC | 6107 | I4 | INT | [Conveyor Manager] Number of Conveyors = |
| c_Jog1Dist | EC | 6108 | A[30] | FLT | [Conveyor Manager] Jog1Dist = |
| c_Jog2Dist | EC | 6109 | A[30] | FLT | [Conveyor Manager] Jog2Dist = |
| c_JogMaxDist | EC | 6110 | A[30] | FLT | [Conveyor Manager] Jog Max Dist = |
| c_ConveyorControlType1 | EC | 6111 | A[20] | ASCII | [Conveyor Manager] Control Type 1 = |
| c_ConveyorControlType2 | EC | 6112 | A[20] | ASCII | [Conveyor Manager] Control Type 2 = |
| c_ConfirmACWMove | EC | 6113 | A[4] | ASCII | [Conveyor Manager] Confirm ACW Move = |
| c_ConveyorControlType_C1 | EC | 6114 | A[20] | ASCII | [Conveyor] Control Type = |
| c_IsCustomConveyor_C1 | EC | 6115 | A[4] | ASCII | [Conveyor] Is Custom Conveyor = |
| c_StyleType_C1 | EC | 6116 | A[100] | ASCII | [Conveyor] Style Type = |
| c_ConveyorMode_C1 | EC | 6117 | I4 | INT | [Conveyor] Mode = |
| c_FMWsPerUnit_C1 | EC | 6118 | A[30] | FLT | [Conveyor] FMW's Per Unit = |
| c_ResetOutput_C1 | EC | 6119 | I4 | INT | [Conveyor] Reset Output = |
| c_RunNumberEnabled_C1 | EC | 6120 | A[4] | ASCII | [Conveyor] Run Number Enabled = |
| c_NumberofRuns_C1 | EC | 6121 | I4 | INT | [Conveyor] Number of Runs = |
| c_WetRunEnabled_C1 | EC | 6122 | A[4] | ASCII | [Conveyor] Wet Run Enabled = |
| c_UseConveyorEnabled_C1 | EC | 6123 | A[4] | ASCII | [Conveyor] Use Conveyor Enabled = |
| c_EnableXTravelLimitChecking_C1 | EC | 6124 | A[4] | ASCII | [Conveyor] Enable X Travel Limit Checking = |
| c_EnableYTravelLimitChecking_C1 | EC | 6125 | A[4] | ASCII | [Conveyor] Enable Y Travel Limit Checking = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|------------------------------|-----------|------|-----------|--------------|---|
| c_TwinConveyorWait_C1 | EC | 6126 | I4 | INT | [Conveyor] Twin Conveyor Wait = |
| c_BeltSpeed_C1 | EC | 6127 | A[30] | INT, FLT | [Conveyor] Belt Speed = |
| c_BeltAccel_C1 | EC | 6128 | A[30] | INT, FLT | [Conveyor] Belt Accel = |
| c_LongMove_C1 | EC | 6129 | A[30] | INT, FLT | [Conveyor] Long Move = |
| c_ShortMove_C1 | EC | 6130 | A[30] | INT, FLT | [Conveyor] Short Move = |
| c_Retries_C1 | EC | 6131 | A[30] | INT, FLT | [Conveyor] Retries = |
| c_BackMove_C1 | EC | 6132 | A[30] | INT, FLT | [Conveyor] Back Move = |
| c_TypesFile_C1 | EC | 6133 | A[60] | ASCII | [Conveyor] Types File = |
| c_StartupFileName_C1 | EC | 6134 | A[60] | ASCII | [Conveyor] Startup File Name = |
| c_AtResetFileName_C1 | EC | 6135 | A[60] | ASCII | [Conveyor] At Reset File Name = |
| c_PreBoardRunFileName_C1 | EC | 6136 | A[60] | ASCII | [Conveyor] Pre-Board Run File Name = |
| c_AtAbortFileName_C1 | EC | 6137 | A[60] | ASCII | [Conveyor] At Abort File Name = |
| c_AtRunCompletionFileName_C1 | EC | 6138 | A[60] | ASCII | [Conveyor] At Run Completion File Name = |
| c_VisionSystem | EC | 6139 | A[30] | ASCII | [Vision] Vision System = |
| c_VideoMixer | EC | 6140 | A[30] | ASCII | [Vision] Video Mixer = |
| c_VisionSubdir | EC | 6141 | A[40] | ASCII | [Vision] Vision Subdir = |
| c_ACSFilename | EC | 6142 | A[60] | ASCII | [Vision] ACS Filename = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--------------------------|-----------|------|-----------|--------------|---|
| c_Xpel | EC | 6143 | A[30] | FLT | [Vision] X/pel = |
| c_Ypel | EC | 6144 | A[30] | FLT | [Vision] Y/pel = |
| c_DfltMotionAntibacklash | EC | 6145 | A[4] | ASCII | [Vision] Dflt Motion Anti-backlash = |
| c_DfltUsePipeline | EC | 6146 | A[4] | ASCII | [Vision] Dflt Use Pipeline = |
| c_AnnouncePipelineMiss | EC | 6147 | A[4] | ASCII | [Vision] Announce Pipeline Miss = |
| c_DfltImagegain | EC | 6148 | I4 | INT | [Vision] Dflt Image gain = |
| c_DfltImageoffset | EC | 6149 | I4 | INT | [Vision] Dflt Image offset = |
| c_DfltImagesettlingtime | EC | 6150 | I4 | INT | [Vision] Dflt Image settling time = |
| c_DfltTextlevel | EC | 6151 | I4 | INT | [Vision] Dflt Text level = |
| c_DfltGraphicslevel | EC | 6152 | I4 | INT | [Vision] Dflt Graphics level = |
| c_DfltPausemode | EC | 6153 | A[4] | ASCII | [Vision] Dflt Pause mode = |
| c_DfltMarkPausemode | EC | 6154 | A[4] | ASCII | [Vision] Dflt Mark Pause mode = |
| c_DfltMFacceptthold | EC | 6157 | A[30] | FLT | [Vision] Dflt MF accept thold = |
| c_DfltMFconfusionthold | EC | 6158 | A[30] | FLT | [Vision] Dflt MF confusion thold = |
| c_DfltMFwidth | EC | 6159 | A[30] | FLT | [Vision] Dflt MF width = |
| c_DfltMFheight | EC | 6160 | A[30] | FLT | [Vision] Dflt MF height = |
| c_DfltMFsearchwinwidth | EC | 6161 | A[30] | FLT | [Vision] Dflt MF search win width = |
| c_DfltMFsearchwinheight | EC | 6162 | A[30] | FLT | [Vision] Dflt MF search win height = |
| c_DfltMFwinloc | EC | 6163 | A[30] | FLT | [Vision] Dflt MF win loc = |
| c_DfltCFanchorpt | EC | 6164 | A[30] | FLT | [Vision] Dflt CF anchor pt = |
| c_DfltCFscanlen | EC | 6165 | A[30] | FLT | [Vision] Dflt CF scan len = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------|-----------|------|-----------|--------------|---|
| c_DfltCFsearchinward | EC | 6166 | A[30] | FLT | [Vision] Dflt CF search inward = |
| c_DfltCFdensity | EC | 6167 | A[30] | FLT | [Vision] Dflt CF density = |
| c_DfltCFsearchlen | EC | 6168 | I4 | INT | [Vision] Dflt CF search len = |
| c_DfltCFprojlen | EC | 6169 | I4 | INT | [Vision] Dflt CF proj len = |
| c_DfltCFEFsize | EC | 6170 | A[30] | FLT | [Vision] Dflt CF EF size = |
| c_DfltCFEFleniency | EC | 6171 | A[30] | FLT | [Vision] Dflt CF EF leniency = |
| c_DfltCFmincontrast | EC | 6172 | A[30] | FLT | [Vision] Dflt CF min contrast = |
| c_DfltCFpolarity | EC | 6173 | A[30] | FLT | [Vision] Dflt CF polarity = |
| c_DfltCFacceptthold | EC | 6174 | A[30] | FLT | [Vision] Dflt CF accept thold = |
| c_DfltCFscorefunc | EC | 6175 | A[30] | FLT | [Vision] Dflt CF score func = |
| c_DfltCFLSFconsectol | EC | 6176 | I4 | INT | [Vision] Dflt CF LSF consec tol = |
| c_DfltCFLSFminpoints | EC | 6177 | I4 | INT | [Vision] Dflt CF LSF min points = |
| c_DfltCForthogonality | EC | 6178 | A[30] | FLT | [Vision] Dflt CF orthogonality = |
| c_ErrDetrepositionradius | EC | 6179 | A[30] | FLT | [Vision] ErrDet reposition radius = |
| c_ErrDetfidloctol | EC | 6180 | A[30] | FLT | [Vision] ErrDet fid loc tol = |
| c_ErrDetdiagdisttol | EC | 6181 | A[30] | FLT | [Vision] ErrDet diag dist tol = |
| c_ErrDetspiralarc | EC | 6182 | A[30] | FLT | [Vision] ErrDet spiral arc = |
| c_ErrDetfidskipmode | EC | 6183 | A[4] | ASCII | [Vision] ErrDet fid skip mode = |
| c_ErrDetPurge | EC | 6184 | A[4] | ASCII | [Vision] ErrDet Purge = |
| c_ErrDetMoveToPurgeStation | EC | 6185 | A[4] | ASCII | [Vision] ErrDet Move To Purge Station = |
| c_ErrDetPurgeBeforeResume | EC | 6186 | A[4] | ASCII | [Vision] ErrDet Purge Before Resume = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|------------------------|-----------|------|-----------|--------------|---|
| c_ScaleCalMove | EC | 6187 | A[30] | FLT | [Vision] Scale Cal Move = |
| c_Xcalib | EC | 6188 | A[30] | FLT | [Vision] Xcalib = |
| c_Ycalib | EC | 6189 | A[30] | FLT | [Vision] Ycalib = |
| c_UseFidZPosition | EC | 6191 | A[4] | ASCII | [Vision] Use Fid Z Position = |
| c_DfltFidSearchAtSafeZ | EC | 6192 | A[4] | ASCII | [Vision] Dflt Fid Search At Safe Z = |
| c_SensorType | EC | 6193 | A[20] | ASCII | [Needle Finder] Sensor Type = |
| c_Dottype | EC | 6194 | I4 | INT | [Needle Finder] Dot type = |
| c_NSBeam1toCorner | EC | 6195 | A[30] | FLT | [Needle Finder] NS Beam1 to Corner = |
| c_NSBeam2toCorner | EC | 6196 | A[30] | FLT | [Needle Finder] NS Beam2 to Corner = |
| c_NSBeam1torefdot | EC | 6199 | A[30] | FLT | [Needle Finder] NS Beam 1 to ref dot = |
| c_NSBeam2torefdot | EC | 6200 | A[30] | FLT | [Needle Finder] NS Beam 2 to ref dot = |
| c_NSSlot1Width | EC | 6203 | A[30] | FLT | [Needle Finder] NS Slot1Width = |
| c_NSSlot2Width | EC | 6204 | A[30] | FLT | [Needle Finder] NS Slot2Width = |
| c_NSZBeam1toCorner | EC | 6205 | A[30] | FLT | [Needle Finder] NSZ Beam1 to Corner = |
| c_NSZBeam2toCorner | EC | 6206 | A[30] | FLT | [Needle Finder] NSZ Beam2 to Corner = |
| c_NSZBeam1torefdot | EC | 6207 | A[30] | FLT | [Needle Finder] NSZ Beam 1 to ref dot = |
| c_NSZBeam2torefdot | EC | 6208 | A[30] | FLT | [Needle Finder] NSZ Beam 2 to ref dot = |
| c_NSZSlot1Width | EC | 6211 | A[30] | FLT | [Needle Finder] NSZ Slot1Width = |
| c_NSZSlot2Width | EC | 6212 | A[30] | FLT | [Needle Finder] NSZ Slot2Width = |
| c_TactileSensorInput | EC | 6213 | I4 | INT | [Needle Finder] Tactile Sensor Input = |
| c_NSBeamInput | EC | 6214 | I4 | INT | [Needle Finder] NS Beam Input = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------|-----------|------|-----------|--------------|---|
| c_NSZBeamInput | EC | 6215 | I4 | INT | [Needle Finder] NSZ Beam Input = |
| c_Slot1XY | EC | 6216 | A[40] | FLT, FLT | [Needle Finder] Slot1XY = |
| c_Slot2XY | EC | 6217 | A[40] | FLT, FLT | [Needle Finder] Slot2XY = |
| c_refDot1 | EC | 6218 | A[40] | FLT, FLT | [Needle Finder] refDot1 = |
| c_refDot2 | EC | 6219 | A[40] | FLT, FLT | [Needle Finder] refDot2 = |
| c_refDot3 | EC | 6220 | A[40] | FLT, FLT | [Needle Finder] refDot3 = |
| c_refDot4 | EC | 6221 | A[40] | FLT, FLT | [Needle Finder] refDot4 = |
| c_XsearchDir | EC | 6222 | I4 | INT | [Needle Finder] XsearchDir = |
| c_YsearchDir | EC | 6223 | I4 | INT | [Needle Finder] YsearchDir = |
| c_GoldenSafeZ | EC | 6224 | A[30] | FLT | [Needle Finder] Golden Safe Z = |
| c_CurSafeZ | EC | 6225 | A[30] | FLT | [Needle Finder] Cur Safe Z = |
| c_SafeZOffset | EC | 6226 | A[30] | FLT | [Needle Finder] Safe Z Offset = |
| c_SafeZCamXY | EC | 6227 | A[40] | FLT, FLT | [Needle Finder] Safe Z Cam XY = |
| c_suckbackPeriod | EC | 6228 | A[30] | FLT | [Needle Finder] Suckback Period = |
| c_SuckbackLength | EC | 6229 | A[30] | FLT | [Needle Finder] Suckback Length = |
| c_PurgeTimeBeforeDispense | EC | 6230 | I4 | INT | [Needle Finder] Purge Time Before Dispense = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------------|-----------|------|-----------|--------------|---|
| c_RevTimeBeforeXYZ | EC | 6231 | A[30] | FLT | [Needle Finder] Rev Time Before XYZ = |
| c_NSZVerticalSearchExt | EC | 6232 | A[30] | FLT | [Needle Finder] NSZ Vertical Search Ext = |
| c_CamCurOffset | EC | 6233 | A[40] | FLT, FLT | [Needle Finder] CamCurOffset = |
| c_Autoenable | EC | 6234 | I4 | INT | [Needle Finder] Auto enable = |
| c_MaxStep | EC | 6235 | A[30] | FLT | [Needle Finder] Max Step = |
| c_RevTimeBeforeTouch | EC | 6236 | A[30] | FLT | [Needle Finder] Rev Time Before Touch = |
| c_MinProbedz_N1 | EC | 6237 | A[30] | FLT | [Ndl Finder 1] Min Probe dz = |
| c_RatetoTactile_N1 | EC | 6238 | A[30] | FLT | [Ndl Finder 1] Rate to Tactile = |
| c_AcceltoTactile_N1 | EC | 6239 | A[30] | FLT | [Ndl Finder 1] Accel to Tactile = |
| c_RateatTactile_N1 | EC | 6240 | A[30] | FLT | [Ndl Finder 1] Rate at Tactile = |
| c_AccelatTactile_N1 | EC | 6241 | A[30] | FLT | [Ndl Finder 1] Accel at Tactile = |
| c_BackupatTactile_N1 | EC | 6242 | A[30] | FLT | [Ndl Finder 1] Backup at Tactile = |
| c_CurrentNdIXYinSlot_N1 | EC | 6243 | A[40] | FLT, FLT | [Ndl Finder 1] Current Ndl XY in Slot = |
| c_CurrentNdITipinSlot2_N1 | EC | 6244 | A[30] | FLT | [Ndl Finder 1] Current Ndl Tip in Slot2 = |
| c_forwardtime | EC | 6245 | A[30] | FLT | [Prompted Setup] forward time = |
| c_reversetime | EC | 6246 | A[30] | FLT | [Prompted Setup] reverse time = |
| c_purgetime | EC | 6247 | A[30] | FLT | [Prompted Setup] purge time = |
| c_extraZ | EC | 6248 | A[30] | FLT | [Prompted Setup] extra Z = |
| c_PrimeextraZ | EC | 6249 | A[30] | FLT | [Prompted Setup] Prime extra Z = |
| c_Valvelocwhilecheckforpurgecup | EC | 6250 | A[40] | FLT, FLT | [Prompted Setup] Valve loc while check for purge cup = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--------------------------------------|-----------|------|-----------|--------------|--|
| c_TeachZJogMove | EC | 6251 | A[30] | FLT | [Prompted Setup] Teach Z Jog Move = |
| c_TeachZJogMoveLimit | EC | 6252 | A[30] | FLT | [Prompted Setup] Teach Z Jog Move Limit = |
| c_PurgeLocTeachZJogMove | EC | 6253 | A[30] | FLT | [Prompted Setup] Purge Loc Teach Z Jog Move = |
| c_ScaleLocTeachZJogMove | EC | 6254 | A[30] | FLT | [Prompted Setup] Scale Loc Teach Z Jog Move = |
| c_UseScript | EC | 6255 | A[4] | ASCII | [Prompted Setup] Use Script = |
| c_EnableValveOffsetsVerificationStep | EC | 6256 | A[4] | ASCII | [Prompted Setup] Enable Valve Offsets Verification Step = |
| c_ValveOffsetsVerificationTolerance | EC | 6257 | A[30] | FLT | [Prompted Setup] Valve Offsets Verification Tolerance (.1 mil) = |
| c_RequireNameandLot | EC | 6258 | A[4] | ASCII | [Prompted Setup] Require Name and Lot = |
| c_Valve1PromptedSetupScriptFile | EC | 6259 | A[60] | ASCII | [Prompted Setup] Valve 1 Prompted Setup Script File = |
| c_Valve1ChangeSyringeScriptFile | EC | 6260 | A[60] | ASCII | [Prompted Setup] Valve 1 Change Syringe Script File = |
| c_Valve1LowFluidScriptFile | EC | 6261 | A[60] | ASCII | [Prompted Setup] Valve 1 Low Fluid Script File = |
| c_Light1Controller | EC | 6262 | A[20] | ASCII | [Light Manager] Light 1 Controller = |
| c_Light1DfltLevel | EC | 6263 | I4 | INT | [Light Manager] Light 1 Dflt Level = |
| c_Light1ShutterOutput | EC | 6264 | I4 | INT | [Light Manager] Light 1 Shutter Output = |
| c_Light2Controller | EC | 6265 | A[20] | ASCII | [Light Manager] Light 2 Controller = |
| c_Light2DfltLevel | EC | 6266 | I4 | INT | [Light Manager] Light 2 Dflt Level = |
| c_Light2ShutterOutput | EC | 6267 | I4 | INT | [Light Manager] Light 2 Shutter Output = |
| c_MaxRBBlueOutput | EC | 6268 | I4 | INT | [Light Manager] Max RB Blue Output = |
| c_MaxRBRedOutput | EC | 6269 | I4 | INT | [Light Manager] Max RB Red Output = |
| c_MaxRedOutput | EC | 6270 | I4 | INT | [Light Manager] Max Red Output = |
| c_LightType | EC | 6271 | A[30] | ASCII | [Light Manager] Light Type = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------|-----------|------|-----------|--------------|---|
| c_Turnlightoffonexit | EC | 6272 | A[4] | ASCII | [Light Manager] Turn light off on exit = |
| c_ControlType | EC | 6273 | A[20] | ASCII | [Valve Manager] Control Type = |
| c_DualActionHead | EC | 6274 | A[4] | ASCII | [Valve Manager] Dual Action Head = |
| c_Valve1Type | EC | 6275 | A[20] | ASCII | [Valve Manager] Valve 1 Type = |
| c_DefaultValve | EC | 6276 | I4 | INT | [Valve Manager] Default Valve = |
| c_DualActionOutput | EC | 6277 | I4 | INT | [Valve Manager] Dual Action Output = |
| c_ToggleDelay | EC | 6278 | A[30] | FLT | [Valve Manager] Toggle Delay (ms) = |
| c_Valve1FluidSensor | EC | 6279 | A[4] | ASCII | [Valve Manager] Valve 1 Fluid Sensor = |
| c_Valve2FluidSensor | EC | 6280 | A[4] | ASCII | [Valve Manager] Valve 2 Fluid Sensor = |
| c_Name_V1 | EC | 6281 | A[30] | ASCII | [Valve 1] Name = |
| c_Type_V1 | EC | 6282 | A[20] | ASCII | [Valve 1] Type = |
| c_Number_V1 | EC | 6283 | I4 | INT | [Valve 1] Number = |
| c_Enabled_V1 | EC | 6284 | A[4] | ASCII | [Valve 1] Enabled = |
| c_HasHS_V1 | EC | 6285 | A[4] | ASCII | [Valve 1] Has HS = |
| c_BitMask_V1 | EC | 6286 | I4 | INT | [Valve 1] Bit Mask = |
| c_OnState_V1 | EC | 6287 | I4 | INT | [Valve 1] On State = |
| c_OffState_V1 | EC | 6288 | I4 | INT | [Valve 1] Off State = |
| c_ReverseBitMask_V1 | EC | 6289 | I4 | INT | [Valve 1] Reverse Bit Mask = |
| c_ReverseOnState_V1 | EC | 6290 | I4 | INT | [Valve 1] Reverse On State = |
| c_ReverseOffState_V1 | EC | 6291 | I4 | INT | [Valve 1] Reverse Off State = |
| c_ForwardIObit_V1 | EC | 6292 | I4 | INT | [Valve 1] Forward IO bit = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------|-----------|------|-----------|--------------|---|
| c_ReverselObit_V1 | EC | 6293 | I4 | INT | [Valve 1] Reverse IO bit = |
| c_ZneedleOffset_V1 | EC | 6294 | A[30] | FLT | [Valve 1] Z Needle Offset = |
| c_XYNeedleOffset_V1 | EC | 6295 | A[40] | FLT, FLT | [Valve 1] XY Needle Offset = |
| c_NdltoHSoffset_V1 | EC | 6296 | A[40] | FLT, FLT | [Valve 1] Ndl to HS Offset = |
| c_PurgeLocName_V1 | EC | 6297 | A[30] | ASCII | [Valve 1] Purge Loc Name = |
| c_ScaleLocName_V1 | EC | 6298 | A[30] | ASCII | [Valve 1] Scale Loc Name = |
| c_ZstorageVariable_V1 | EC | 6299 | I4 | INT | [Valve 1] Z Storage Variable = |
| c_FluidPressure_V1 | EC | 6300 | I4 | INT | [Valve 1] Fluid Pressure = |
| c_ForwardValveSpeed_V1 | EC | 6301 | A[30] | FLT | [Valve 1] Forward Valve Speed = |
| c_ReverseValveSpeed_V1 | EC | 6302 | A[30] | FLT | [Valve 1] Reverse Valve Speed = |
| c_Acceleration_V1 | EC | 6303 | A[30] | FLT | [Valve 1] Acceleration = |
| c_Proportional_V1 | EC | 6304 | I4 | INT | [Valve 1] Proportional = |
| c_Integral_V1 | EC | 6305 | I4 | INT | [Valve 1] Integral = |
| c_Derivative_V1 | EC | 6306 | I4 | INT | [Valve 1] Derivative = |
| c_EncoderFollowingError_V1 | EC | 6307 | I4 | INT | [Valve 1] Encoder Following Error = |
| c_UseAdvancedPID_V1 | EC | 6308 | A[4] | ASCII | [Valve 1] Use Advanced PID = |
| c_AdvProportional_V1 | EC | 6309 | A[30] | FLT | [Valve 1] Adv Proportional = |
| c_AdvIntegral_V1 | EC | 6310 | A[30] | FLT | [Valve 1] Adv Integral = |
| c_AdvDerivative_V1 | EC | 6311 | A[30] | FLT | [Valve 1] Adv Derivative = |
| c_FeedForwardAccel_V1 | EC | 6312 | A[30] | FLT | [Valve 1] Feed Forward Accel = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--------------------------------|-----------|------|-----------|--------------|---|
| c_FeedForwardVelocity_V1 | EC | 6313 | A[30] | FLT | [Valve 1] Feed Forward Velocity = |
| c_StateMachineForwardSpeed_V1 | EC | 6314 | A[30] | FLT | [Valve 1] State Machine Forward Speed = |
| c_StateMachineReverseSpeed_V1 | EC | 6315 | A[30] | FLT | [Valve 1] State Machine Reverse Speed = |
| c_StateMachineDispenseDelay_V1 | EC | 6316 | I4 | INT | [Valve 1] State Machine Dispense Delay = |
| c_StateMachineRefillDelay_V1 | EC | 6317 | I4 | INT | [Valve 1] State Machine Refill Delay = |
| c_ResetOutput_V1 | EC | 6318 | I4 | INT | [Valve 1] Reset Output = |
| c_ValveControlOutput_V1 | EC | 6319 | I4 | INT | [Valve 1] Valve Control Output = |
| c_ValvePressureOutput_V1 | EC | 6320 | I4 | INT | [Valve 1] Valve Pressure Output = |
| c_FluidPressureModeOutput_V1 | EC | 6321 | I4 | INT | [Valve 1] Fluid Pressure Mode Output = |
| c_FluidPressureMode_V1 | EC | 6322 | I4 | INT | [Valve 1] Fluid Pressure Mode = |
| c_CamtoNdlDottype_V1 | EC | 6323 | I4 | INT | [Valve 1] Cam to Ndl Dot type = |
| c_AlignmentDotLocation1_V1 | EC | 6324 | A[40] | FLT, FLT | [Valve 1] Alignment Dot Location 1 = |
| c_AlignmentDotLocation2_V1 | EC | 6325 | A[40] | FLT, FLT | [Valve 1] Alignment Dot Location 2 = |
| c_AlignmentDotLocation3_V1 | EC | 6326 | A[40] | FLT, FLT | [Valve 1] Alignment Dot Location 3 = |
| c_AlignmentDotLocation4_V1 | EC | 6327 | A[40] | FLT, FLT | [Valve 1] Alignment Dot Location 4 = |
| c_NeedlePositionoverTactile_V1 | EC | 6328 | A[40] | FLT, FLT | [Valve 1] Needle Position over Tactile = |
| c_PrimeForwardTime1_V1 | EC | 6329 | A[30] | FLT | [Valve 1] Prime Forward Time 1 (sec) = |
| c_PrimeForwardTime2_V1 | EC | 6330 | A[30] | FLT | [Valve 1] Prime Forward Time 2 (sec) = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--------------|---|
| c_PrimeReverseTime_V1 | EC | 6331 | A[30] | FLT | [Valve 1] Prime Reverse Time (sec) = |
| c_PrimeExtraZ_V1 | EC | 6332 | A[30] | FLT | [Valve 1] Prime Extra Z = |
| c_IsDlgForForward_V1 | EC | 6333 | A[4] | ASCII | [Valve 1] Is Dlg For Forward = |
| c_ForwardTime_V1 | EC | 6334 | A[30] | FLT | [Valve 1] Forward Time (sec) = |
| c_ReverseTime_V1 | EC | 6335 | A[30] | FLT | [Valve 1] Reverse Time (sec) = |
| c_ForwardOnlyTime_V1 | EC | 6336 | A[30] | FLT | [Valve 1] Forward Only Time (sec) = |
| c_ReverseOnlyTime_V1 | EC | 6337 | A[30] | FLT | [Valve 1] Reverse Only Time (sec) = |
| c_FloatingHead_V1 | EC | 6338 | A[4] | ASCII | [Valve 1] Floating Head = |
| c_FloatingHeadZOvertravel_V1 | EC | 6339 | A[30] | FLT | [Valve 1] Floating Head Z Overtravel = |
| c_ConstantSyringePressure_V1 | EC | 6340 | A[4] | ASCII | [Valve 1] Constant Syringe Pressure = |
| c_SyringePressureOutput_V1 | EC | 6341 | I4 | INT | [Valve 1] Syringe Pressure Output = |
| c_LineCharLocation1_V1 | EC | 6343 | A[40] | FLT, FLT | [Valve 1] Line Char Location 1 = |
| c_LineCharLocation2_V1 | EC | 6344 | A[40] | FLT, FLT | [Valve 1] Line Char Location 2 = |
| c_DotCharLocation_V1 | EC | 6345 | A[40] | FLT | [Valve 1] Dot Char Location = |
| c_AutoRefillafterPrimingFluid_V1 | EC | 6346 | A[4] | ASCII | [Valve 1] Auto Refill after Priming Fluid = |
| c_FluidPrimingTimeoutEnabled_V1 | EC | 6347 | A[4] | ASCII | [Valve 1] Fluid Priming Timeout Enabled = |
| c_FluidPrimingTimeoutDuration_V1 | EC | 6348 | I4 | INT | [Valve 1 (Type)] Fluid Priming Timeout Duration = |
| c_PrimeHomeTimeout_V1 | EC | 6349 | A[30] | FLT | [Valve 1] Prime/Home Timeout (ms) = |
| c_RefillAfterPurge_V1 | EC | 6351 | A[4] | ASCII | [Valve 1] Refill After Purge = |
| c_RefillAfterMeasFlowRate_V1 | EC | 6352 | A[4] | ASCII | [Valve 1] Refill After Meas Flow Rate = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------|-----------|------|-----------|--------------|---|
| c_TopGearRatio_V1 | EC | 6353 | A[30] | ASCII | [Valve 1] Top Gear Ratio = |
| c_PlanetaryGearRatio_V1 | EC | 6354 | A[30] | ASCII | [Valve 1] Planetary Gear Ratio = |
| c_ChamberSize_V1 | EC | 6355 | A[30] | ASCII | [Valve 1] Chamber Size = |
| c_CleanPurgeTime | EC | 6356 | A[30] | FLT | [Valve Clean Parm] Clean Purge Time = |
| c_CleanFlushCount | EC | 6357 | I4 | INT | [Valve Clean Parm] Clean Flush Count = |
| c_CleanAirDryTime | EC | 6358 | A[30] | FLT | [Valve Clean Parm] Clean Air Dry Time = |
| c_CleanFlushOnTime | EC | 6359 | A[30] | FLT | [Valve Clean Parm] Clean Flush On Time = |
| c_CleanFlushOffTime | EC | 6360 | A[30] | FLT | [Valve Clean Parm] Clean Flush Off Time = |
| c_UserDefineROMVersion | EC | 6361 | A[30] | FLT | [Valve Clean Parm] User Define ROM Version = |
| c_PrelimNeedleLocation_V1 | EC | 6362 | A[40] | FLT, FLT | [VO Valve 1] Prelim Needle Location = |
| c_PurgeLocHSOffset_V1 | EC | 6363 | A[40] | FLT, FLT | [VO Valve 1] Purge Loc HS Offset = |
| c_PurgeLocCircumPt1_V1 | EC | 6364 | A[40] | FLT, FLT | [VO Valve 1] Purge Loc Circum Pt1 = |
| c_PurgeLocCircumPt2_V1 | EC | 6365 | A[40] | FLT, FLT | [VO Valve 1] Purge Loc Circum Pt2 = |
| c_PurgeLocCircumPt3_V1 | EC | 6366 | A[40] | FLT, FLT | [VO Valve 1] Purge Loc Circum Pt3 = |
| c_PurgeXtraZ_V1 | EC | 6367 | A[30] | FLT | [VO Valve 1] Purge Xtra Z = |
| c_PurgeTeachCenter_V1 | EC | 6368 | A[4] | ASCII | [VO Valve 1] Purge Teach Center = |
| c_ScaleLocHSOffset_V1 | EC | 6369 | A[40] | FLT, FLT | [VO Valve 1] Scale Loc HS Offset = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--------------------------------|-----------|------|-----------|--|---|
| c_ScaleLocCircumPt1_V1 | EC | 6370 | A[40] | FLT, FLT | [VO Valve 1] Scale Loc Circum Pt1 = |
| c_ScaleLocCircumPt2_V1 | EC | 6371 | A[40] | FLT, FLT | [VO Valve 1] Scale Loc Circum Pt2 = |
| c_ScaleLocCircumPt3_V1 | EC | 6372 | A[40] | FLT, FLT | [VO Valve 1] Scale Loc Circum Pt3 = |
| c_ScaleXtraZ_V1 | EC | 6373 | A[30] | FLT | [VO Valve 1] Scale Xtra Z = |
| c_ScaleTeachCenter_V1 | EC | 6374 | A[4] | ASCII | [VO Valve 1] Scale Teach Center = |
| c_ZoffsetCircumPt1_V1 | EC | 6375 | A[40] | FLT, FLT | [VO Valve 1] Zoffset Circum Pt1 = |
| c_ZoffsetCircumPt2_V1 | EC | 6376 | A[40] | FLT, FLT | [VO Valve 1] Zoffset Circum Pt2 = |
| c_ZoffsetCircumPt3_V1 | EC | 6377 | A[40] | FLT, FLT | [VO Valve 1] Zoffset Circum Pt3 = |
| c_ZoffsetTeachCenter_V1 | EC | 6378 | A[4] | ASCII | [VO Valve 1] Zoffset Teach Center = |
| c_TeachDotsCorner1_V1 | EC | 6379 | A[40] | FLT, FLT | [VO Valve 1] Teach Dots Corner 1 = |
| c_TeachDotsCorner2_V1 | EC | 6380 | A[40] | FLT, FLT | [VO Valve 1] Teach Dots Corner 2 = |
| c_ZoffsetLightStateCenterPt_V1 | EC | 6381 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Zoffset LightState Center Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open If no light levels assigned, the value is = (none) |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--|--|
| c_ZoffsetLightStateCircumPt1_V1 | EC | 6382 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Zoffset LightState Circum Pt1 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ZoffsetLightStateCircumPt2_V1 | EC | 6383 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Zoffset LightState Circum Pt2 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ZoffsetLightStateCircumPt3_V1 | EC | 6384 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Zoffset LightState Circum Pt3 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_PurgeLocLightStateCenterPt_V1 | EC | 6385 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Purge Loc LightState Center Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_PurgeLocLightStateCircumPt1_V1 | EC | 6386 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Purge Loc LightState Circum Pt1 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--|--|
| c_PurgeLocLightStateCircumPt2_V1 | EC | 6387 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Purge Loc LightState Circum Pt2 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_PurgeLocLightStateCircumPt3_V1 | EC | 6388 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Purge Loc LightState Circum Pt3 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_PurgeLocLightStateHSPt_V1 | EC | 6389 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Purge Loc LightState HS Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ScaleLocLightStateCenterPt_V1 | EC | 6390 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale Loc LightState Center Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ScaleLocLightStateCircumPt1_V1 | EC | 6391 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale Loc LightState Circum Pt1 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--|--|
| c_ScaleLocLightStateCircumPt2_V1 | EC | 6392 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale Loc LightState Circum Pt2 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ScaleLocLightStateCircumPt3_V1 | EC | 6393 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale Loc LightState Circum Pt3 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ScaleLocLightStateHSPt_V1 | EC | 6394 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale Loc LightState HS Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_TactileLightStateCenterPt_V1 | EC | 6395 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Tactile LightState Center Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_TactileLightStateCircumPt1_V1 | EC | 6396 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Tactile LightState Circum Pt1 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------------|-----------|------|-----------|--|--|
| c_TactileLightStateCircumPt2_V1 | EC | 6397 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Tactile LightState Circum Pt2 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_TactileLightStateCircumPt3_V1 | EC | 6398 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Tactile LightState Circum Pt3 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_SafeZLightStatePt_V1 | EC | 6399 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Safe Z LightState Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_NdlToCamLightStatePt_V1 | EC | 6400 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Ndl To Cam LightState Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_HSToCamLightStatePt_V1 | EC | 6401 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] HS To Cam LightState Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------------|-----------|------|-----------|--|---|
| c_SubstrateLightStateCorner1_V1 | EC | 6402 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Substrate LightState Corner1 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_SubstrateLightStateCorner2_V1 | EC | 6403 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Substrate LightState Corner2 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ZoffsetTolerance_V1 | EC | 6404 | A[30] | FLT | [VO Valve 1] Zoffset Tolerance = |
| c_ZoffsetRepeat_V1 | EC | 6405 | I4 | INT | [VO Valve 1] Zoffset Repeat = |
| c_DispDotLightStatePt_V1 | EC | 6406 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Disp Dot LightState Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_NdltoNdlPt_V1 | EC | 6407 | A[40] | FLT, FLT | [VO Valve 1] Ndl to Ndl Pt = |
| c_NdlBeam1_V1 | EC | 6408 | A[40] | FLT, FLT | [Needle XYZ Valve 1] Ndl Beam 1 = |
| c_NdlBeam2_V1 | EC | 6409 | A[40] | FLT, FLT | [Needle XYZ Valve 1] Ndl Beam 2 = |
| c_SubstrateHSLoc_V1 | EC | 6410 | A[40] | FLT, FLT | [Needle XYZ Valve 1] Substrate HS Loc = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--------------|---|
| c_SubstrateHSZ_V1 | EC | 6411 | A[30] | FLT | [Needle XYZ Valve 1] Substrate HS Z = |
| c_SubstrateNdlLoc_V1 | EC | 6412 | A[40] | FLT, FLT | [Needle XYZ Valve 1] Substrate Ndl Loc = |
| c_SubstrateNdlZ_V1 | EC | 6413 | A[30] | FLT | [Needle XYZ Valve 1] Substrate Ndl Z = |
| c_CurrentHSXYinSlot_V1 | EC | 6414 | A[40] | FLT, FLT | [Needle XYZ Valve 1] Current HS XY in Slot = |
| c_CurrentNdlTipinSlot2_V1 | EC | 6415 | A[30] | FLT | [Needle XYZ Valve 1] Current Ndl Tip in Slot2 = |
| c_CurrentHSTipinSlot2_V1 | EC | 6416 | A[30] | FLT | [Needle XYZ Valve 1] Current HS Tip in Slot2 = |
| c_HSTDXY_V1 | EC | 6417 | A[40] | FLT, FLT | [Needle XYZ Valve 1] HS TD XY = |
| c_HSTDZ_V1 | EC | 6418 | A[30] | FLT | [Needle XYZ Valve 1] HS TD Z = |
| c_NdlTDXY_V1 | EC | 6419 | A[40] | FLT, FLT | [Needle XYZ Valve 1] Ndl TD XY = |
| c_NdlTDZ_V1 | EC | 6420 | A[30] | FLT | [Needle XYZ Valve 1] Ndl TD Z = |
| c_ForceReteachBeams_V1 | EC | 6431 | A[4] | ASCII | [Needle XYZ Valve 1] Force Re-teach Beams = |
| c_SkipHeightSenseforXYOffsets_V1 | EC | 6432 | A[4] | ASCII | [Needle XYZ Valve 1] Skip Height Sense for XY Offsets = |
| c_HeaterOffsets | EC | 6433 | A[4] | ASCII | [Local Machine Offsets] Heater Offsets = |
| c_HeaterMaint | EC | 6434 | A[4] | ASCII | [Local Machine Offsets] Heater Maint = |
| c_HeaterWarn | EC | 6435 | I4 | INT | [Local Machine Offsets] Heater Warn = |
| c_HeaterFail | EC | 6436 | I4 | INT | [Local Machine Offsets] Heater Fail = |
| c_WorkpieceOrigin | EC | 6437 | A[4] | ASCII | [Local Machine Offsets] Workpiece Origin = |
| c_WorkpieceOriginName | EC | 6438 | A[30] | ASCII | [Local Machine Offsets] Workpiece Origin Name = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-----------------------------|-----------|------|-----------|--|---|
| c_WorkpieceMaint | EC | 6439 | A[4] | ASCII | [Local Machine Offsets] Workpiece Maint = |
| c_WorkpieceWarn | EC | 6440 | I4 | INT | [Local Machine Offsets] Workpiece Warn = |
| c_WorkpieceFail | EC | 6441 | I4 | INT | [Local Machine Offsets] Workpiece Fail = |
| c_ValveBias | EC | 6442 | A[4] | ASCII | [Local Machine Offsets] Valve Bias = |
| c_ValveMaint | EC | 6443 | A[4] | ASCII | [Local Machine Offsets] Valve Maint = |
| c_ValveWarn | EC | 6444 | I4 | INT | [Local Machine Offsets] Valve Warn = |
| c_ValveFail | EC | 6445 | I4 | INT | [Local Machine Offsets] Valve Fail = |
| c_ValveBiasMax | EC | 6446 | A[30] | FLT | [Local Machine Offsets] Valve Bias Max = |
| c_ValveBiasMin | EC | 6447 | A[30] | FLT | [Local Machine Offsets] Valve Bias Min = |
| c_PurgeUseFids | EC | 6448 | A[4] | ASCII | [Machine Fiducial Setup] Purge Use Fids = |
| c_PurgeNumberofFids | EC | 6449 | I4 | INT | [Machine Fiducial Setup] Purge Number of Fids = |
| c_Purge1FidTaught | EC | 6450 | A[4] | ASCII | [Machine Fiducial Setup] Purge 1 Fid Taught = |
| c_Purge3FidsTaught | EC | 6451 | A[4] | ASCII | [Machine Fiducial Setup] Purge 3 Fids Taught = |
| c_PurgeOffsetFromCenter | EC | 6452 | A[40] | FLT, FLT | [Machine Fiducial Setup] Purge Offset From Center = |
| c_PurgeUseOffsetFromCenter | EC | 6453 | A[4] | ASCII | [Machine Fiducial Setup] Purge Use Offset From Center = |
| c_PurgeConfirmLocLightstate | EC | 6454 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [Machine Fiducial Setup] Purge Confirm Loc Lightstate = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_PurgeOpAutoLoc | EC | 6455 | A[4] | ASCII | [Machine Fiducial Setup] Purge Op Auto Loc = |
| c_PurgeOpVerifyFinalLoc | EC | 6456 | A[4] | ASCII | [Machine Fiducial Setup] Purge Op Verify Final Loc = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-----------------------------|-----------|------|-----------|--|---|
| c_PurgeOpAdjustFinalLoc | EC | 6457 | A[4] | ASCII | [Machine Fiducial Setup] Purge Op Adjust Final Loc = |
| c_PurgeOpFinalLocPause | EC | 6458 | A[4] | ASCII | [Machine Fiducial Setup] Purge Op Final Loc Pause = |
| c_PurgeOpFinalLocPauseSecs | EC | 6459 | I4 | INT | [Machine Fiducial Setup] Purge Op Final Loc Pause Secs = |
| c_PurgeOpManualFidFind | EC | 6460 | A[4] | ASCII | [Machine Fiducial Setup] Purge Op Manual Fid Find = |
| c_PurgeOpSkipHSAdjust | EC | 6461 | A[4] | ASCII | [Machine Fiducial Setup] Purge Op Skip HS Adjust = |
| c_ScaleUseFids | EC | 6462 | A[4] | ASCII | [Machine Fiducial Setup] Scale Use Fids = |
| c_ScaleNumberofFids | EC | 6463 | I4 | INT | [Machine Fiducial Setup] Scale Number of Fids = |
| c_Scale1FidTaught | EC | 6464 | A[4] | ASCII | [Machine Fiducial Setup] Scale 1 Fid Taught = |
| c_Scale3FidsTaught | EC | 6465 | A[4] | ASCII | [Machine Fiducial Setup] Scale 3 Fids Taught = |
| c_ScaleOffsetFromCenter | EC | 6466 | A[40] | FLT, FLT | [Machine Fiducial Setup] Scale Offset From Center = |
| c_ScaleUseOffsetFromCenter | EC | 6467 | A[4] | ASCII | [Machine Fiducial Setup] Scale Use Offset From Center = |
| c_ScaleConfirmLocLightstate | EC | 6468 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [Machine Fiducial Setup] Scale Confirm Loc Lightstate = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_ScaleOpAutoLoc | EC | 6469 | A[4] | ASCII | [Machine Fiducial Setup] Scale Op Auto Loc = |
| c_ScaleOpVerifyFinalLoc | EC | 6470 | A[4] | ASCII | [Machine Fiducial Setup] Scale Op Verify Final Loc = |
| c_ScaleOpAdjustFinalLoc | EC | 6471 | A[4] | ASCII | [Machine Fiducial Setup] Scale Op Adjust Final Loc = |
| c_ScaleOpFinalLocPause | EC | 6472 | A[4] | ASCII | [Machine Fiducial Setup] Scale Op Final Loc Pause = |
| c_ScaleOpFinalLocPauseSecs | EC | 6473 | I4 | INT | [Machine Fiducial Setup] Scale Op Final Loc Pause Secs = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-------------------------------|-----------|------|-----------|--|---|
| c_ScaleOpManualFidFind | EC | 6474 | A[4] | ASCII | [Machine Fiducial Setup] Scale Op Manual Fid Find = |
| c_ScaleOpSkipHSAdjust | EC | 6475 | A[4] | ASCII | [Machine Fiducial Setup] Scale Op Skip HS Adjust = |
| c_TactileUseFids | EC | 6476 | A[4] | ASCII | [Machine Fiducial Setup] Tactile Use Fids = |
| c_TactileNumberOfFids | EC | 6477 | I4 | INT | [Machine Fiducial Setup] Tactile Number of Fids = |
| c_Tactile1FidTaught | EC | 6478 | A[4] | ASCII | [Machine Fiducial Setup] Tactile 1 Fid Taught = |
| c_Tactile3FidsTaught | EC | 6479 | A[4] | ASCII | [Machine Fiducial Setup] Tactile 3 Fids Taught = |
| c_TactileOffsetFromCenter | EC | 6480 | A[40] | FLT, FLT | [Machine Fiducial Setup] Tactile Offset From Center = |
| c_TactileUseOffsetFromCenter | EC | 6481 | A[4] | ASCII | [Machine Fiducial Setup] Tactile Use Offset From Center = |
| c_TactileConfirmLocLightstate | EC | 6482 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [Machine Fiducial Setup] Tactile Confirm Loc Lightstate = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_TactileOpAutoLoc | EC | 6483 | A[4] | ASCII | [Machine Fiducial Setup] Tactile Op Auto Loc = |
| c_TactileOpVerifyFinalLoc | EC | 6484 | A[4] | ASCII | [Machine Fiducial Setup] Tactile Op Verify Final Loc = |
| c_TactileOpAdjustFinalLoc | EC | 6485 | A[4] | ASCII | [Machine Fiducial Setup] Tactile Op Adjust Final Loc = |
| c_TactileOpManualFidFind | EC | 6486 | A[4] | ASCII | [Machine Fiducial Setup] Tactile Op Manual Fid Find = |
| c_SubstrateUseFids | EC | 6487 | A[4] | ASCII | [Machine Fiducial Setup] Substrate Use Fids = |
| c_SubstrateNumberOfFids | EC | 6488 | I4 | INT | [Machine Fiducial Setup] Substrate Number of Fids = |
| c_Substrate2FidsTaught | EC | 6489 | A[4] | ASCII | [Machine Fiducial Setup] Substrate 2 Fids Taught = |
| c_SubstrateOpManualFidFind | EC | 6490 | A[4] | ASCII | [Machine Fiducial Setup] Substrate Op Manual Fid Find = |
| c_NdlFinderUseFids | EC | 6491 | A[4] | ASCII | [Machine Fiducial Setup] NdlFinder Use Fids = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---------------------------------|-----------|------|-----------|--|---|
| c_NdlFinderNumberofFids | EC | 6492 | I4 | INT | [Machine Fiducial Setup] NdlFinder Number of Fids = |
| c_NdlFinder1FidTaught | EC | 6493 | A[4] | ASCII | [Machine Fiducial Setup] NdlFinder 1 Fid Taught = |
| c_NdlFinderConfirmLocLightstate | EC | 6494 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [Machine Fiducial Setup] NdlFinder Confirm Loc Lightstate = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_NdlFinderOpAutoLoc | EC | 6495 | A[4] | ASCII | [Machine Fiducial Setup] NdlFinder Op Auto Loc = |
| c_NdlFinderOpVerifyFinalLoc | EC | 6496 | A[4] | ASCII | [Machine Fiducial Setup] NdlFinder Op Verify Final Loc = |
| c_DJTactileHSOffset_V1 | EC | 6501 | A[40] | FLT, FLT | [VO Valve 1] DJ Tactile HS Offset = |
| c_DJCycleCount_V1 | EC | 6502 | A[30] | FLT | [Valve 1] DJ Cycle Count = |
| c_CheckDJFlowRate_V1 | EC | 6504 | A[30] | FLT | [Flow Rate Manager] Check DJ Flowrate Valve 1 (mg/dot) |
| c_CheckDJFlowRate_V2 | EC | 6505 | A[30] | FLT | [Flow Rate Manager] Check DJ Flowrate Valve 2 (mg/dot) |
| c_LmoHeightSenseEnabled | EC | 6506 | A[4] | ASCII | [Local Machine Offsets] Height Sense = |
| c_LmoHeightSenseMaintEnabled | EC | 6507 | A[4] | ASCII | [Local Machine Offsets] Height Sense Maint = |
| c_LmoHeightSenseMaintWarnDays | EC | 6508 | I4 | INT | [Local Machine Offsets] Height Sense Warn = |
| c_LmoHeightSenseMaintFailDays | EC | 6509 | I4 | INT | [Local Machine Offsets] Height Sense Fail = |
| c_PrimeForwardMaxRetriesDJ9K_V1 | EC | 6510 | I4 | INT | [Valve 1] Prime Forward Max Retries For DJ 9K (times) = |
| c_PrimeForwardInitTimeDJ9K_V1 | EC | 6511 | A[30] | FLT | [Valve 1] Prime Forward Init Time For DJ 9K (sec) = |
| c_PrimeForwardInitWeightDJ9K_V1 | EC | 6512 | A[30] | FLT | [Valve 1] Prime Forward Init Weight For DJ 9K (mg) = |
| c_PrimeForwardTimeDJ9K_V1 | EC | 6513 | A[30] | FLT | [Valve 1] Prime Forward Time For DJ 9K (sec) = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--|---|
| c_PrimeForwardWeightDJ9K_V1 | EC | 6514 | A[30] | FLT | [Valve 1] Prime Forward Weight For DJ 9K (mg) = |
| c_PrimeForwardWeightDiffDJ9K_V1 | EC | 6515 | A[30] | FLT | [Valve 1] Prime Forward Stop Weight Difference For DJ 9K (mg) = |
| c_PrimeForwardAutoRun_V1 | EC | 6516 | A[4] | ASCII | [Valve 1] Prime Forward Auto Run Next Time = |
| c_LmoHeightSenseLane1 | EC | 6517 | A[30] | FLT | [Local Machine Offsets] Height Sense Value Lane 1 = |
| c_LmoHeightSenseLane2 | EC | 6518 | A[30] | FLT | [Local Machine Offsets] Height Sense Value Lane 2 = |
| c_AirflowUnits | EC | 6520 | I4 | INT | [Airflow Manager] Units = |
| c_DJFlowrate_V1 | EC | 6521 | A[30] | FLT | [Flow Rate Manager] DJ Flowrate 1 (mg/dot) = |
| c_DJFlowrate_V2 | EC | 6522 | A[30] | FLT | [Flow Rate Manager] DJ Flowrate 2 (mg/dot) = |
| c_CpH_Enabled | EC | 6523 | A[4] | ASCII | [Heater Manager] Controlled Process Heat = |
| c_Scale2LocName_V1 | EC | 6524 | A[30] | ASCII | [Valve 2] Scale 2 Loc Name = |
| c_ServiceStationFidXY_1 | EC | 6526 | A[40] | FLT, FLT | [Service Station Setup] Left Pin Location = |
| c_ServiceStationFidXY_2 | EC | 6527 | A[40] | FLT, FLT | [Service Station Setup] Right Pin Location = |
| c_DJOffsetHeadSpeed_V1 | EC | 6539 | A[30] | FLT | [Valve 1] DJ Offset Calibration Speed (FMW/sec) = |
| c_DJOffsetDispenseGap_V1 | EC | 6540 | A[30] | FLT | [Valve 1] DJ Offset Calibration Dispense Gap (FMW) = |
| c_Scale2LocLightStateCenterPt_V1 | EC | 6544 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale 2 Loc LightState Center Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-----------------------------------|-----------|------|-----------|--|--|
| c_Scale2LocLightStateCircumPt1_V1 | EC | 6545 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale 2 Loc LightState Circum Pt1 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_Scale2LocLightStateCircumPt2_V1 | EC | 6546 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale 2 Loc LightState Circum Pt2 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_Scale2LocLightStateCircumPt3_V1 | EC | 6547 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale 2 Loc LightState Circum Pt3 = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_Scale2LocLightStateHSPt_V1 | EC | 6548 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [VO Valve 1] Scale 2 Loc LightState HS Pt = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_Scale2LocHSOffset_V1 | EC | 6549 | A[40] | FLT, FLT | [VO Valve 1] Scale 2 Loc HS Offset = |
| c_Scale2LocCircumPt1_V1 | EC | 6550 | A[40] | FLT, FLT | [VO Valve 1] Scale 2 Loc Circum Pt1 = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|------------------------------|-----------|------|-----------|--|---|
| c_Scale2LocCircumPt2_V1 | EC | 6551 | A[40] | FLT, FLT | [VO Valve 1] Scale 2 Loc Circum Pt2 = |
| c_Scale2LocCircumPt3_V1 | EC | 6552 | A[40] | FLT, FLT | [VO Valve 1] Scale 2 Loc Circum Pt3 = |
| c_Scale2XtraZ_V1 | EC | 6553 | A[30] | FLT | [VO Valve 1] Scale 2 Xtra Z = |
| c_Scale2TeachCenter_V1 | EC | 6554 | A[4] | ASCII | [VO Valve 1] Scale 2 Teach Center = |
| c_Scale2UseFids | EC | 6555 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Use Fids = |
| c_Scale2NumberofFids | EC | 6556 | I4 | INT | [Machine Fiducial Setup] Scale 2 Number of Fids = |
| c_Scale2_1FidTaught | EC | 6557 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 1 Fid Taught = |
| c_Scale2_3FidsTaught | EC | 6558 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 3 Fids Taught |
| c_Scale2OffsetFromCenter | EC | 6559 | A[40] | FLT, FLT | [Machine Fiducial Setup] Scale 2 Offset From Center = |
| c_Scale2UseOffsetFromCenter | EC | 6560 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Use Offset From Center = |
| c_Scale2ConfirmLocLightstate | EC | 6561 | A[40] | INT, BOOL, INT, BOOL, INT, BOOL | [Machine Fiducial Setup] Scale 2 Confirm Loc Lightstate = light level 1, shutter 1 open, light level 2, shutter 2 open, light level 3, shutter 3 open |
| c_Scale2OpAutoLoc | EC | 6562 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Op Auto Loc = |
| c_Scale2OpVerifyFinalLoc | EC | 6563 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Op Verify Final Loc = |
| c_Scale2OpAdjustFinalLoc | EC | 6564 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Op Adjust Final Loc = |
| c_Scale2OpFinalLocPause | EC | 6565 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Op Final Loc Pause = |
| c_Scale2OpFinalLocPauseSecs | EC | 6566 | I4 | INT | [Machine Fiducial Setup] Scale 2 Op Final Loc Pause Secs = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|------------------------------|-----------|------|-----------|--------------|---|
| c_Scale2OpManualFidFind | EC | 6567 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Op Manual Fid Find = |
| c_Scale2OpSkipHSAdjust | EC | 6568 | A[4] | ASCII | [Machine Fiducial Setup] Scale 2 Op Skip HS Adjust = |
| c_ElectronicPressureEnabled | EC | 6569 | A[4] | ASCII | [E/P Control Manager] Enabled = |
| c_ElectronicPressureUnits | EC | 6570 | A[10] | ASCII | [E/P Control Manager] Setting Units = |
| c_OverflowTimeLimit | EC | 6571 | I4 | INT | [Purge Station] Overflow time limit (minutes) = |
| c_ElapsedPurgeTime | EC | 6572 | A[30] | FLT | [Purge Station] Elapsed purge time (minutes) = |
| c_DJOffset_V2 | EC | 6573 | A[30] | FLT | [Valve 2] DJ dispense offset time (ms) (valve 2) = |
| c_DJOffsetInitialDotXY_V2 | EC | 6574 | A[40] | FLT, FLT | [Valve 2] DJ Offset Calibration Line Start Pt (valve 2) = |
| c_DJOffsetHeadSpeed_V2 | EC | 6575 | A[30] | FLT | [Valve 2] DJ Offset Calibration Speed (FMW/sec) (valve 2) = |
| c_DJOffsetDispenseGap_V2 | EC | 6576 | A[30] | FLT | [Valve 2] DJ Offset Calibration Dispense Gap (FMW) (valve 2) = |
| c_DJOffsetUseDotFinder | EC | 6577 | I[2] | INT | [Valve 1] DJ Offset Calibration Use Dot Finder = |
| c_DJOffsetRunUnassisted | EC | 6578 | A[4] | ASCII | [Valve 1] DJ Offset Calibration Run Unassisted = |
| c_ActiveNozzleEnabled | EC | 6580 | A[4] | ASCII | [Valve 1] Active Nozzle Enabled = |
| c_DJOffsetCalEndPtXY_V2 | EC | 6581 | A[40] | FLT, FLT | [Valve 2] DJ Offset Calibration Line End Pt (valve 2) = |
| c_ServiceStationSubstrateTL | EC | 6582 | A[40] | FLT, FLT | [Service Station Setup] Substrate Top Left Offset = |
| c_ServiceStationSubstrateBR | EC | 6583 | A[40] | FLT, FLT | [Service Station Setup] Substrate Bottom Right Offset = |
| c_ImageCaptureWpFidsFound | EC | 6584 | A[4] | ASCII | [Image Capture] Workpiece Fids Found = |
| c_ImageCaptureWpFidsNotFound | EC | 6585 | A[4] | ASCII | [Image Capture] Workpiece Fids Not Found = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--------------|---|
| c_ImageCapturePattFidsFound | EC | 6586 | A[4] | ASCII | [Image Capture] Pattern Fids Found = |
| c_ImageCapturePattFidsNotFound | EC | 6587 | A[4] | ASCII | [Image Capture] Pattern Fids Not Found = |
| c_ImageCaptureServiceStationPins | EC | 6588 | A[4] | ASCII | [Image Capture] Service Station Pins = |
| c_ImageCaptureLUCModelTeachFind | EC | 6589 | A[4] | ASCII | [Image Capture] Lookup Camera Teach/Find = |
| c_FindWorkpieceFids | EC | 6590 | A[4] | ASCII | [Gem Manager] Find Workpiece Fids = |
| c_FindPatternFids | EC | 6591 | A[4] | ASCII | [Gem Manager] Find Pattern Fids = |
| c_ImageCaptureXYOffsetDots | EC | 6597 | A[4] | ASCII | [Image Capture] Needle XY Offset Dots = |
| c_ImageCaptureLmoWpFids | EC | 6598 | A[4] | ASCII | [Image Capture] LMO Workpiece Fids = |
| c_ImageCaptureFilenamePrefix | EC | 6599 | A[50] | ASCII | [Image Capture] Image Filename Prefix = |
| c_OperatorLevel | EC | 6600 | I4 | INT | [Password] Mode = |
| c_UseServiceStationData | EC | 6601 | A[4] | ASCII | [Service Station Setup] Use Service Station Data = |
| c_PurgeBeforeRun_V1 | EC | 6602 | A[4] | ASCII | [Runtime Preferences] Valve 1 Purge Before Run = |
| c_LotControlEnabled | EC | 6604 | A[4] | ASCII | [Runtime Preferences] Lot Control Enabled = |
| c_CheckAirPressEveryInstruction | EC | 6605 | I4 | INT | [Runtime Preferences] Check System Air Pressure Every Instruction = |
| c_ConveyorEmptyTimeLimit | EC | 6606 | I4 | INT | [Runtime Preferences] Conveyor Empty Time Limit (sec) = |
| c_EnableToolingVacuum_1 | EC | 6607 | A[4] | ASCII | [Runtime Preferences] Check Tooling Vacuum (ON/OFF) = |
| c_ToolingVacuumInput_1 | EC | 6608 | I4 | INT | [Runtime Preferences] Tooling Vacuum Input = |
| c_EnableToolingVacuum_2 | EC | 6609 | A[4] | ASCII | [Runtime Preferences] Check Tooling Vacuum 2 (ON/OFF) = |
| c_ToolingVacuumInput_2 | EC | 6610 | I4 | INT | [Runtime Preferences] Tooling Vacuum Input 2 = |
| c_E10StatesEnabled | EC | 6611 | A[4] | ASCII | [E10 States] E10 States Enabled = |
| c_GenErrStateEnabledBeacon | EC | 6612 | A[4] | ASCII | [Beacon] General Error State Enabled Beacon |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--------------|---|
| c_GenErrStateEnabledAudAlarm | EC | 6613 | A[4] | ASCII | [Beacon] General Error State Enabled Aud Alarm = |
| c_GenErrStateOutputBit | EC | 6614 | I4 | INT | [Beacon] General Error State Output Bit = |
| c_GenErrStateOutputLevel | EC | 6615 | A[40] | ASCII | [Beacon] General Error State Output Level = |
| c_VisionErrStateEnabledBeacon | EC | 6616 | A[4] | ASCII | [Beacon] Vision Error State Enabled Beacon = |
| c_VisionErrStateEnabledAudAlarm | EC | 6617 | A[4] | ASCII | [Beacon] Vision Error State Enabled Aud Alarm = |
| c_VisionErrStateOutputBit | EC | 6618 | I4 | INT | [Beacon] Vision Error State Output Bit = |
| c_VisionErrOutputLevel | EC | 6619 | A[40] | ASCII | [Beacon] Vision Error State Output Level = |
| c_HeaterErrStateEnabledBeacon | EC | 6620 | A[4] | ASCII | [Beacon] Heater Error State Enabled Beacon = |
| c_HeaterErrStateEnabledAudAlarm | EC | 6621 | A[4] | ASCII | [Beacon] Heater Error State Enabled Aud Alarm = |
| c_HeaterErrStateOutputBit | EC | 6622 | I4 | INT | [Beacon] Heater Error State Output Bit = |
| c_HeaterErrStateOutputLevel | EC | 6623 | A[40] | ASCII | [Beacon] Heater Error State Output Level = |
| c_ProdRunStateEnabledBeacon | EC | 6624 | A[4] | ASCII | [Beacon] Production Run State Enabled Beacon = |
| c_ProdRunStateEnabledAudAlarm | EC | 6625 | A[4] | ASCII | [Beacon] Production Run State Enabled Aud Alarm = |
| c_ProdRunStateOutputBit | EC | 6626 | I4 | INT | [Beacon] Production Run State Output Bit = |
| c_ProdRunStateOutputLevel | EC | 6627 | A[40] | ASCII | [Beacon] Production Run State Output Level = |
| c_ProgRunStateEnabledBeacon | EC | 6628 | A[4] | ASCII | [Beacon] Programming Run State Enabled Beacon = |
| c_ProgRunStateEnabledAudAlarm | EC | 6629 | A[4] | ASCII | [Beacon] Programming Run State Enabled Aud Alarm = |
| c_ProgRunStateOutputBit | EC | 6630 | I4 | INT | [Beacon] Programming Run State Output Bit = |
| c_ProgRunStateOutputLevel | EC | 6631 | A[40] | ASCII | [Beacon] Programming Run State Output Level = |
| c_SECSGEMRunStateEnabledBeacon | EC | 6632 | A[4] | ASCII | [Beacon] SECS/GEM Run State Enabled Beacon = |
| c_SECSGEMRunStateEnabledAudAlarm | EC | 6633 | A[4] | ASCII | [Beacon] SECS/GEM Run State Enabled Aud Alarm = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|---|-----------|------|-----------|--------------|---|
| c_SECSGEMRunStateOutputBit | EC | 6634 | I4 | INT | [Beacon] SECS/GEM Run State Output Bit = |
| c_SECSGEMRunStateOutputLevel | EC | 6635 | A[40] | ASCII | [Beacon] SECS/GEM Run State Output Level = |
| c_DryRunStateEnabledBeacon | EC | 6636 | A[4] | ASCII | [Beacon] Dry Run State Enabled Beacon = |
| c_DryRunStateEnabledAudAlarm | EC | 6637 | A[4] | ASCII | [Beacon] Dry Run State Enabled Aud Alarm = |
| c_DryRunStateOutputBit | EC | 6638 | I4 | INT | [Beacon] Dry Run State Output Bit = |
| c_DryRunStateOutputLevel | EC | 6639 | A[40] | ASCII | [Beacon] Dry Run State Output Level = |
| c_LowFluidStateEnabledBeacon | EC | 6640 | A[4] | ASCII | [Beacon] Low Fluid State Enabled Beacon = |
| c_LowFluidStateEnabledAudAlarm | EC | 6641 | A[4] | ASCII | [Beacon] Low Fluid State Enabled Aud Alarm = |
| c_LowFluidOutputBit | EC | 6642 | I4 | INT | [Beacon] Low Fluid State Output Bit = |
| c_LowFluidAuxOutputBit | EC | 6643 | I4 | INT | [Beacon] Low Fluid State Auxiliary Output Bit = |
| c_LowFluidOutputLevel | EC | 6644 | A[40] | ASCII | [Beacon] Low Fluid State Output Level = |
| c_LowFluidBoardCntDwnStateEnabledBeacon | EC | 6645 | A[4] | ASCII | [Beacon] Low Fluid Board Countdown State Enabled Beacon = |
| c_LowFluidBoardCntDwnStateEnabledAudAlarm | EC | 6646 | A[4] | ASCII | [Beacon] Low Fluid Board Countdown State Enabled Aud Alarm = |
| c_LowFluidBoardCntDwnOutputBit | EC | 6647 | I4 | INT | [Beacon] Low Fluid Board Countdown State Output Bit = |
| c_LowFluidBoardCntDwnOutputLevel | EC | 6648 | A[40] | ASCII | [Beacon] Low Fluid Board Countdown State Output Level = |
| c_PotLifeLowStateEnabledBeacon | EC | 6649 | A[4] | ASCII | [Beacon] Pot Life Low State Enabled Beacon = |
| c_PotLifeLowStateEnabledAudAlarm | EC | 6650 | A[4] | ASCII | [Beacon] Pot Life Low State Enabled Aud Alarm = |
| c_PotLifeLowOutputBit | EC | 6651 | I4 | INT | [Beacon] Pot Life Low State Output Bit = |
| c_PotLifeLowOutputLevel | EC | 6652 | A[40] | ASCII | [Beacon] Pot Life Low State Output Level = |
| c_PotLifeExpStateEnabledBeacon | EC | 6653 | A[4] | ASCII | [Beacon] Pot Life Expired State Enabled Beacon = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------------|-----------|------|-----------|--------------|---|
| c_PotLifeExpStateEnabledAudAlarm | EC | 6654 | A[4] | ASCII | [Beacon] Pot Life Expired State Enabled Aud Alarm = |
| c_PotLifeExpOutputBit | EC | 6655 | I4 | INT | [Beacon] Pot Life Expired Output Bit = |
| c_PotLifeExpOutputLevel | EC | 6656 | A[40] | ASCII | [Beacon] Pot Life Expired State Output Level = |
| c_FmIdleStateEnabledBeacon | EC | 6657 | A[4] | ASCII | [Beacon] FmNT Idle State Enabled Beacon = |
| c_FmIdleStateEnabledAudAlarm | EC | 6658 | A[4] | ASCII | [Beacon] FmNT Idle State Enabled Aud Alarm = |
| c_FmIdleOutputBit | EC | 6659 | I4 | INT | [Beacon] FmNT Idle State Output Bit = |
| c_FmIdleOutputLevel | EC | 6660 | A[40] | ASCII | [Beacon] FmNT Idle State Output Level = |
| c_LowAirThreshold | EC | 6661 | I4 | INT | [Motion Controller] Low Air DAC Threshold |
| c_FlowmeterEnabled | | 6662 | A[4] | ASCII | [Flowmeter] Enabled = |
| c_ME LaserRangeFinderMode | EC | 6663 | A[4] | ASCII | [Height Sensor] ME Laser Range Finder Mode = |
| c_HeightSenseMode | EC | 6664 | I4 | INT | [Height Sensor] Height Sense Mode = |
| c_ME LaserHSDownSpeed | EC | 6665 | A[30] | FLT | [Height Sensor] Down Speed ME Laser HS = |
| c_ME LaserHSUpSpeed | EC | 6666 | A[30] | FLT | [Height Sensor] Up Speed ME Laser HS = |
| c_ME LaserHSAccel | EC | 6667 | A[30] | FLT | [Height Sensor] Accel ME Laser HS = |
| c_ME LaserHSMaxDist | EC | 6668 | A[30] | FLT | [Height Sensor] Max Dist ME Laser HS = |
| c_ME LaserHSMaxDistRunTime | EC | 6669 | A[30] | FLT | [Height Sensor] Max Dist ME Laser HS Run Time = |
| c_ME LaserHSRetractDist | EC | 6670 | A[30] | FLT | [Height Sensor] Retract Ht (FMW) ME Laser HS = |
| c_RetractBeforeHeightSense | EC | 6671 | A[4] | ASCII | [Height Sensor] Retract Before Height Sense = |
| c_MonitorPurgeCupOverflowTime | EC | 6672 | A[4] | ASCII | [Purge Station] Monitor purge cup overflow time = |
| c_ScaleCalibWeight | EC | 6673 | A[30] | FLT | [Scale Manager] Calibration Weight = |
| c_WorkpieceNumberOfFids | EC | 6675 | I4 | INT | [Wkpc Align Options] Num Fids = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|------------------------------------|-----------|------|-----------|--------------|---|
| c_VerifyWkpcOrgNoFids | EC | 6676 | A[4] | ASCII | [Wkpc Align Options] Verify Origin When No Fids = |
| c_AutoConveyorWidthEnable | EC | 6677 | A[4] | ASCII | [Conveyor Manager] Automatic Conveyor Width = |
| c_AutoConveyorWidthEnable2 | EC | 6678 | A[4] | ASCII | [Conveyor Manager] Automatic Conveyor 2 Width = |
| c_ConfirmACWMove2 | EC | 6679 | A[4] | ASCII | [Conveyor Manager] Confirm ACW Move Conveyor 2 = |
| c_AutoPurgeEnabled | EC | 6680 | A[4] | ASCII | [Heater Manager] Enabled Autopurge = |
| c_PreHeatTimerEnabled | EC | 6681 | A[4] | ASCII | [Heater Manager] Enable Pre-Heat Timer = |
| c_DefaultPreHeatTime | EC | 6683 | I4 | INT | [Heater Manager] Default Pre-Heat Time = |
| c_WarnHeaterFileChange | EC | 6684 | A[4] | ASCII | [Heater Manager] Warn If Heater File Modified = |
| c_RunRecoveryEnabled | EC | 6685 | A[4] | ASCII | [Motion Controller] Enable Run Recovery = |
| c_RecoveryPromptPosition | EC | 6686 | I4 | INT | [Motion Controller] Recovery Prompt Position = |
| c_SkipDryRunRecovery | EC | 6687 | A[4] | ASCII | [Motion Controller] Skip Dry Run Recovery = |
| c_WarnIfRecoverySkipped | EC | 6688 | A[4] | ASCII | [Motion Controller] Warn if Recovery Skipped = |
| c_DoHSRunRecovery | EC | 6689 | A[4] | ASCII | [Motion Controller] Do Height Sense in Run Recovery = |
| c_ModuleReaderEnabled | EC | 6690 | A[4] | ASCII | [Module Status Manager] Enable = |
| c_CheckDiskSpaceProd | EC | 6691 | A[4] | ASCII | [Misc Parm] Event Log Chk Disk Space Prod = |
| c_LowFluidWarnStateEnabledAudAlarm | EC | 6692 | A[4] | ASCII | [Beacon] Low Fluid Warning State Enabled Aud Alarm = |
| c_LowFluidWarnOutputBit | EC | 6693 | I4 | INT | [Beacon] Low Fluid Warning State Output Bit = |
| c_LowFluidWarnOutputLevel | EC | 6694 | A[40] | ASCII | [Beacon] Low Fluid Warning State Output Level = |
| c_LowFluidWarnStateEnabledBeacon | EC | 6696 | A[4] | ASCII | [Beacon] Low Fluid Warning State Enabled Beacon = |
| c_PurgeBeforeRun_V2 | EC | 6698 | A[4] | ASCII | [Runtime Preferences] Valve 2 Purge Before Run = |
| c_PurgeAfterRun_V1 | EC | 6699 | A[4] | ASCII | [Runtime Preferences] Valve 1 Purge After Run = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|--------------------------------------|-----------|------|-----------|--------------|---|
| c_PurgeAfterRun_V2 | EC | 6700 | A[4] | ASCII | [Runtime Preferences] Valve 2 Purge After Run = |
| c_CheckForDisabledInstructions | EC | 6701 | A[4] | ASCII | [Runtime Preferences] Check for Disabled Instructions = |
| c_LearnWorkpieceAngleFirst | EC | 6702 | A[4] | ASCII | [Wkpc Align Options] Learn Wkpc Angle |
| c_OverflowProtectionEnabled_S1 | EC | 6703 | A[4] | ASCII | [Scale Manager] Overflow Protection Enabled = |
| c_OverflowProtectionEnabled_S2 | EC | 6704 | A[4] | ASCII | [Scale Manager] Scale 2 Overflow Protection Enabled = |
| c_OverflowMaxCapacityMG_S1 | EC | 6705 | A[30] | FLT | [Scale Manager] Max Capacity (mg) = |
| c_OverflowMaxCapacityMG_S2 | EC | 6706 | A[30] | FLT | [Scale Manager] Scale 2 Max Capacity (mg) = |
| c_OverflowWarningPercentage_S1 | EC | 6707 | A[30] | FLT | [Scale Manager] Warning Percentage = |
| c_OverflowWarningPercentage_S2 | EC | 6708 | A[30] | FLT | [Scale Manager] Scale 2 Warning Percentage = |
| c_OverflowCurrentCupWeightMG_S1 | EC | 6709 | A[30] | FLT | [Scale Manager] Current Cup Weight (mg) = |
| c_OverflowCurrentCupWeightMG_S2 | EC | 6710 | A[30] | FLT | [Scale Manager] Scale 2 Current Cup Weight (mg) = |
| c_OverflowAccumulatedTotalMG_S1 | EC | 6711 | A[30] | FLT | [Scale Manager] Accumulated Total (mg) = |
| c_OverflowAccumulatedTotalMG_S2 | EC | 6712 | A[30] | FLT | [Scale Manager] Scale 2 Accumulated Total (mg) = |
| c_OverflowPreTareMG_S1 | EC | 6713 | A[30] | FLT | [Scale Manager] Pre-Tare Total (mg) = |
| c_OverflowPreTareMG_S2 | EC | 6714 | A[30] | FLT | [Scale Manager] Scale 2 Pre-Tare Total (mg) = |
| c_OverflowLastWeightReadingStable_S1 | EC | 6715 | A[4] | ASCII | [Scale Manager] Last Weight Reading Stable = |
| c_OverflowLastWeightReadingStable_S2 | EC | 6716 | A[4] | ASCII | [Scale Manager] Scale 2 Last Weight Reading Stable = |
| c_ProgramIdleTimeLimit | EC | 6717 | I4 | INT | [Misc Parms] Program idle limit = |
| c_AskBeforeUpdatingPatternLibrary | EC | 6718 | A[4] | ASCII | [Pattern Library] Ask Before Updating Library = |
| c_ReticleCircle1Enable | EC | 6719 | A[4] | ASCII | [Vision] Reticle Circle 1 Enable = |
| c_ReticleCircle1Diameter | EC | 6720 | A[30] | FLT | [Vision] Reticle Circle 1 Diameter = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|------------------------------------|-----------|------|-----------|--------------|---|
| c_ReticleCircle2Enable | EC | 6721 | A[4] | ASCII | [Vision] Reticle Circle 2 Enable = |
| c_ReticleCircle2Diameter | EC | 6722 | A[30] | FLT | [Vision] Reticle Circle 2 Diameter = |
| c_ReticleAdditionalCircles | EC | 6723 | I4 | INT | [Vision] Reticle Additional Circles |
| c_ReticleRectangleEnable | EC | 6724 | A[4] | ASCII | [Vision] Reticle Rectangle Enable = |
| c_ReticleRectangleXSize | EC | 6725 | A[30] | FLT | [Vision] Reticle Rectangle X size = |
| c_ReticleRectangleYSize | EC | 6726 | A[30] | FLT | [Vision] Reticle Rectangle Y size = |
| c_ReticleGraduationsEnable | EC | 6727 | A[4] | ASCII | [Vision] Reticle Graduations Enable = |
| c_ReticleGraduationsSpacing | EC | 6728 | A[30] | FLT | [Vision] Reticle Graduations Spacing = |
| c_ReticleColor | EC | 6729 | I4 | INT | [Vision] Reticle Cognex color (B/W) = |
| c_ApplyCameraRotationCorrection | EC | 6730 | A[4] | ASCII | [Vision] Correct for camera rotation = |
| c_FidDripControlEnabled | EC | 6731 | A[4] | ASCII | [Fid Search Fluid Control - Valve 1] Enabled = |
| c_SuppressLogFile | EC | 6732 | A[4] | ASCII | [Misc Parms] Suppress Log File Creation = |
| c_AutoDeleteLogFiles | EC | 6733 | A[4] | ASCII | [Misc Parms] Auto-delete .log files = |
| c_AutoDeleteTrcFiles | EC | 6734 | A[4] | ASCII | [Misc Parms] Auto-delete .trc files = |
| c_AutoDeleteDbgFiles | EC | 6735 | A[4] | ASCII | [Misc Parms] Auto-delete .dbg files = |
| c_AutoDeleteFilesDaysAfterCreation | EC | 6736 | I4 | INT | [Misc Parms] Auto-delete interval (days) = |
| c_AutoDeleteFreqDays | EC | 6737 | I4 | INT | [Misc Parms] Auto-delete frequency (days) = |
| c_AutoDeleteFilesUserConfirm | EC | 6738 | A[4] | ASCII | [Misc Parms] Auto-delete confirm = |
| c_CheckDiskSpaceInterval | EC | 6739 | I4 | INT | [Misc Parms] Check Disk Space Interval = |
| c_MinDiskSpaceNeeded | EC | 6740 | I4 | INT | [Misc Parms] FmNT Min Disk Space = |
| c_DiskSpaceTooLow | EC | 6741 | I4 | INT | [Misc Parms] Log Files Min Disk Space = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|-------------------------------|-----------|------|-----------|--------------|---|
| c_OutputToFile | EC | 6742 | A[4] | ASCII | [Motion Controller] Output to File = |
| c_ConveyorControlType_C2 | EC | 6743 | A[20] | ASCII | [Conveyor2] Control Type = |
| c_ConveyorMode_C2 | EC | 6744 | I4 | INT | [Conveyor2] Mode = |
| c_StartupFileName_C2 | EC | 6745 | A[60] | ASCII | [Conveyor2] Startup File Name = |
| c_StyleType_C2 | EC | 6746 | A[100] | ASCII | [Conveyor2] Style Type = |
| c_BeltSpeed_C2 | EC | 6747 | A[30] | INT, FLT | [Conveyor2] Belt Speed = VID, VALUE |
| c_BeltAccel_C2 | EC | 6748 | A[30] | INT, FLT | [Conveyor2] Belt Accel = VID, VALUE |
| c_LongMove_C2 | EC | 6749 | A[30] | INT, FLT | [Conveyor2] Long Move = VID, VALUE |
| c_ShortMove_C2 | EC | 6750 | A[30] | INT, FLT | [Conveyor2] Short Move = VID, VALUE |
| c_BackMove_C2 | EC | 6751 | A[30] | INT, FLT | [Conveyor2] Back Move = VID, VALUE |
| c_Retries_C2 | EC | 6752 | A[30] | INT, FLT | [Conveyor2] Retries = VID, VALUE |
| c_TwinConveyorWait_C2 | EC | 6753 | I4 | INT | [Conveyor2] Twin Conveyor Wait = |
| c_ConveyorWidthSpeed | EC | 6754 | A[30] | FLT | [Conveyor Manager] Runtime Width Speed = |
| c_ConveyorWidthAccel | EC | 6755 | A[30] | FLT | [Conveyor Manager] Runtime Width Accel = |
| c_AutoConveyorWidthClearance | EC | 6756 | A[30] | FLT | [Conveyor Manager] Automatic Conveyor Width Clearance = |
| c_AutoConveyorWidthClearance2 | EC | 6757 | A[30] | FLT | [Conveyor Manager] Automatic Conveyor 2 Width Clearance = |

Table D-1 FmConfig.ini File Variables (Continued)

| Variable Name | Data Type | ID | SECS Type | Storage Type | Fmconfig.ini File Description [Group] (configuration item =) |
|----------------------------|-----------|------|-----------|--------------|---|
| c_E116StatesEnabled | EC | 6758 | A[4] | ASCII | [E116 States] E116 States Enabled = |
| c_WorkpieceLane2Origin | EC | 6759 | A[4] | ASCII | [Local Machine Offsets] WorkpieceLane2 Origin = |
| c_WorkpieceLane2OriginName | EC | 6760 | A[30] | ASCII | [Local Machine Offsets] WorkpieceLane2 Origin Name = |
| c_AddWorkpieceLane2 | EC | 6761 | A[4] | ASCII | [Wkpc Align Options] Add Workpiece for Lane 2 = |
| c_LastConfigECID | EC | 6768 | I2 | INT | Last configuration equipment constant |

Appendix E SECS/GEM Remote Commands

E.1 Overview

The SECS/GEM interface on equipment enables the host to control equipment actions such as processing by sending Remote Commands.

E.2 SECS/GEM Remote Commands

SECS/GEM remote commands are listed in Table E-1.

Table E-1 SECS/GEM Remote Commands

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|------------------------------|--|--|---|
| "ABORT" | Abort production run See Appendix F – "ABORT" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "CHECKCPJ" | Check Calibrated Process Jetting for DJ valve See Appendix F – "CHECKCPJ" remote command | Valve 1 Valve 2 Scale 1 Scale 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "DJ OFFSET CALIBRATION" | Start DJ Offset calibration See Appendix F – "DJ OFFSET CALIBRATION" remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "DJ9K VACUUM ASSISTED PRIME" | Start DJ9K Vacuum Assisted Prime See Appendix F – "DJ9K VACUUM ASSISTED PRIME" remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command is not recognized 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "DWV" | Start Dispense Weight Verification See Appendix F – "DWV" remote command | Valve 1 Valve 2 Scale 1 Scale 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Table E-1 SECS/GEM Remote Commands (Continued)

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|-----------------|--|--|--|
| "FLOWRATECALIB" | Start Flow Rate Calibration See Appendix F – "FLOWRATECALIB" remote command | Valve 1 Valve 2 Scale 1 Scale 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "HS XY OFFSETS" | Start Height Sense XY Offsets setup See Appendix F – "HS XY OFFSETS" remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "LMO_WP_ALIGN" | Run LMO Workpiece alignment See Appendix F – Local Machine Offsets Workpiece Align | None | 0x00 Command received successfully and is executing 0x40 Not in REMOTE mode 0x45 LMO Workpiece is not enabled 0x46 LMO Workpiece fiducials were not taught 0x47 Cannot execute LMO while program is running 0x48 Cannot execute LMO in programming window |
| "LOAD BOARD 1" | Load board on conveyor 1 See Appendix F – "LOAD BOARD" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "LOAD BOARD 2" | Load board on conveyor 2 See Appendix F – "LOAD BOARD" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Table E-1 SECS/GEM Remote Commands (Continued)

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|--------------------------|---|---------------------|---|
| "LOCAL" | Change SECS/GEM control state to "Local" mode See Appendix F – "LOCAL" remote command | None | 0x00 Command received successfully and is executing |
| "LOCATE SERVICE STATION" | Locate Service Station See Appendix F – "LOCATE SERVICE STATION" remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "MOVE HOME" | Move dispense head to home location See Appendix F – "MOVE HOME" remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "MOVE TO CENTER" | Move dispense head to center location See Appendix F – "MOVE TO CENTER" remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "MOVE TO FRONT" | Move dispense head to front location See Appendix F – "MOVE TO FRONT" remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Table E-1 SECS/GEM Remote Commands (Continued)

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|---|--|--|---|
| “NEEDLE XY OFFSETS” “NEEDLE XY OFFSETS NO PURGE” | Start Needle XY Offsets setup with or without purge during the process. See Appendix F – “NEEDLE XY OFFSETS” and “NEEDLE XY OFFSETS NO PURGE” remote commands | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| “NEEDLE Z OFFSETS” | Start Needle Z Offset setup See Appendix F – “NEEDLE Z OFFSETS” remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| “PAUSE” | Pause production run See Appendix F – “PAUSE” remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program is paused – cannot execute command |
| “PP-SELECT” | Load Recipe file See Appendix F – “PP-SELECT” remote command | Lot ID Lot Name PP ID PP Name | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Table E-1 SECS/GEM Remote Commands (Continued)

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|---------------------------|--|---------------------|---|
| "PRELIM NEEDLE TO CAMERA" | Start preliminary Needle to Camera Offset setup See Appendix F – "PRELIM NEEDLE TO CAMERA" remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "PRIME" | Prime valve See Appendix F – "PRIME" remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "PURGE" | Purge Valve See Appendix F – "PURGE" remote command | Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "REMOTE" | Change SECS/GEM control state to "Remote" mode See Appendix F – "REMOTE" remote command | None | 0x00 Command received successfully and is executing |
| "RESTART_APPLICATION" | Restart Fluidmove application See Appendix F – "RESTART_APPLICATION" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Table E-1 SECS/GEM Remote Commands (Continued)

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|----------------|--|--|--|
| "RESUME" | Resume production run See Appendix F – "RESUME" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program not paused – cannot execute command |
| "RUN PSS FILE" | Run Prompted Setup Script file See Appendix F – "RUN PSS FILE" remote command | Prompted Setup Script Filename Valve 1 Valve 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command 0x43 PP Select file not found |
| "START" | Start production run See Appendix F – "START" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command 0x46 Production start blocked by RFID validation |
| "STOP" | Stop production run See Appendix F – "STOP" remote command | None | 0x00 Command received successfully and is executing 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program not running – cannot execute command |
| "TEACH SCALE" | Teach scale location See Appendix F – "TEACH SCALE" remote command | Valve 1 Valve 2 Scale 1 Scale 2 | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x03 Command has a bad parameter 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Table E-1 SECS/GEM Remote Commands (Continued)

| Remote Command | Description | Optional Parameters | Return Status Code Description |
|----------------|---|---------------------|---|
| "VACUUM OFF" | Turn purge cup vacuum off See Appendix F – "VACUUM OFF" remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |
| "VACUUM ON" | Turn purge cup vacuum on See Appendix F – "VACUUM ON" remote command | None | 0x00 Command received successfully and is executing 0x01 Command invalid in current configuration 0x02 Not in Production window 0x40 Not in REMOTE mode 0x41 Program running – cannot execute command |

Appendix F Variables Grouped by Fluidmove Activity

F.1 Overview

This appendix lists various Fluidmove activities that have some type of associated SECS/GEM capability. Each activity lists associated SECS/GEM variables, events and remote commands. The SECS/GEM data listed in this appendix is listed in previous appendices, but this appendix can be used to determine what SECS/GEM capabilities exist for a specific Fluidmove activity.

The following abbreviations will be used:

| | |
|------|-----------------------|
| CE | Collection Event |
| CEID | CEID |
| DV | Data Variable |
| EC | Equipment Constant |
| ECID | Equipment Constant ID |
| SV | Status Variable |

This appendix covers the following topics:

| <u>Fluidmove Activity</u> | <u>Page</u> |
|---|-------------|
| F.2 Setup Level Variables | F-4 |
| F.3 Lot Level Variables..... | F-5 |
| F.4 Carrier Level Variables and Equipment Constants..... | F-6 |
| F.5 Configuration Parameter Download Rejection Variables..... | F-9 |
| F.6 Configuration Change Notification | F-10 |
| F.7 Recipe Change Notification | F-12 |
| F.8 Program Instruction Variables..... | F-13 |
| F.9 Local Machine Offsets (LMO) - Workpiece Origin | F-27 |
| F.10 LMO Workpiece Align – Remote Command..... | F-29 |
| F.11 LMO Height Sense..... | F-30 |
| F.12 Dispense Head Linear Fluid Sensor Level Percent | F-31 |
| F.13 Dispense Head Linear Fluid Level State..... | F-31 |
| F.14 Limited Start Number of Runs..... | F-32 |
| F.15 Remote Restart Application – Remote Command..... | F-33 |
| F.16 Calibrated Process Jetting (CPJ) – Remote Command | F-34 |
| F.17 Flow Rate Calibration – Remote Command | F-37 |
| F.18 Dispense Weight Verification (DWV) – Remote Command..... | F-42 |
| F.19 DJ9K Vacuum Assisted Prime – Remote Command..... | F-46 |

| | | |
|------|---|-------|
| F.20 | Run PSS File – Remote Command | F-49 |
| F.21 | Height Sense XY Offsets – Remote Command | F-52 |
| F.22 | Needle XY Offsets – Remote Command | F-55 |
| F.23 | Needle Z Offsets – Remote Command | F-59 |
| F.24 | Locate Service Station – Remote Command | F-62 |
| F.25 | Prime – Remote Command | F-65 |
| F.26 | Purge – Remote Command | F-68 |
| F.27 | Teach Scale – Remote Command | F-71 |
| F.28 | PP-Select – Remote Command | F-75 |
| F.29 | DJ Offset Calibration – Remote Command | F-77 |
| F.30 | Move Home – Remote Command | F-82 |
| F.31 | Move To Center – Remote Command | F-84 |
| F.32 | Move To Front – Remote Command | F-86 |
| F.33 | Load Board – Remote Command | F-88 |
| F.34 | Vacuum On/Off – Remote Command | F-91 |
| F.35 | Preliminary Needle To Camera Offsets – Remote Command | F-95 |
| F.36 | Control Dot Weight – Remote Command | F-98 |
| F.37 | Auto Setup – Remote commands | F-102 |
| F.38 | Abort – Remote Command | F-107 |
| F.39 | Local – Remote Command | F-108 |
| F.40 | Pause – Remote Command | F-109 |
| F.41 | Remote – Remote Command | F-110 |
| F.42 | Resume – Remote Command | F-111 |
| F.43 | Start – Remote Command | F-112 |
| F.44 | Stop – Remote Command | F-113 |
| F.45 | Auto Setup Variables | F-114 |
| F.46 | Controlled Process Heat (CpH) Air Flow Variables | F-115 |
| F.47 | Multiple Flow Rates | F-120 |
| F.48 | Carrier Sequence Number | F-124 |
| F.49 | Lane Number | F-125 |
| F.50 | Carrier Load/Unload Time Stamps | F-126 |
| F.51 | Lookup Camera (LUC) Model Teach/Find | F-127 |
| F.52 | Pressure Controlled CPJ (DWCA) Variables | F-128 |
| F.53 | Setup “Offset” Data | F-133 |
| F.54 | Image Capture | F-134 |
| F.55 | Additional Offset Variables | F-136 |
| F.56 | Prompted Setup, Flowrate and Purge Collection Events | F-137 |
| F.57 | DJ Cycle Count | F-138 |

| | | |
|------|---|-------|
| F.58 | Low Fluid Collection Events..... | F-138 |
| F.59 | Height Sense..... | F-138 |
| F.60 | Electronic Pressure | F-139 |
| F.61 | Scale Number | F-140 |
| F.62 | Program Fiducial ON/OFF Control..... | F-140 |
| F.63 | Scale Overflow | F-146 |
| F.64 | Electronic Pressure LMO | F-150 |
| F.65 | Operator ID | F-152 |
| F.66 | Additional Configuration Parameter Variables..... | F-153 |

F.2 Setup Level Variables

Table F.2-1 Setup Level Variables

| Variable Name | Data Type | ID | SECS Type | Description |
|--------------------------------|-----------|------|-----------|---|
| c_PurgeLocationXYZ_V1 | EC | 6498 | A[50] | Purge XYZ location for Valve 1 |
| c_NeedlePositionoverTactile_V1 | EC | 6328 | A[40] | Tactile Sensor XY location for Valve 1 |
| c_CurSafeZ | EC | 6225 | A[30] | Safe Height Z |
| c_XYNeedleOffset_V1 | EC | 6295 | A[40] | Camera to needle XY offset for Valve 1 |
| c_XYNeedleOffset_V2 | EC | 6543 | A[40] | Camera to needle XY offset for valve 2 |
| c_ZNeedleOffset_V1 | EC | 6294 | A[30] | Needle tip to height sense probe Z offset for Valve 1 |
| c_ScaleLocationXYZ_V1 | EC | 6497 | A[50] | Scale XYZ location for Valve 1 |
| c_ScaleLocationXYZ_V2 | EC | 6499 | A[50] | Scale XYZ Location for valve 2 |
| c_Scale2LocationXYZ_V1 | EC | 6525 | A[50] | Scale 2 XYZ Location for Valve 1 |
| c_Scale2LocationXYZ_V2 | EC | 6542 | A[50] | Scale 2 XYZ Location for valve 2 |

F.3 Lot Level Variables

Table F.3-1 Lot Level Variables

| Variable Name | Data Type | ID | SECS Type | Related CEID | Description |
|----------------------------------|-----------|--------------|-----------|--------------|---|
| FlowRate1 | DV | 400 | F8 | 4012 | Flow rate for Valve 1 |
| ScaleMeasurement1 | DV | 406 | F8 | 4010 | Scale measurement for Valve 1 |
| DWVMEASUREDAVG | DV | 416 | F8 | 4020 | Average measured weight of all dispenses during the dispense weight verification procedure. |
| RefillRate1 | DV | 418 | A[100] | 3001 | DP refill rate for Valve 1 |
| SPHTR1CHAN1-SPHTR1CHAN17 | SV | 1101 to 1117 | F8 | 3003 | Set Points for Heater 1 channels 1 to 17. |
| SPHTR2CHAN1-SPHTR2CHAN17 | SV | 1118 to 1134 | F8 | 3003 | Set Points for Heater 2 channels 1 to 17. |
| SPHTR3CHAN1-SPHTR3CHAN17 | SV | 1135 to 1151 | F8 | 3003 | Set Points for Heater 3 channels 1 to 17. |
| SPHTR4CHAN1-SPHTR4CHAN17 | SV | 1152 to 1168 | F8 | 3003 | Set Points for Heater 4 channels 1 to 17. |
| OFFSETHTR1CHAN1-OFFSETHTR1CHAN17 | SV | 1201 to 1217 | F8 | 3003 | Offsets for Heater 1 channels 1 to 17. |
| OFFSETHTR2CHAN1-OFFSETHTR2CHAN17 | SV | 1218 to 1234 | F8 | 3003 | Offsets for Heater 2 channels 1 to 17. |
| OFFSETHTR3CHAN1-OFFSETHTR3CHAN17 | SV | 1235 to 1251 | F8 | 3003 | Offsets for Heater 3 channels 1 to 17. |
| OFFSETHTR4CHAN1-OFFSETHTR4CHAN17 | SV | 1252 to 1268 | F8 | 3003 | Offsets for Heater 4 channels 1 to 17. |

Table F.3-2 Lot Level Variables – Related Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|--|
| ce_HeaterTempsUpdated | 5014 | 801-851 | Collection event triggered when heater temperatures are updated. |

F.4 Carrier Level Variables and Equipment Constants

All variables in this table are defined as “Data Variables”. There is some redundancy here to allow the SECS/GEM host to collect the data real time as the fiducials are found or by waiting until the board has been processed and collecting all of the data at once at the end of the program.

These variables will be overwritten each time a new board (carrier) is processed. The SECS/GEM host must collect the data immediately as each corresponding collection event occurs or create a report containing the desired variables and attach the report to a collection event signaling processing of the board is complete (such as “DispensingDone1” collection event 2002).

Table F.4-1 Carrier Level Variables

| Variable Name | ID | SECS Type | Related CEID | Description |
|--|-------------|-----------|----------------------|--|
| BoardSequenceNumber | 7800 | U4 | 8800 | Carrier Sequence # (sequential) This number is reset each time “GO” is pressed. For a running board count processed since powerup, see existing SV 106 (BoardCount). |
| WPFidFoundXY_1 | 7801 | A[40] | 8801 | Workpiece Fiducial #1 XY in machine units (actual found) |
| WPFidFoundXY_2 | 7802 | A[40] | 8802 | Workpiece Fiducial #2 XY in machine units (actual found) |
| CurrentFidFoundXY | 7000 | A[40] | 8000 8801 8802 | XY location of currently found fiducial in machine units. As fiducials are found, this variable will be updated and either collection event 8000 (for pattern fiducials), 8001 (for workpiece 1 fiducial) or 8002 (for workpiece fiducial 2) will be triggered. By using this variable, fiducials can be collected at the moment they are found. The XY locations will also be stored in variables 7801 (for workpiece 1) or 7802 (for workpiece 2) or sequentially to variables 7001 to 7300 (for pattern fiducials) if it is more efficient to upload all fiducial locations at once at the end of the program. |
| PATTFidFoundXY_1 – PATTFidFoundXY_300 | 7001 – 7300 | A[40] | 2002 | Sequential XY location (machine units) of found pattern fiducials in order dictated by program (300 max) Collection event 2002 is an existing event that is triggered when dispensing is done. A report can be created containing all or some of the fiducial locations and then tied to CE 2002. |

Table F.4-1 Carrier Level Variables (Continued)

| Variable Name | ID | SECS Type | Related CEID | Description |
|--|---------------|-----------|----------------------|---|
| WPFidFoundScore_1 | 7803 | I2 | 8801 | Workpiece fiducial #1 score. |
| WPFidFoundScore_2 | 7804 | I2 | 8802 | Workpiece fiducial #2 score. |
| CurrentFidFoundScore | 10000 | I2 | 8000 8801 8802 | Fiducial score of currently found fiducial. As fiducials are found, this variable will be updated and either collection event 8000 (for pattern fiducials), 8801 (for workpiece 1 fiducial) or 8802 (for workpiece fiducial 2) will be triggered. By using this variable, fiducial scores can be collected at the moment they are found. The scores will also be stored in variables 7803 (for workpiece fid 1) or 7804 (for workpiece fid 2) or sequentially to variables 10001 to 10000 (for pattern fiducials) if it is more efficient to upload all fiducial scores at once at the end of the program. |
| PATTFidFoundScore_1 – PATTFidFoundScore_300 | 10001 - 10300 | I2 | 2002 | Sequential fiducial scores of found pattern fiducials in order dictated by program (300 max) Collection event 8000 is triggered as each pattern fiducial is found. A report can be linked to event 8000 containing DV 10000 to upload the currently found pattern fiducial score or a report can be linked to event 2002 (dispensing done) to upload all or some of the fiducial scores (DVs 10001-10300) after dispensing completes on the current board. |
| CurrentHSFoundXYZ | 7400 | A[50] | 8400 | XYZ location of current height sense. As locations are recorded, this variable will be updated each time and collection event 8400 will be triggered. Using this method, height sense locations can be collected at the moment they occur. The XYZ locations will also be set sequentially to variables 7401 to 7700 if it is more efficient to upload all height sense locations at once at the end of the program. |
| HSFoundXYZ_1 – HSFoundXYZ_300 | 7401 – 7700 | A[50] | 2002 | Sequential XY location and Z height detected of height senses in order dictated by program (300 max) Collection event 2002 is an existing event that is triggered when dispensing is done. A report can be created containing all or some of the height sense locations and then tied to CE 2002. |

Table F.4-2 Carrier Level Variables – Related Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------|------|------------------------|--|
| ce_CurrentFidFoundXY | 8000 | 7000 10000 | Program pattern fiducial has been found |
| ce_CurrentFidNotFoundXY | 8001 | 7000 10000 | Program pattern fiducial was not found Related XY locations indicate “expected” location. |
| ce_WPFidFoundXY_1 | 8801 | 7000 10000 | Program workpiece fiducial 1 has been found. |
| ce_WPFidFoundXY_2 | 8802 | 7000 10000 | Program workpiece fiducial 2 has been found. |
| ce_CurrentHSFoundXYZ | 8400 | 7400 | Collection event triggered when a program height sense has been performed. |

F.5 Configuration Parameter Download Rejection Variables

If the SECS/GEM host downloads a parameter that is rejected by the equipment, the equipment set variable “ConfigParmRejectedID” to the invalid status variable ID and will trigger a “ce_ConfigParmRejected” collection event.

Reasons for rejection include:

- Invalid format such as (FLT,FLT) expected but (FLT) received.
- Parameter is not defined for this machine such as DP Valve setting downloaded but machine is not using a DP valve.

Table F.5-1 Configuration Parameter Download Rejection Variables

| Variable Name | ID | Storage Type | Class | Related CEID | Description |
|----------------------|------|--------------|-------|--------------|---|
| ConfigParmRejectedID | 5999 | I2 | DV | 3650 | This data variable contains the EC ID of the invalid configuration parameter rejected by the equipment. |

Table F.5-2 Configuration Parameter Download Rejection Variables – Related Collection Events

| Variable Name | CEID | Related Status Variable | Description |
|-----------------------|------|-------------------------|---|
| ce_ConfigParmRejected | 3650 | 5999 | Collection event that is triggered when the host attempts to download an invalid configuration parameter. Status Variable 5999 will contain the EC ID of the rejected configuration parameter. |

F.6 Configuration Change Notification

The SECS/GEM host will be notified when the operator modifies a configuration variable on the equipment. Associated data variables will contain the variable ID of the changed parameter, the new and the old values.

There are two categories of configuration parameters: strings and integers.

When a *string* configuration parameter has been modified, data variable “ConfigParmChanged” will be set to the variable ID of the changed parameter. Data variable “ConfigParmStringNew” will be set to the new parameter, data variable “ConfigParmStringOld” will be set to the old value of the parameter and collection event “ce_ConfigParmChangedString” will be triggered.

When an *integer* configuration parameter has been modified, data variable “ConfigParmChanged” will be set to the variable ID of the changed parameter. Data variable “ConfigParmIntNew” will be set to the new parameter, data variable “ConfigParmIntOld” will be set to the old value of the parameter and collection event “ce_ConfigParmChangedInt” will be triggered.

New Collection Events

Table F.6-1 Configuration Change Notification - New Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------|------|------------------------|---|
| ce_ConfigParmChangedString | 3638 | 450 451 453 | Event triggered when operator changes a “string” type configuration parameter |
| ce_ConfigParmChangedInt | 3639 | 450 452 454 | Event triggered when operator changes an “integer” type configuration parameter |

New Data Variables

These data variables are also used for recipe change notification.

Table F.6-2 Configuration Change Notification - New Data Variables

| Data Variable Name | ID | Storage Type | Related CEID | Description |
|---------------------|-----|--------------|------------------------------|--|
| ParameterChangedVid | 450 | I4 | 3638 3639 3651 3652 | Set to the variable ID of the configuration, fluid or heater file parameter changed by operator. |
| NewParameterString | 451 | A[100] | 3638 3651 | New "string" value of configuration, fluid or heater file parameter changed by operator. |
| OldParameterString | 453 | A[100] | 3638 3651 | Old "string" value of configuration, fluid or heater file parameter before changed by operator. |
| NewParameterInt | 452 | I4 | 3639 3652 | New "integer" value of configuration, fluid or heater file parameter changed by operator. |
| OldParameterInt | 454 | I4 | 3639 3652 | Old "integer" value of configuration, fluid or heater file parameter before changed by operator. |

F.7 Recipe Change Notification

Table F.7-1 Recipe Change Notification – Related Report Variables

| Variable Name | CEID | Related Report Variables | Description |
|-----------------------|------|--------------------------|---|
| GemPPChangeEvent | 3 | 468 41 | Event triggered when a recipe file is saved or deleted. Vid 468 contains the name of the affected recipe. Vid 41 (PPCHANGESTATUS) contains 1 = New recipe file has been created 2 = Existing recipe file has been overwritten 3 = Recipe file has been deleted |
| ce_RecipeLoadComplete | 3667 | 468 | Event triggered upon successful completion of a recipe load. Note: if recipe load is initiated from gem host, and the load is successful, the S2F28 command acknowledge field will contain 0x00. |
| ce_RecipeLoadFailed | 3668 | 468 | Event triggered upon unsuccessful completion of an attempted recipe load. Note: if recipe load is initiated from gem host, and the load fails, the S2F28 command acknowledge field will contain 0x42 (process program format error). |

Table F.7-2 Recipe Change Notification – Related Collection Events

| Data Variable Name | ID | SECS Type | Related CEID | Description |
|--------------------|-----|-----------|-------------------|---|
| RecipeFilename | 468 | A[100] | 3 3667 3668 | Recipe name for related collection event. |

F.8 Program Instruction Variables

Program Modification Collection Events

The following collection events are triggered when a program instruction is modified.

Table F.8-1 Program Modification - Collection Events

| Collection Event Name | CEID | Related Report Variables | Description |
|---------------------------|------|--|---|
| ce_ProgInstructionChange | 3663 | 461 462 463 464 465 466 | Event triggered when a program instruction is modified, added or deleted. |
| ce_ProgPatternCreated | 3664 | 467 461 | Event triggered when a new pattern is created in the program. DV 467 stores the name of the pattern created. |
| ce_ProgPatternDeleted | 3665 | 467 461 | Event triggered when a pattern is deleted from program. DV 467 stores the name of the pattern created. |
| ce_ProgSaved | 3666 | 461 | Event triggered when program is saved. DV 461 will contain saved program name. |
| ce_ProgWorkpieceRealigned | 3669 | 464 465 461 | Event triggered when workpiece is re-aligned. |
| ce_ProgFiducialEdit | 3670 | 462 461 | Event triggered when the fiducial(s) of a pattern are edited. |
| ce_ProgSkipMarkEdit | 3671 | 462 461 | Event triggered when the skip mark of a pattern is modified. |

Table F.8-2 Program Instruction Change Collection Events – Related Data Variables

| Data Variable Name | ID | SECS Type | Related CEID | Description |
|---------------------------|-----|-----------|--------------------------------------|---|
| ProgramName | 461 | A[100] | 3663 3664 3669 3670 3671 | Currently loaded program name |
| PatternName | 462 | A[100] | 3663 3670 3671 | Name of pattern being edited |
| PattInstructionChangeType | 463 | I4 | 3663 | 1 = Line Inserted 2 = Line Deleted 3 = Line Modified |
| PattInstructionNew | 464 | A[200] | 3663 3669 | Modified or new instruction. |
| PattInstructionOld | 465 | A[200] | 3663 3669 | Original instruction before modification or deleted instruction |
| PattInstructionLineNum | 466 | I4 | 3663 | Pattern line number modified |
| PatternNameAddedOrDeleted | 467 | A[100] | 3664 3665 | Name of pattern created (CE 3664) or deleted (CE 3665). |

Program Header Change Collection Events

Table F.8-3 Program Header Change - Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|--------------------------------|------|------------------------|--|
| ce_ProgHeaderParmChangedString | 3672 | 450 451 453 | Event triggered when operator changes a “string” type program header parameter |
| ce_ProgHeaderParmChangedInt | 3673 | 450 452 454 | Event triggered when operator changes an “integer” type program header parameter |

Heater Parameter Change Collection Events

The following collection events are triggered when heater parameters are modified.

Table F.8-4 Heater Parameter Change - Collection Events

| Collection Event Name | CEID | Related Report Variables | Description |
|-----------------------------|------|--------------------------|---|
| ce_HeaterParmChangedString | 3653 | 450 451 453 | Event triggered when operator changes a “string” heater file parameter. |
| ce_HeaterParmChangedInt | 3654 | 450 452 454 | Event triggered when operator changes an “integer” heater file parameter. |
| ce_HeaterFileManualDownload | 3655 | 458 460 | Event triggered when a heater file is manually downloaded from the heater terminal window. DV 458 will contain the new heater filename. DV 460 will contain the heater filename being replaced. |
| ce_HeaterFileManualUpload | 3656 | 458 | Event triggered when a heater file is manually uploaded from the heater terminal window. DV 458 will contain the heater filename the parameters are uploaded to. |

Table F.8-4 Heater Parameter Change - Collection Events (Continued)

| Collection Event Name | CEID | Related Report Variables | Description |
|-----------------------|------|--------------------------|--|
| ce_HeaterFileSave | 3657 | 458 460 | Event triggered when a heater file is manually saved in the heater terminal window. DV 458 will contain the new heater filename. DV 460 will contain the heater filename being replaced. |
| ce_HeaterFileLMOSave | 3658 | 458 | Event triggered when heater local machine offsets are saved. DV 458 will contain the heater filename the offsets are linked to. |
| ce_HeaterLMODownload | 3659 | 458 | Event triggered when heater local machine offsets are downloaded. DV 458 will contain the heater filename the offsets are linked to. |
| ce_HeaterLMORemoved | 3660 | 458 | Event triggered when heater local machine offsets are removed (turned off). DV 458 will contain the current heater filename when the offsets were turned off. |
| ce_HeaterFileNotSaved | 3661 | None | Heater file was modified but saved. |
| ce_HeaterLMONotSaved | 3662 | None | Local machine offsets were modified but not saved. |

Table F.8-5 Heater File Parameter Change - Data Variables

| Data Variable Name | ID | SECS Type | Related CEID | Description |
|--------------------|-----|-----------|--|---|
| HeaterFilename | 458 | A[100] | 3653 3654 3655 3656 3657 3658 3659 3660 | Name of the heater file being modified, manually saved, manually uploaded (depending on collection event). |
| HeaterLoopChanged | 459 | I2 | 3653 3654 | Loop number of heater file parameter being modified. |
| HeaterFilenameOld | 460 | A[100] | 3655 3657 | Only valid during collection events 3655 and 3657. Name of heater file replaced when the heater file is saved (ce 3657) or a heater file is manually downloaded (ce 3655). The new (current) heater filename is stored in "Y (VID 458). Note that the old and new heater filename may be the same. |

Heater File Data Variables

The following data variables and their IDs are for reference only and their values should not be directly requested. They are valid only at the time of one of the collection events listed above.

Table F.8-6 Heater File - Data Variables

| Data Variable Name | ID | SECS Type | Storage Type | Heater File Entry |
|---------------------------|-------|-----------|--------------|----------------------------|
| | | | | [GLOBAL] |
| h_VerifyTimeout | 11400 | I4 | INT | Verify Timeout |
| h_Numberofloops | 11401 | I4 | INT | Number of loops |
| | | | | [RUNTIME_LOOP] |
| h_Name | 11410 | A[100] | ASCII | Name |
| h_TurnOffDuringFids | 11411 | I4 | INT | Turn Off During Fids |
| h_OutputDuringFids | 11412 | I4 | INT | Output During Fids |
| h_VerifyBeforeDispense | 11413 | I4 | INT | Verify Before Dispense |
| h_VerifyUpperLimit | 11414 | I4 | INT | Verify Upper Limit |
| h_VerifyLowerLimit | 11415 | I4 | INT | Verify Lower Limit |
| h_SetOffWhenIdle | 11416 | I4 | INT | Set Off When Idle |
| h_WarnBeforeHeaterOff | 11417 | I4 | INT | Warn Before Heater Off |
| h_PreventFlowRateIfHtrOff | 11418 | I4 | INT | *Not stored in heater file |
| h_PreventPurgeIfHtrOff | 11419 | I4 | INT | *Not stored in heater file |
| | | | | [SETTINGS_LOOP] |
| h_OnOff | 11420 | I4 | INT | On/Off |
| h_AutoManual | 11421 | I4 | INT | Auto/Manual |
| h_ManualOutputLevel | 11422 | A[30] | FLT | Manual Output Level |
| h_ScaleUnits | 11423 | I4 | INT | Scale Units |
| h_SetPoint | 11424 | A[30] | FLT | Set Point |
| h_ProportionalBand | 11425 | I4 | INT | Proportional Band |
| h_Integral | 11426 | I4 | INT | Integral |

Table F.8-6 Heater File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Heater File Entry |
|--------------------------|-------|-----------|--------------|---------------------------|
| h_Derivative | 11427 | I4 | INT | Derivative |
| h_OutputFilter | 11428 | I4 | INT | Output Filter |
| h_HotColdSpread | 11429 | A[30] | FLT | Integral Preload |
| h_InputType | 11430 | I4 | INT | Input Type |
| h_InputReadingOffsetBias | 11431 | I4 | INT | Input Reading Offset Bias |
| h_InputFilter | 11432 | I4 | INT | Input Filter |
| h_OutputEnable | 11433 | I4 | INT | Output Enable |
| h_OutputControlType | 11434 | I4 | INT | Output Control Type |
| h_OutputAction | 11435 | I4 | INT | Output Action |
| h_OutputHeatCycleTime | 11436 | I4 | INT | Output Heat Cycle Time |
| h_OutputHeatLimitPC | 11437 | I4 | INT | Output Heat Limit PC |
| h_OutputHeatLimitTime | 11438 | I4 | INT | Output Heat Limit Time |
| h_Deadband | 11439 | A[30] | FLT | Deadband |
| h_Deviation | 11440 | I4 | INT | Deviation |
| h_ProcAlarmDelay | 11441 | I4 | INT | Proc Alarm Delay |
| h_HighProcAlarmOutput | 11442 | I4 | INT | High Proc Alarm Output |
| h_HighProcAlarmSetPoint | 11443 | A[30] | FLT | High Proc Alarm Set Point |
| h_HighProcAlarmMode | 11444 | I4 | INT | High Proc Alarm Mode |
| h_LowProcAlarmOutput | 11445 | I4 | INT | Low Proc Alarm Output |
| h_LowProcAlarmSetPoint | 11446 | A[30] | FLT | Low Proc Alarm Set Point |
| h_LowProcAlarmMode | 11447 | I4 | INT | Low Proc Alarm Mode |
| h_HighDevOutput | 11448 | I4 | INT | High Dev Output |
| h_HighDevMode | 11449 | I4 | INT | High Dev Mode |

Table F.8-6 Heater File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Heater File Entry |
|----------------------------|-------|-----------|--------------|----------------------------|
| h_LowDevOutput | 11450 | I4 | INT | Low Dev Output |
| h_LowDevMode | 11451 | I4 | INT | Low Dev Mode |
| h_LocalMachineHeaterOffset | 11452 | I4 | INT | *Not stored in heater file |

Fluid File Variables

A fluid file contains “characteristics”, “dot” and “line” parameters. Each set of dot and line parameters are duplicated 10 times to represent 10 possible dot and line types. Fluid files are also linked to a particular valve (if the equipment contains more than one valve). Note that a single fluid file can be linked to both valves.

Characteristic, dot and line parameters are internally represented by either an ASCII string or INTEGER value. A separate collection event will be triggered for each of these two data types to facilitate creating and linking reports based on the data type. In general, a report should be created for each collection event defining the old and new values, the ID of the variable changed, the fluid filename, the valve number linked to the fluid file and the dot/line type.

The following collection events are triggered when a fluid file parameter is modified.

Table F.8-7 Fluid File Parameter Change – Collection Events

| Collection Event Name | CEID | Related Report Variables | Description |
|---------------------------|------|--|--|
| ce_FluidParmChangedString | 3651 | 450 451 453 455 456 457 | Event triggered when operator changes a “string” fluid file parameter. |
| ce_FluidParmChangedInt | 3652 | 450 452 454 455 456 457 | Event triggered when operator changes an “integer” fluid file parameter. |

Table F.8-8 Fluid File Parameter Change – Data Variables

| Data Variable Name | ID | SECS Type | Related CEID | Description |
|-----------------------------|-----|-----------|--------------|---|
| FluidFilenameChanged | 455 | A[100] | 3651 3652 | Name of the fluid file being modified. Note that the parameters will not be persistent unless the fluid file is saved. |
| FluidTypeChanged | 456 | I2 | 3651 3652 | Type changed: 0 = Characteristic 1 = Dot/Line Type 1 2 = Dot/Line Type 2 3 = Dot/Line Type 3 4 = Dot/Line Type 4 5 = Dot/Line Type 5 6 = Dot/Line Type 6 7 = Dot/Line Type 7 8 = Dot/Line Type 8 9 = Dot/Line Type 9 10 = Dot/Line Type 10 |
| FluidFileChangedValveNumber | 457 | I2 | 3651 3652 | Valve Number Fluid File is currently mapped to: 1 = Valve 1 2 = Valve 2 |

Fluid File Data Variables

The following data variables and their IDs are for reference only and their values should not be directly requested. They are valid only at the time of their modification and one of the collection events listed above.

Table F.8-9 Fluid File - Data Variables

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|--------------------|-------|-----------|--------------|------------------|
| | | | | [Dot Parameters] |
| fd_OnTime | 11000 | A[30] | FLT | On Time |
| fd_DwellSecs | 11001 | A[30] | FLT | Dwell Secs |
| fd_DispenseGap | 11002 | A[30] | FLT | Dispense Gap |
| fd_Notes | 11003 | A[100] | ASCII | Notes |
| fd_MidmoveCount1 | 11004 | A[30] | FLT | Midmove Count 1 |

Table F.8-9 Fluid File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|---------------------|-------|-----------|--------------|--------------------------|
| fd_MidmoveCount2 | 11005 | A[30] | FLT | Midmove Count 2 |
| fd_DownSpeed | 11006 | A[30] | FLT | Down Speed |
| fd_DownAccel | 11007 | A[30] | FLT | Down Accel |
| fd_SettleSecs | 11008 | A[30] | FLT | Settle Secs |
| fd_OnVectorMode | 11009 | I4 | INT | On Vector Mode |
| fd_OffVectorMode | 11010 | I4 | INT | Off Vector Mode |
| fd_NumShots | 11011 | I4 | INT | Num Shots |
| fd_MultishotZDelta | 11012 | A[30] | FLT | Multishot Z Delta |
| fd_UpSpeed | 11013 | A[30] | FLT | Up Speed |
| fd_UpAccel | 11014 | A[30] | FLT | Up Accel |
| fd_RetractDistance | 11015 | A[30] | FLT | Retract Distance |
| fd_Suckback | 11016 | A[30] | FLT | Suckback |
| fd_PostRetractDwell | 11017 | A[30] | FLT | Post Retract Dwell |
| fd_AssistDelay | 11018 | A[30] | FLT | Assist Delay |
| fd_AssistDuration | 11019 | A[30] | FLT | Assist Duration |
| fd_ValveOnTime | 11020 | A[30] | FLT | Valve On Time |
| fd_DotSpacing | 11021 | A[30] | FLT | Dot Spacing |
| fd_Acceleration | 11022 | A[30] | FLT | Acceleration |
| fd_EncEnable | 11023 | A[4] | ASCII | Enc Enable |
| fd_EncForwardSpd | 11024 | A[30] | FLT | Enc Forward Spd |
| fd_EncReverseSpd | 11025 | A[30] | FLT | Enc Reverse Spd |
| fd_EncAccel | 11026 | A[30] | FLT | Enc Accel |
| fd_EncDecel | 11027 | A[30] | FLT | Enc Decel |
| fd_EncCounts | 11028 | I4 | INT | Enc Counts |
| fd_EncSuckback | 11029 | I4 | INT | Enc Suckback |
| | | | | [Line Parameters] |
| fl_PremoveDelay | 11100 | A[30] | FLT | Pre-move Delay |
| fl_ShutoffDistance | 11101 | A[30] | FLT | Shutoff Distance |
| fl_DispenseGap | 11102 | A[30] | FLT | Dispense Gap |

Table F.8-9 Fluid File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|-----------------------------|-------|-----------|--------------|-------------------------------------|
| fl_Speed | 11103 | A[30] | FLT | Speed |
| fl_Weightcontrollinespeed | 11104 | A[30] | FLT | Weight-control line speed (FMW/sec) |
| fl_DwellTime | 11105 | A[30] | FLT | Dwell Time |
| fl_RetractDistance | 11106 | A[30] | FLT | Retract Distance |
| fl_BacktrackGap | 11107 | A[30] | FLT | Backtrack Gap |
| fl_BacktrackLength | 11108 | A[30] | FLT | Backtrack Length |
| fl_BacktrackSpeed | 11109 | A[30] | FLT | Backtrack Speed |
| fl_Notes | 11110 | A[100] | ASCII | Notes |
| fl_DownSpeed | 11111 | A[30] | FLT | Down Speed |
| fl_DownAccel | 11112 | A[30] | FLT | Down Accel |
| fl_UpSpeed | 11113 | A[30] | FLT | Up Speed |
| fl_UpAccel | 11114 | A[30] | FLT | Up Accel |
| fl_Suckback | 11115 | A[30] | FLT | Suckback |
| fl_VelocityAdjustmentFactor | 11116 | A[30] | FLT | Velocity Adjustment Factor |
| fl_FluidOnResponseTime | 11117 | A[30] | FLT | Fluid On Response Time |
| fl_FluidOffResponseTime | 11118 | A[30] | FLT | Fluid Off Response Time |
| fl_Assist1OnResponseTime | 11119 | A[30] | FLT | Assist 1 On Response Time |
| fl_Assist1OffResponseTime | 11120 | A[30] | FLT | Assist 1 Off Response Time |
| fl_Assist2OnResponseTime | 11121 | A[30] | FLT | Assist 2 On Response Time |
| fl_Assist2OffResponseTime | 11122 | A[30] | FLT | Assist 2 Off Response Time |
| fl_DispenseHeight | 11123 | A[30] | FLT | Dispense Height |
| fl_DispenseWidth | 11124 | A[30] | FLT | Dispense Width |
| | | | | [Characteristics] |
| fc_PurgeEnabled | 11200 | A[4] | ASCII | Purge Enabled |
| fc_PurgeDuration | 11201 | A[30] | FLT | Purge Duration |
| fc_PurgeInterval | 11202 | A[30] | FLT | Purge Interval |
| fc_FlowRateEnabled | 11203 | A[4] | ASCII | Flow Rate Enabled |
| fc_FlowCalibrationInterval | 11204 | A[30] | FLT | Flow Calibration Interval |
| fc_FlowCalibrationDuration | 11205 | A[30] | FLT | Flow Calibration Duration |

Table F.8-9 Fluid File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|-------------------------------------|-------|-----------|--------------|--|
| fc_DJFlowCalibrationMinWeight | 11206 | A[30] | FLT | DJ Flow Calibration Min Weight (mg) |
| fc_PercentofMaxDJWeightControlSpeed | 11207 | A[30] | FLT | Percent of Max DJ Weight-Control Speed |
| fc_SetPurgeOnTimer | 11208 | I4 | INT | Set Purge On Timer |
| fc_SetFlowRateOnTimer | 11209 | I4 | INT | Set FlowRate On Timer |
| fc_PurgeonRunCount | 11210 | I4 | INT | Purge on Run Count |
| fc_FlowRateCalibrationonRunCount | 11211 | I4 | INT | Flow Rate Calibration on Run Count |
| fc_FlowCalibrationDispenses | 11212 | I4 | INT | Flow Calibration Dispenses |
| fc_FlowCalibrationIntervalDelay | 11213 | A[30] | FLT | Flow Calibration Interval Delay |
| fc_MinimumFlowRate | 11214 | A[30] | FLT | Minimum Flow Rate |
| fc_MaximumFlowRate | 11215 | A[30] | FLT | Maximum Flow Rate |
| fc_Fluidname | 11216 | A[100] | ASCII | Fluid name |
| fc_PotLifeEnabled | 11217 | A[4] | ASCII | Pot Life Enabled |
| fc_Potlife | 11218 | A[30] | FLT | Pot life |
| fc_Potlifefluid | 11219 | A[30] | FLT | Pot life fluid |
| fc_ScaleBias | 11220 | A[30] | FLT | Scale Bias (%) |
| fc_ZeroScaleXOffset | 11221 | A[30] | FLT | Zero Scale X Offset |
| fc_ZeroScaleYOffset | 11222 | A[30] | FLT | Zero Scale Y Offset |
| fc_ZeroScaleZOffset | 11223 | A[30] | FLT | Zero Scale Z Offset |
| fc_FlowCalibrationPreMove | 11224 | A[100] | ASCII | Flow Calibration Pre-Move |
| fc_FlowCalibrationPostMove | 11225 | A[100] | ASCII | Flow Calibration Post-Move |
| fc_FilletBias | 11226 | A[30] | | Fillet Bias (%) |
| fc_BoardsafterLowFluidSensed | 11227 | I4 | INT | Boards after Low Fluid Sensed |
| fc_LowFluidBoardsToGo | 11228 | I4 | INT | Low Fluid Boards To Go |
| fc_EnableLowFluidCheck | 11229 | A[4] | ASCII | Enable Low Fluid Check |
| fc_LowFluidCheck | 11230 | I4 | INT | Low Fluid Check |
| fc_DefaultWeightofPrimedFluid | 11231 | A[30] | FLT | Default Weight of Primed Fluid (mg) |
| fc_Initialsyringeweight | 11232 | A[30] | FLT | Initial syringe weight (mg) |
| Fc_Warningsyringeweight | 11233 | A[30] | FLT | Warning syringe weight (mg) |
| fc_Criticalsyringeweight | 11234 | A[30] | FLT | Critical syringe weight (mg) |

Table F.8-9 Fluid File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|---------------------------------------|-------|-----------|--------------|--|
| fc_AllowFutureThawTime | 11235 | A[4] | ASCII | Allow Future Thaw Time |
| fc_DisplaywarningonlowFluidSense | 11236 | A[4] | ASCII | Display warning on low Fluid Sense |
| fc_VacuumShutoffDelayTime | 11237 | A[30] | FLT | Vacuum Shutoff Delay Time (ms) |
| fc_VacuumDelayEnabled | 11238 | A[4] | ASCII | Vacuum Delay Enabled |
| fc_VacuumPreShutoffTime | 11239 | A[30] | FLT | Vacuum Pre-Shutoff Time (ms) |
| fc_VacuumPreShutoffEnabled | 11240 | A[4] | ASCII | Vacuum Pre-Shutoff Enabled |
| fc_MultiFlowRateCalibrationEnable | 11241 | A[4] | ASCII | Multi Flow Rate Calibration Enable |
| fc_MultiFlowRateCalibrationCount | 11242 | I4 | INT | Multi Flow Rate Calibration Count |
| fc_ResetFlowRateTimer | 11243 | A[4] | ASCII | Reset Flow Rate Timer |
| fc_ResetPurgeTimer | 11244 | A[4] | ASCII | Reset Purge Timer |
| fc_ResetDispenseWeightVerifyTimer | 11245 | A[4] | ASCII | Reset Dispense Weight Verify Timer |
| fc_DispenseWeightBlockProduction | 11246 | A[4] | ASCII | Dispense Weight Block Production |
| fc_DispenseWeightTarget | 11247 | A[30] | FLT | Dispense Weight Target |
| fc_DispenseWeightTimeBetweenDispenses | 11248 | A[30] | FLT | Dispense Weight Time Between Dispenses |
| fc_DispenseWeightMaximumLimit | 11249 | A[30] | FLT | Dispense Weight Maximum Limit |
| fc_DispenseWeightMinimumLimit | 11250 | A[30] | FLT | Dispense Weight Minimum Limit |
| fc_DispenseWeightNumberofDispenses | 11251 | I4 | INT | Dispense Weight Number of Dispenses |
| fc_DispenseWeightCheckMaxRange | 11252 | A[4] | ASCII | Dispense Weight Check Max Range |
| fc_DispenseWeightMaxRange | 11253 | A[30] | FLT | Dispense Weight Max Range |
| fc_DispenseWeightPurgeBeforeVerify | 11254 | A[4] | ASCII | Dispense Weight Purge Before Verify |
| fc_FlowRateBlockProduction | 11255 | A[4] | ASCII | Flow Rate Block Production |
| fc_ValveAutoBiasBlockProduction | 11256 | A[4] | ASCII | Valve Auto Bias Block Production |
| fc_ValveAutoBiasTargetWeight | 11257 | A[30] | FLT | Valve Auto Bias Target Weight |
| fc_LastComputedValveAutoBias | 11258 | A[30] | FLT | Last Computed Valve Auto Bias (%) |
| fc_ValveAutoBiasMaximumLimit | 11259 | A[30] | FLT | Valve Auto Bias Maximum Limit |
| fc_ValveAutoBiasMinimumLimit | 11260 | A[30] | FLT | Valve Auto Bias Minimum Limit |
| fc_ValveAutoBiasNumberofDispenses | 11261 | I4 | INT | Valve Auto Bias Number of Dispenses |
| fc_ValveAutoBiasTimeBetweenDispenses | 11262 | A[30] | FLT | Valve Auto Bias Time Between Dispenses |
| fc_SkipFirstShotinMFR | 11263 | A[4] | ASCII | Skip First Shot in MFR |

Table F.8-9 Fluid File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|---|-------|-----------|--------------|--|
| fc_LoadPromptedSetupPSS | 11264 | A[4] | ASCII | Load Prompted Setup PSS |
| fc_LoadChangeSyringePSS | 11265 | A[4] | ASCII | Load Change Syringe PSS |
| fc_LoadLowFluidPSS | 11266 | A[4] | ASCII | Load Low Fluid PSS |
| fc_PromptedSetupPSSFilename | 11267 | A[100] | ASCII | Prompted Setup PSS Filename |
| fc_ChangeSyringePSSFilename | 11268 | A[100] | ASCII | Change Syringe PSS Filename |
| fc_LowFluidPSSFilename | 11269 | A[100] | ASCII | Low Fluid PSS Filename |
| fc_FluxWtBlockProduction | 11270 | A[4] | ASCII | Flux Wt Block Production |
| fc_FluxWtValveOnTime | 11271 | A[30] | FLT | Flux Wt Valve On Time |
| fc_FluxWtTarget | 11272 | A[30] | FLT | Flux Wt Target |
| fc_FluxWtTimeBetweenDispenses | 11273 | A[30] | FLT | Flux Wt Time Between Dispenses |
| fc_FluxWtMaxLimit | 11274 | A[30] | FLT | Flux Wt Max Limit |
| fc_FluxWtMinLimit | 11275 | A[30] | FLT | Flux Wt Min Limit |
| fc_FluxWtNumberOfDispenses | 11276 | I4 | INT | Flux Wt Number of Dispenses |
| fc_FluxWtCheckMaxRange | 11277 | A[4] | ASCII | Flux Wt Check Max Range |
| fc_FluxWtMaxRange | 11278 | A[30] | FLT | Flux Wt Max Range |
| fc_FluxWtCheckLimits | 11279 | A[4] | ASCII | Flux Wt Check Limits |
| fc_FluxWtPurgeBeforeVerify | 11280 | A[4] | ASCII | Flux Wt Purge Before Verify |
| fc_FluxWtPurgeBetweenDispenses | 11281 | A[4] | ASCII | Flux Wt Purge Between Dispenses |
| fc_DJvalveontime | 11282 | A[30] | FLT | DJ valve on time (ms) |
| fc_DJvalveofftime | 11283 | A[30] | FLT | DJ valve off time (ms) |
| fc_Numberofdotsininitialdispense | 11284 | I4 | INT | Number of dots in initial dispense |
| fc_Fluxvalveontime | 11285 | A[30] | FLT | Flux valve on time (ms) |
| fc_RuntimeDispenseWeightVerificationEnabled | 11286 | A[4] | ASCII | Runtime Dispense Weight Verification Enabled |
| fc_DispenseWeightVerificationInterval | 11287 | A[30] | FLT | Dispense Weight Verification Interval (sec) |
| fc_DispenseWeightVerificationonRunCount | 11288 | I4 | INT | Dispense Weight Verification on Run Count |
| fc_DoDispenseWeightVerificationonTimer | 11289 | I4 | INT | Do Dispense Weight Verification on Timer |
| fc_MaxDeviationAbovePreviousFlowrate | 11290 | A[30] | FLT | Max % Deviation Above Previous Flowrate |
| fc_MaxDeviationBelowPreviousFlowrate | 11291 | A[30] | FLT | Max % Deviation Below Previous Flowrate |
| fc_PressureSettingUnits_V1 | 11292 | A[10] | ASCII | Setting units |

Table F.8-9 Fluid File - Data Variables (Continued)

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|-----------------------------------|-------|-----------|--------------|--|
| fc_FluidPressureSetting_V1 | 11293 | A[30] | FLT | Fluid Pressure Setting |
| fc_ValvePressureSetting_V1 | 11294 | A[30] | FLT | Valve Pressure Setting |
| fc_CoolingPressureSetting_V1 | 11295 | A[30] | FLT | Cooling Pressure Setting |
| fc_FluidPressureTol_V1 | 11296 | A[30] | FLT | Fluid Pressure Tolerance |
| fc_ValvePressureTol_V1 | 11297 | A[30] | FLT | Valve Pressure Tolerance |
| fc_CoolingPressureTol_V1 | 11298 | A[30] | FLT | Cooling Pressure Tolerance |
| fc_DotWeightPressureControlled_V1 | 11299 | A[4] | ASCII | "ON" = Dot Weight Pressure Control is enabled "OFF" = Dot Weight Pressure Control is disabled |
| fc_DesiredDotWeight_V1 | 11300 | A[30] | FLT | Desired dot weight when running pressure controlled setup |
| fc_MinFluidPressure_V1 | 11301 | A[30] | FLT | Minimum fluid pressure when running pressure controlled setup |
| fc_MaxFluidPressure_V1 | 11302 | A[30] | FLT | Maximum fluid pressure when running pressure controlled setup |

F.9 Local Machine Offsets (LMO) - Workpiece Origin

Table F.9-1 LMO Workpiece Origin - Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------|------|------------------------|---|
| ce_LmoWpEnabled | 3710 | 6438 | Collection event that is triggered when Local Machine Offsets Workpiece Origin has been enabled. |
| ce_LmoWpDisabled | 3711 | 6438 | Collection event that is triggered when Local Machine Offsets Workpiece Origin has been disabled. |
| ce_LmoWpModified | 3712 | 6438 | Collection event that is triggered when the Local Machine Offsets Workpiece Origin has been modified. |
| ce_LmoWpAlignSuccessful | 3713 | 7705 | Collection event that is triggered after Local Machine Offsets Workpiece Origin realignment has completed and was successfully realigned. |

Table F.9-1 LMO Workpiece Origin - Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|--|
| ce_LmoWpAlignFailed | 3714 | 7705 | Collection event that is triggered after Local Machine Offsets Workpiece Origin realignment has completed and did not succeed. |
| ce_LmoWpFidFound_1 | 3718 | 7706 7708 | Collection event triggered when fiducial 1 of Local Machine Workpiece is found. |
| ce_LmoWpFidFound_2 | 3719 | 7707 7709 | Collection event triggered when fiducial 2 of Local Machine Workpiece is found. |
| ce_LmoWpFidNotFound_1 | 3760 | 7706 7708 | Collection event triggered when fiducial 1 of Local Machine Workpiece is not found. |
| ce_LmoWpFidNotFound_2 | 3761 | 7707 7709 | Collection event triggered when fiducial 2 of Local Machine Workpiece is not found. |

Table F.9-2 LMO Workpiece Origin – Data Variables

| Data Variable Name | ID | SECS Type | Storage Type | Fluid File Entry |
|----------------------|------|-----------|--------------|---|
| LmoWpFrame | 7705 | A[50] | FLT,FLT,FLT | Current X, Y, Theta origin of the Local Machine Workpiece Offset name selected. If LMO workpiece is not enabled or the LMO name selected is not valid, this string will contain "-1, -1, -1". These values are in user units. |
| LmoWpFidFoundXY_1 | 7706 | A[40] | FLT,FLT | Fiducial 1 XY location (in machine units) found during LMO workpiece re-alignment. Valid after collection event 3718 or 3760 occurs. Note that this is the "expected" location for CEID 3760. |
| LmoWpFidFoundXY_2 | 7707 | A[40] | FLT,FLT | Fiducial 2 XY location (in machine units) found during LMO workpiece re-alignment. Valid after collection event 3719 or 3761 occurs. Note that this is the "expected" location for CEID 3761. |
| LmoWpFidFoundScore_1 | 7708 | I2 | INT | Fiducial 1 found score during LMO workpiece re-alignment. Valid after collection event 3718 or 3760 occurs. |
| LmoWpFidFoundScore_2 | 7709 | I2 | INT | Fiducial 2 found score during LMO workpiece re-alignment. Valid after collection event 3719 or 3761 occurs. |

F.10 LMO Workpiece Align – Remote Command

LMO Workpiece Align is a remote command to execute Local Machine Offsets Workpiece Origin realignment.

SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related to LMO_WP_ALIGN.

Table F.10-1 LMO Workpiece Align – Remote Command

| Remote Command | Related CEID | Related Data and Status Variables | Description |
|---|--|--|--|
| Remote Command String = "LMO_WP_ALIGN" | See Local Machine Offsets – Workpiece Origin CE table | See Local Machine Offsets – Workpiece Origin data table | Remote control command to execute Local Machine Offsets Workpiece Origin realignment on the tool. The tool must be in remote mode, have Local Machine Offsets Workpiece Origin enabled, the workpiece alignment points must be taught with fiducials and the tool must not be running a program and must not be in the programming window. |

LMO Workpiece Align HCAK Rejection Codes

Table F.10-2 LMO Workpiece Align – HCAK Rejection Codes

| HCAK | Description |
|------|--|
| 0x40 | Tool is not is not in ON-LINE REMOTE state |
| 0x45 | LMO Workpiece Origin is not enabled |
| 0x46 | LMO Workpiece is not aligned using fiducials |
| 0x47 | Cannot execute while program is running |
| 0x48 | Cannot execute while in programming window |

F.11 LMO Height Sense

Table F.11-1 LMO Height Sense – Equipment Constants

| Variable Name | ID | SECS Type | Storage Type | Description |
|------------------------------|------|-----------|--------------|--|
| c_LmoHeightSenseEnabled | 6506 | A[4] | ASCII | Enables / disables LMO Height Sense. Set variable string to “ON” to enable LMO Height Sense. Set variable string to “OFF” to disable LMO Height Sense. (FmConfig.ini entry: Height Sense =) |
| c_LmoHeightSenseLane1 | 6517 | A[30] | FLT | Height sense value used for Lane 1 when LMO Height Sense is active. NOTE: THIS VALUE IS IN 0.1 MIL UNITS (FmConfig.ini entry: Height Sense Value Lane 1=) |
| c_LmoHeightSenseLane2 | 6518 | A[30] | FLT | Height sense value used for Lane 2 when LMO Height Sense is active. NOTE: THIS VALUE IS IN 0.1 MIL UNITS (FmConfig.ini entry: Height Sense Value Lane 2=) |
| LmoHeightSenseLane1UserUnits | 7703 | A[30] | FLT | Height sense value used for Lane 1 when LMO Height Sense is active. NOTE: THIS VALUE IS IN USER UNITS (inch, mm, ...) |
| LmoHeightSenseLane2UserUnits | 7704 | A[30] | FLT | Height sense value used for Lane 2 when LMO Height Sense is active. NOTE: THIS VALUE IS IN USER UNITS (inch, mm, ...) |

Table F.11-2 LMO Height Sense - Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|---|
| ce_LmoHsEnabled | 3715 | | Collection event that is triggered when Local Machine Offsets Height Sense has been enabled. |
| ce_LmoHsDisabled | 3716 | | Collection event that is triggered when Local Machine Offsets Height Sense has been disabled. |
| ce_LmoHsModified | 3717 | | Collection event that is triggered when the Local Machine Offsets Height Sense has been modified. |

F.12 Dispense Head Linear Fluid Sensor Level Percent

Table F.12-1 Dispense Head Linear Fluid Sensor Level Percent –Status Variables and Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|-----------------------------|------|--------------|-----------|------|---|
| DHLinearFluidSensorPct | 1539 | I4 | SV | --- | Dispense head linear fluid sensor level percent. |
| ce_DHLinearFluidSensorLevel | --- | --- | CEID | 3762 | Collection event is triggered when level is checked by Fluidmove. (Before each board) Collection event 3709 is used for level percent and state variables. |

F.13 Dispense Head Linear Fluid Level State

Table F.13-1 Dispense Head Linear Fluid Sensor Level Percent – Status Variables and Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|-----------------------------|------|--------------|-----------|------|---|
| DHLinearFluidSensorState | 1540 | I4 | SV | --- | Dispense head linear fluid sensor level state of sensors. |
| ce_DHLinearFluidSensorLevel | --- | --- | CEID | 3762 | Collection event is triggered when level is checked by Fluidmove. (Before each board) |

F.14 Limited Start Number of Runs

The Limited Start Number of Runs feature is a method for the Remote Host to set the number of program run cycles to complete.

Table F.14-1 Limited Start Number of Runs – Equipment Constants

| Constant Name | ID | Storage Type | SECS Type | CEID | Description |
|---------------------|-----|--------------|-----------|------|--|
| NumberOfRuns | 634 | A[6] | EC | None | Number of runs (production window.) Host sets the number of runs to complete. Dual Conveyor systems will complete 2 boards for each run. Number of Runs Enabled (635) must be set to TRUE to use this feature. |
| NumberOfRunsEnabled | 635 | Boolean | EC | None | Number of runs enabled (production window.) |

Usage Scenario

The Host will set the **NumberOfRuns** and **NumberOfRunsEnabled** equipment constants prior to starting the machine run. When the program is started, it will run the number of program cycles specified by **NumberOfRuns** and then stop.

F.15 Remote Restart Application – Remote Command

Restart Application is a remote command to restart the Fluidmove application.

SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Locate Service Station.

Table F.15-1 Remote Restart Application - Remote Commands

| Remote Command | Related CEID | Related Data and Status Variables | Description |
|--|--------------|-----------------------------------|--|
| Remote Command String = "RESTART_APPLICATION" | None | None | Remote control command to restart Fluidmove application. This command is valid if Fluidmove program is not running production. |

Usage Scenario

The SECS/GEM host initiates the Restart Application process by sending the remote command to the dispensing tool.

SECS/GEM Scripts for Restart Application Remote Command

```
RESTARTAPP_CMD: S2F41 W
  <L [2]
    <A 'RESTART APPLICATION'>    /* RCMD */
  <L
  >
  > .
```

F.16 Calibrated Process Jetting (CPJ) – Remote Command

Check Calibrated Process Jetting is a process to check dispensed fluid flow rate accuracy and consistency. This is accomplished by taking several sequential dispense measurements and computing the average of the weight data and valve flow rate. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables relating to Check Calibrated Process Jetting.

Table F.16-1 Calibrated Process Jetting (CPJ) - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---|------|--|--|
| Remote Command String = "CHECKCPJ" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | Valve 1 = 6504 Valve 2 = 6505 Status = 420 | Remote control command to start Calibrated Process Jetting Check. (mg/dot flowrate) The actual valve flow rate is not changed. |
| | 3701 | | ce_CPJCheckComplete_V1Pass |
| | 3780 | | ce_CPJCheckComplete_V1Fail |
| | 3702 | | ce_CPJCheckComplete_V2Pass |
| | 3781 | | ce_CPJCheckComplete_V2Fail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.16-2 CPJ Check Remote Command – Related Variables, Equipment Constants and Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|----------------------------|------|--------------|-----------|--------------|---|
| c_DJFlowRateCheck_V1 | 6504 | A[30] | EC | 3701 | Results of Check CPJ process (DJ Valve 1) |
| c_DJFlowRateCheck_V2 | 6505 | A[30] | EC | 3702 | Results of Check CPJ process (DJ valve 2) |
| ce_CPJCheckComplete_V1Pass | 3701 | --- | CE | --- | Collection event triggered when Check CPJ process is completed (DJ Valve 1) |
| ce_CPJCheckComplete_V2Pass | 3702 | --- | CE | --- | Collection event triggered when Check CPJ process is completed (DJ valve 2) |
| ce_CPJCheckComplete_V1Fail | 3780 | --- | CE | --- | Collection event triggered when Check CPJ process fails (DJ Valve 1) |
| ce_CPJCheckComplete_V2Fail | 3781 | --- | CE | --- | Collection event triggered when Check CPJ process fails (DJ valve 2) |
| CPJCheckResultStatus | 420 | U2 | DV | 3701 3702 | Return status of CPJ Check process |

Table F.16-3 Calibrated Process Jetting - Check CPJ Results Status

| Return Value | Description |
|--------------|---------------------|
| 0 | Passed |
| 1 | Failed Setup Error |
| 2 | Failed Out-of-Range |
| 5 | Failed User Aborted |
| 6 | Failed Other |

Usage Scenario

The SECS/GEM host starts the Check CPJ process by sending the remote command **CHECKCPJ**. After the Check CPJ process is finished, a collection event **3701** or **3702** is triggered and the dispensed average valve flow rate value (**6504** or **6505**) is updated on the host. The completion status of the Check CPJ process is saved to SECS Gem variable **420**.

SECS/GEM Scripts for Testing CHECKCPJ Remote Command

```
REMOTE_CPJCHECK_VALVE_1: S2F41 W
<L [2]
  <A 'CHECKCPJ'>      /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>      /* COMMAND PARAMETER NAME */
      <U2 1>           /* COMMAND PARAMETER VALUE */
    >
  >
> .
```


F.17 Flow Rate Calibration – Remote Command

Flow Rate Calibration is a process to measure dispensed fluid weight accuracy and consistency. This is accomplished by taking several sequential dispense measurements and computing the average fluid weight and flow rate data. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Flow Rate Calibration process.

Table F.17-1 Flow Rate Calibration – Remote Command – Collection Events

| Collection Event Name | CEID | Related Data and Status Variables | Description |
|--|------|--|---|
| Remote Command String = “FLOWRATECALIB” Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | Valve 1 = 400 Valve 2 = 403 Status = 640 | Remote control command to start Flow Rate Calibration. When a DJ valve is used, this command will perform the Calibrated Process Jetting routine. (mg/dot flowrate) The valve flow rate is changed to the new calibrated value. |
| | 3730 | | ce_FlowRateCalibComplete_V1Pass |
| | 3731 | | ce_FlowRateCalibComplete_V2Pass |
| | 3784 | | ce_FlowRateCalibComplete_V1Fail |
| | 3785 | | ce_FlowRateCalibComplete_V2Fail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.17-2 Flow Rate Calibration – Remote Command – Related Data Variables and Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|-----------------------------|------|--------------|-----------|--------------|--|
| FlowRate1 | 400 | F8 | DV | 3730 | Flow Rate value (Valve 1) |
| FlowRate2 | 403 | F8 | DV | 3731 | Flow Rate value (valve 2) |
| ce_FlowRateCalibComplete_V1 | 3730 | --- | CE | --- | Collection event triggered when Valve 1 Flow Rate Calibration process is completed |
| ce_FlowRateCalibComplete_V2 | 3731 | --- | CE | --- | Collection event triggered when valve 2 Flow Rate Calibration process is completed |
| FlowRateCalibStatus | 640 | U2 | DV | 3730 3731 | Return status of Flow Rate Calibration process. (Valve 1&2) |

Table F.17-3 Flow Rate Calibration Results Status

| Return Value | Description |
|--------------|---------------------|
| 0 | Passed |
| 1 | Failed Setup Error |
| 2 | Failed Out-of-Range |
| 5 | Failed User Aborted |
| 6 | Failed Other |

Usage Scenario

The SECS/GEM host starts the Flow Rate Calibration process by sending the remote command **FLOWRATECALIB**. After the Flow Rate Calibration process is finished, a collection event **3730** or **3731** is triggered and the calibrated flow rate value (400 or 403) is updated on the host. The completion status of the Flow Rate Calibration process is saved to SECS Gem variable **640**.

SECS/GEM Scripts for Testing Flow Rate Calibration

```
FLOWRATE_DEFINE_REPORTS: S2F33 W
```

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>     /* RPTID */
      <L
        <U2 640>  /* VID FLOW RATE CALIB STATUS */
        <U2 400>  /* VID FLOW RATE AVG VALUE */
      >
    >
  >
  <L [2]
    <U2 103>     /* RPTID */
    <L
      <U2 640>  /* VID FLOW RATE CALIB STATUS */
      <U2 403>  /* VID FLOW RATE 2 AVG VALUE */
    >
  >
>
```

SECS/GEM Scripts for Testing Flow Rate Calibration (Continued)

FLOWRATE_LINK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 3730> /* CEID */
      <L
        <U2 102> /* RPTID */
      >
    >
  <L [2]
    <U2 3731> /* CEID */
    <L
      <U2 103> /* RPTID */
    >
  >
>.
```

FLOWRATE_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3730> /* FLOW RATE CALIB complete */
    <U4 3731> /* FLOW RATE CALIB complete */
  >
>.
```

SECS/GEM Scripts for Testing Flow Rate Calibration (Continued)

REMOTE_FLOW_RATE_CALIB_VALVE_1: S2F41 W

```
<L [2]
  <A 'FLOWRATECALIB'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>        /* COMMAND PARAMETER NAME */
      <U2 1>              /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

REMOTE_FLOW_RATE_CALIB_VALVE_2: S2F41 W

```
<L [2]
  <A 'FLOWRATECALIB'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>        /* COMMAND PARAMETER NAME */
      <U2 2>              /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.18 Dispense Weight Verification (DWV) – Remote Command

Dispense Weight Verification is a process to calibrate dispensed weight accuracy and consistency. This is accomplished by taking several sequential weight controlled dispenses and computing the average of the weight data. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Dispense Weight Verification.

Table F.18-1 Dispense Weight Verification – Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|--|------|-----------------------------------|---|
| Remote Command String = "DWV" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | 416 | Remote control command to start Dispense Weight Verification. |
| | 3721 | | ce_DWVCalibComplete_V1Pass |
| | 3722 | | ce_DWVCalibComplete_V2Pass |
| | 3782 | | ce_DWVCalibComplete_V1Fail |
| | 3783 | | ce_DWVCalibComplete_V2Fail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.18-2 Dispense Weight Verification – Data Variables and Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|-------------------|------|--------------|-----------|--------------|---|
| DWVRESULT | 408 | U2 | DV | 4020 | DWV result status. |
| DWVMEASUREDAVG | 416 | F8 | DV | 4020 | Average measured weight of all dispenses during the dispense weight verification procedure. |
| DWVSTATUS | 639 | U2 | DV | 3721 3722 | Return status of Dispense Weight Verification process. |
| ce_DWVComplete_V1 | 3721 | -- | CE | -- | Collection event is triggered when DWV process is complete. (Valve 1) |
| ce_DWVComplete_V2 | 3722 | -- | CE | -- | Collection event is triggered when DWV process is complete. (valve 2) |

Usage Scenario

The SECS/GEM host can read and change the dispense weight target value **DWVTarget, 410**, before starting the DWV procedure. The host starts the DWV procedure by sending the remote command **DWV**. After the DWV procedure is finished, collection events **4020** and **3721 or 3722** are triggered and DWV measured average variable **416** is updated for the host.

SECS/GEM script for testing DWV

DWV_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 101>      /* RPTID DWV DATA */
      <L
        <U2 639>    /* VID DWVSTATUS */
        <U2 408>    /* VID DWVRESULT Status */
        <U2 416>    /* VID DWVMEASUREDAVG */
      >
    >
  >
> .
```

DWV_LINK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3721>      /* CEID */
      <L
        <U2 101>      /* RPTID */
      >
    >
    <L [2]
      <U2 3722>      /* CEID */
      <L
        <U2 101>      /* RPTID */
      >
    >
  >
> .
```


SECS/GEM script for testing DWV (Continued)

DWV_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3721>          /* DWV start complete */
    <U4 3722>          /* DWV start complete */
  >
> .
```

REMOTE_DWV_VALVE_1: S2F41 W

```
<L [2]
  <A 'DWV'>          /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>      /* COMMAND PARAMETER NAME */
      <U2 1>           /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.19 DJ9K Vacuum Assisted Prime – Remote Command

DJ9K Vacuum Assisted Prime is a script command used during machine setup to prime the DJ9K valve with vacuum on to improve fluid priming. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related DJ9K Vacuum Assisted Prime.

Table F.19-1 DJ9K Vacuum Assisted Prime – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|---|------|------------------------|---|
| Remote Command String = "DJ9K VACUUM ASSISTED PRIME" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | 6247 | Remote control command to start DJ9K prime. |
| | 3746 | | ce_DJ9KVAPrimePass |
| | 3772 | | ce_DJ9KVAPrimeFail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Usage Scenario

The SECS/GEM host starts the priming process by sending the remote command **DJ9K VACUUM ASSISTED PRIME** to the dispensing tool. After the priming process is finished, collection event **3746** is triggered to notify the host.

SECS/GEM Scripts for Testing DJ9K Vacuum Assisted Prime Remote Command

DJ9K VA PRIME_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 102> /* RPTID */
      <L
        >
      >
    >
  >
> .
```

DJ9K VA PRIME_LNK_REPS_TO_EVT: S2F35 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 3746> /* CEID */
      <L
        <U2 102> /* RPTID */
        >
      >
    >
  >
> .
```

DJ9K VA PRIME_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3746> /* CEID */
    >
  >
> .
```

SECS/GEM Scripts for Testing DJ9K Vacuum Assisted Prime Remote Command (Continued)

DJ9K VA PURGE_NO_PARM: S2F41 W

```
<L [2]
  <A 'DJ9K VACUUM ASSISTED PRIME'>    /* RCMD */
  <L
  >
> .
```

DJ9K VA PRIME_VALVE_1: S2F41 W

```
<L [2]
  <A 'DJ9K VACUUM ASSISTED PRIME'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>    /* COMMAND PARAMETER NAME */
      <U2 1>        /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

DJ9K VA PURGE_VALVE_2: S2F41 W

```
<L [2]
  <A 'DJ9K VACUUM ASSISTED PRIME'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>    /* COMMAND PARAMETER NAME */
      <U2 2>        /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.20 Run PSS File – Remote Command

Run PSS File remote command to run a prompted setup script file on dispenser. The requested PSS file must already be loaded onto the dispensing machine in the Fluidmove directory or an error will result. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related to Run PSS File process.

Table F.20-1 Run PSS File – Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|--|------|-----------------------------------|---|
| Remote Command String = "RUN PSS FILE" Remote control command includes the filename and valve number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | --- | Remote command runs a prompted setup script file from the host command. |
| | 4001 | | PromptedSetupStarted |
| | 4002 | | PromptedSetupCompleted |

The remote command includes the PSS filename and valve number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No valve parameter in the command message will default to Valve 1

Run PSS File Variables

Table F.20-2 Run PSS File - Related Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|------------------------|------|--------------|-----------|------|--|
| PromptedSetupStarted | 4001 | --- | CE | --- | Collection event triggered when PSS starts. |
| PromptedSetupCompleted | 4002 | --- | CE | --- | Collection event triggered when PSS is complete. |

Usage Scenario

The SECS/GEM host starts the Run PSS File process by sending the remote command with the filename and valve number parameters. When the Run PSS File process is started, collection event **4001** is triggered and when it is finished, collection event **4002** is triggered to notify the host.

SECS/GEM Scripts to Test Run PSS File Command

```
REMOTE_PSSFILE_DJ_SETUP: S2F41 W
<L [2]
  <A 'RUN PSS FILE'>          /* RCMD */
  <L
    <L [2]
      <A 'PSS FILE'>          /* CPNAME */
      <A '_DJ SETUP.PSS'>    /* CPVAL */
    >
  <L [2]
    <A 'VALVE'>              /* COMMAND PARAMETER NAME */
    <U2 1>                   /* COMMAND PARAMETER VALUE */
  >
>
> .
```

SECS/GEM Scripts to Test Run PSS File Command (Continued)

REMOTE_PSSFILE_TENSION: S2F41 W

```
<L [2]
  <A 'RUN PSS FILE'>          /* RCMD */
  <L
    <L [2]
      <A 'PSS FILE'>          /* CPNAME */
      <A '_AUTO TENSION.PSS'> /* CPVAL */
    >
    <L [2]
      <A 'VALVE'>             /* COMMAND PARAMETER NAME */
      <U2 1>                  /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

REMOTE_PSSFILE_GP_SETUP: S2F41 W

```
<L [2]
  <A 'RUN PSS FILE'>          /* RCMD */
  <L
    <L [2]
      <A 'PSS FILE'>          /* CPNAME */
      <A '_GENERIC PROMPTED SETUP.PSS'> /* CPVAL */
    >
    <L [2]
      <A 'VALVE'>             /* COMMAND PARAMETER NAME */
      <U2 1>                  /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.21 Height Sense XY Offsets – Remote Command

Height Sense XY Offsets is a script command used during machine setup to locate the XY offset of the height sensor probe or laser beam relative to the valve. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Height Sense XY Offsets.

Table F.21-1 Height Sense XY Offsets – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|--|
| Remote Command String = "HS XY OFFSETS" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | 6296 | Remote control command to start Height Sense XY Offsets. |
| | 3735 | | ce_HSXYOffsetsPass |
| | 3763 | | ce_HSXYOffsetsFail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.21-2 Height Sense XY Offsets –Related Equipment Constants

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|--------------------|------|--------------|-----------|------|--|
| c_NdltoHSoffset_V1 | 6296 | A40 | EC | None | Needle to height sense offset for Valve 1. |

Usage Scenario

The SECS/GEM host starts the height sensor offset setup process by sending the remote command **HS XY OFFSETS** to the dispensing tool. After the offsets process is finished, collection event **3735** is triggered to notify the host.

SECS/GEM Scripts for Testing HS XY OFFSETS Remote Command

```
HSXYOFFSETS_DEFINE_REPORTS: S2F33 W
```

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>    /* RPTID */
      <L
        <U2 400> /* VID HS XY OFFSETS */
      >
    >
  >
> .
```

```
HSXYOFF_LINK_REPS_TO_EVENTS: S2F35 W
```

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3735>   /* CEID HEIGHT SENSE XY OFFSETS */
      <L
        <U2 102> /* RPTID */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing HS XY OFFSETS Remote Command (continued)

HSXYOFFSETS_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3735> /* height sense xy offsets complete */
  >
> .
```

HSXYOFFSETS_NO_PARM: S2F41 W

```
<L [2]
  <A 'HS XY OFFSETS'> /* RCMD */
  <L
  >
> .
```

HSXYOFFSETS_VALVE_1: S2F41 W

```
<L [2]
  <A 'HS XY OFFSETS'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 1> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

HSXYOFFSETS_VALVE_2: S2F41 W

```
<L [2]
  <A 'HS XY OFFSETS'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 2> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.22 Needle XY Offsets – Remote Command

Needle XY Offsets is a script command used during machine setup to locate the XY offset of the Needle/Jet relative to the camera. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Needle XY Offsets.

Table F.22-1 Needle XY Offsets – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|---|
| Remote Command String = “NEEDLE XY OFFSETS” or “NEEDLE XY OFFSETS NO PURGE” Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | 6295 | Remote control command to start Height Sense XY Offsets with or without valve purge during the process. |
| | 3736 | | ce_NeedleXYOffsetsPass |
| | 3765 | | ce_NeedleXYOffsetsFail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.22-2 Needle XY Offsets Variables

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|---------------------|------|--------------|-----------|------|----------------------------|
| c_XYNeedleOffset_V1 | 6295 | A40 | EC | 3736 | Needle offset for Valve 1. |
| c_XYNeedleOffset_V2 | 6543 | A40 | EC | 3736 | Needle Offset for valve 2. |

Usage Scenario

The SECS/GEM host starts the needle offset setup process by sending the remote command **NEEDLE XY OFFSETS** to the dispensing tool. After the offsets process is finished, collection event **3736** is triggered to notify the host.

SECS/GEM Scripts for Testing NEEDLE XY OFFSETS Remote Command

NEEDLEXYOFF_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>      /* RPTID */
      <L
        <U2 6295>   /* VID HS XY OFFSETS VALVE 1 */
        <U2 6543>   /* VID HS XY OFFSETS VALVE 2 */
      >
    >
  >
>.
```

NEEDLEXYOFF_LINK_REPS_TO_EVT: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3736>     /* CEID HEIGHT SENSE XY OFFSETS */
      <L
        <U2 102>    /* RPTID */
      >
    >
  >
>.
```

SECS/GEM Scripts for Testing NEEDLE XY OFFSETS Remote Command (Continued)

NEEDLEXYOFF_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3736>          /* needle xy offsets complete */
  >
> .
```

NEEDLEXYOFF_NO_PARM: S2F41 W

```
<L [2]
  <A 'NEEDLE XY OFFSETS'>  /* RCMD */
  <L
  >
> .
```

NEEDLEXYOFF_VALVE_1: S2F41 W

```
<L [2]
  <A 'NEEDLE XY OFFSETS'>  /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>          /* COMMAND PARAMETER NAME */
      <U2 1>               /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

SECS/GEM Scripts for Testing NEEDLE XY OFFSETS Remote Command (Continued)

NEEDLEXYOFF_VALVE_2: S2F41 W

```
<L [2]
  <A 'NEEDLE XY OFFSETS'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>             /* COMMAND PARAMETER NAME */
      <U2 2>                  /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.23 Needle Z Offsets – Remote Command

Needle Z Offsets is a script command used during machine setup calculate the Z offset of the Needle/Jet relative to the height sensor origin. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Needle Z Offsets.

Table F.23-1 Needle Z Offsets – Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---|------|-----------------------------------|--|
| Remote Command String = “NEEDLE Z OFFSETS” Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | 6294 | Remote control command to start Needle Z Offsets |
| | 3738 | | ce_NeedleZOffsetsPass |
| | 3786 | | ce_NeedleZOffsetsFail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Needle Z Offsets

Table F.23-2 Needle Z Offsets – Equipment Constants

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|--------------------|------|--------------|-----------|------|------------------------------|
| c_ZNeedleOffset_V1 | 6294 | A40 | EC | 3738 | Needle Z offset for Valve 1. |

Usage Scenario

The SECS/GEM host starts the needle offset setup process by sending the remote command **NEEDLE Z OFFSETS** to the dispensing tool. After the offsets process is finished, collection event **3738** is triggered to notify the host.

SECS/GEM Scripts for Testing NEEDLE Z OFFSETS Remote Command

NEEDLEZOFF_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>      /* RPTID */
      <L
        <U2 6294>    /* VID HS XY OFFSETS VALVE 1 */
      >
    >
  >
>.
```

NEEDLEZOFF_LINK_REPS_TO_EVT: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3738>    /* CEID HEIGHT SENSE Z OFFSETS */
      <L
        <U2 102>    /* RPTID */
      >
    >
  >
>.
```


SECS/GEM Scripts for Testing NEEDLE Z OFFSETS Remote Command (continued)

NEEDLEZOFF_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3738>          /* needle z offsets complete */
  >
> .
```

NEEDLEZOFF_NO_PARM: S2F41 W

```
<L [2]
  <A 'NEEDLE Z OFFSETS'> /* RCMD */
  <L
  >
> .
```

NEEDLEZOFF_VALVE_1: S2F41 W

```
<L [2]
  <A 'NEEDLE Z OFFSETS'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 1> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.24 Locate Service Station – Remote Command

The Locate Service Station process will locate each fiducial and perform a height sense on the purge cup. Once this is complete, the tactile center, the substrate corners, and the purge location are defined.

SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Locate Service Station.

Table F.24-1 Locate Service Station – Remote Command

| Collection Event Name | CEID | Related Data and Status Variables | Description |
|--|------|-----------------------------------|---|
| Remote Command String = "LOCATE SERVICE STATION" Remote control command may include the valve name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1. | | | Remote control command to start Locate Service Station process. |
| | 3742 | | ce_LocateServiceStationPass |
| | 3768 | | ce_LocateServiceStationFail |

Table F.24-2 Locate Service Station - Equipment Constants and Collection Events

| Variable Name | ID | Storage Type | SECS Type | Related CEID | Description |
|-------------------------|------|--------------|-----------|--------------|---|
| c_ServiceStationFidXY_1 | 6526 | A40 | EC | 3742 | Service Station Fid 1 location. |
| c_ServiceStationFidXY_2 | 6527 | A40 | EC | 3742 | Service Station Fid 2 location. |
| ce_LocateServiceStation | 3742 | --- | --- | --- | Collection event triggered when Locate Service Station is complete. |

Usage Scenario

The SECS/GEM host starts the Locate Service Station process by sending the remote command to the dispensing tool. After the process is finished, collection event **3742** is triggered to notify the host.

SECS/GEM Scripts for Locate Service Station Remote Command

LOCSERVSTAT_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>      /* RPTID */
      <L
        <U2 6526 >  /* VID */
        <U2 6527 >  /* VID */
      >
    >
  >
> .
```

LOCSERVSTAT_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3742>     /* CEID */
      <L
        <U2 102>    /* RPTID */
      >
    >
  >
> .
```

SECS/GEM Scripts for Locate Service Station Remote Command (continued)

LOCSEVSTAT_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3742>          /* CEID */
  >
> .
```

LOCSEVSTAT_CMD: S2F41 W

```
<L [2]
  <A 'LOCATE SERVICE STATION'> /* RCMD */
  <L
  >
> .
```

F.25 Prime – Remote Command

Prime is a script command used during machine setup to valves. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Prime remote command.

Table F.25-1 Prime – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|--|
| Remote Command String = "PRIME" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | | Remote control command to start Prime process. |
| | 3741 | | ce_PrimePass |
| | 3767 | | ce_PrimeFail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.25-2 Prime Variables

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|---------------|----|--------------|-----------|------|--------------------------------------|
| ce_Prime | -- | -- | -- | 3741 | Collection event for priming valves. |

Usage Scenario

The SECS/GEM host starts the purge process by sending the remote command **PRIME** to the dispensing tool. After the priming process is finished, collection event **3741** is triggered to notify the host.

SECS/GEM Scripts for Testing Prime Remote Command

PRIME_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>     /* RPTID */
      <L
        <U2 400>   /* VID */
      >
    >
  >
> .
```

PRIME_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3741>    /* CEID */
      <L
        <U2 102>   /* RPTID */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing Prime Remote Command (continued)

PRIME_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3741> /* CEID */
  >
> .
```

PRIME_NO_PARM: S2F41 W

```
<L [2]
  <A 'PRIME'> /* RCMD */
  <L
  >
> .
```

PRIME_VALVE_1: S2F41 W

```
<L [2]
  <A 'PRIME'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 1> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

PRIME_VALVE_2: S2F41 W

```
<L [2]
  <A 'PRIME'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 2> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.26 Purge – Remote Command

Purge is a script command used during machine setup to valves. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Prime remote command.

Table F.26-1 Purge – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|--|
| Remote Command String = "PURGE" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | | Remote control command to start Purge process. |
| | 3740 | | ce_PurgePass |
| | 3766 | | ce_PurgeFail |

The remote command can include the valve and scale name and number parameters:

(SECS/GEM S2F41 Format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1, Scale 1.

Table F.26-2 Purge – Collection Events

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|---------------|----|--------------|-----------|------|---|
| ce_PurgePass | -- | -- | -- | 3740 | Collection event when purge completes successfully |
| ce_PurgeFail | -- | -- | -- | 3766 | Collection event when purge does not complete successfully. |

Usage Scenario

The SECS/GEM host starts the purge process by sending the remote command **PURGE** to the dispensing tool. After the priming process is finished, collection event **3740** is triggered to notify the host.

SECS/GEM Scripts for Testing Purge Remote Command

PURGE_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>     /* RPTID */
      <L
        <U2 400>   /* VID */
      >
    >
  >
> .
```

PURGE_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3740>    /* CEID */
      <L
        <U2 102>   /* RPTID */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing Purge Remote Command (continued)

PURGE_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3740> /* CEID */
  >
> .
```

PURGE_NO_PARM: S2F41 W

```
<L [2]
  <A 'PURGE'> /* RCMD */
  <L
  >
> .
```

PURGE_VALVE_1: S2F41 W

```
<L [2]
  <A 'PURGE'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 1> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

PURGE_VALVE_2: S2F41 W

```
<L [2]
  <A 'PURGE'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* COMMAND PARAMETER NAME */
      <U2 2> /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.27 Teach Scale – Remote Command

Teach Scale is a script command used during machine setup to locate the XY offset of the Scale relative to the needle/Jet. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Teach Scale.

Table F.27-1 Teach Scale – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|---|------|---|--|
| Remote Command String = "TEACH SCALE" Remote control command may include the valve and scale name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1, Scale 1. | | 6497 6499 6525 Scale 2, Valve 2 variable is not yet defined. | Remote control command to start Teach Scale process. |
| | 3737 | | ce_TeachScalePass |
| | 3764 | | ce_TeachScaleFail |

Table F.27-2 Teach Scale – Equipment Constants

| Variable Name | ID | Storage Type | SECS Type | Related CEID | Description |
|------------------------|------|--------------|-----------|--------------|-----------------------------------|
| c_ScaleLocationXYZ_V1 | 6497 | A50 | EC | 3737 | Scale XYZ location for Valve 1. |
| c_ScaleLocationXYZ_V2 | 6499 | A50 | EC | 3737 | Scale XYZ location for valve 2. |
| c_Scale2LocationXYZ_V1 | 6525 | A50 | EC | 3737 | Scale 2 XYZ location for Valve 1. |
| c_Scale2LocationXYZ_V2 | 6542 | A50 | EC | 3737 | Scale 2 XYZ location for valve 2. |

Usage Scenario

The SECS/GEM host starts the needle offset setup process by sending the remote command **TEACH SCALE** to the dispensing tool. After the Teach Scale process is finished, collection event 3737 is triggered to notify the host.

SECS/GEM Scripts for Testing TEACH SCALE Remote Command

TEACH_SCALE_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>      /* RPTID */
      <L
        <U2 400>    /* VID HS XY OFFSETS */
      >
    >
  >
> .
```

TEACH_SCALE_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3737>    /* CEID HEIGHT SENSE XY OFFSETS */
      <L
        <U2 102>    /* RPTID */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing TEACH SCALE Remote Command

TEACH_SCALE_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3737>          /* Height Sense XY offsets complete */
  >
> .
```

TEACH_SCALE_NO_PARM: S2F41 W

```
<L [2]
  <A 'TEACH SCALE'>    /* RCMD */
  <L
  >
> .
```

TEACH_SCALE_VALVE_1: S2F41 W

```
<L [2]
  <A 'TEACH SCALE'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>      /* COMMAND PARAMETER NAME */
      <U2 1>           /* COMMAND PARAMETER VALUE (Valve 1)*/
    >
    <L [2]
      <A 'SCALE'>      /* COMMAND PARAMETER NAME */
      <U2 1>           /* COMMAND PARAMETER VALUE (Scale 1)*/
    >
  >
> .
```

SECS/GEM Scripts for Testing TEACH SCALE Remote Command

TEACH_SCALE_VALVE_2: S2F41 W

```
<L [2]
  <A 'TEACH SCALE '>      /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>          /* COMMAND PARAMETER NAME */
      <U2 2>               /* COMMAND PARAMETER VALUE (Valve 2) */
    >
    <L [2]
      <A SCALE'>           /* COMMAND PARAMETER NAME */
      <U2 2>               /* COMMAND PARAMETER VALUE (Scale 2)*/
    >
  >
> .
```

F.28 PP-Select – Remote Command

PP-Select is a SECS/GEM standard remote function to select which Process Program (Fluidmove Recipe) to run on the machine. The requested Process Program must already be loaded onto the dispensing machine or an error will result. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related PPSelect process.

Table F.28-1 PP-Select – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|---------------------------|--|
| Remote Command String = “PP-SELECT” The remote command must include: LOTID, LOTNAME, PPID, and PPID NAME parameters. (PP-Select S2F41 format) | | PP-Select status = 638 | Remote control command to initiate PP-Select recipe. |
| | 3720 | | ce_PPSelectCompletePass |
| | 3788 | | ce_PPSelectCompleteFail |

The remote command must include: LOTID, LOTNAME, PPID, and PPID NAME parameters.
(PP-Select S2F41 format)

Table F.28-2 PP-Select – Status Variables and Collection Events

| Variable Name | ID | Storage Type | SECS Type | Related CEID | Description |
|----------------------|------|--------------|-----------|--------------|--|
| PPSelectStatus | 638 | U2 | SV | 3720 | Results of PPSelect process. |
| ce_PPSelectCompleted | 3720 | --- | CE | --- | Collection event triggered when PPSelect process is completed. |

Table F.28-3 PP-Select – Results

| Return Value | Description |
|--------------|-----------------|
| 0 | PPSelect Passed |
| 6 | PPSelect Failed |

Usage Scenario

The SECS/GEM host starts the PPSelect process by sending the remote command **PP-SELECT** with lot and process program parameters. After the PP-Select process is finished, a collection event **3720** is triggered and the PPSelectStatus variable **638** is available to the host.

SECS/GEM script to test PP-SELECT command:

REMOTE_PPSELECT_A: S2F41 W

```
<L [2]
  <A 'PP-SELECT'>          /* RCMD */
  <L
    <L [2]
      <A ' ' >              /* CPNAME */
      <A ' ' >              /* CPVAL */
    >
    <L [2]
      <A 'PPID'>            /* CPNAME */
      <A 'TEST_TIMEX.RCP'> /* CPVAL */
    >
  >
> .
```

REMOTE_PPSELECT_B: S2F41 W

```
<L [2]
  <A 'PP-SELECT'>          /* RCMD */
  <L
    <L [2]
      <A ' ' >              /* CPNAME */
      <A ' ' >              /* CPVAL */
    >
    <L [2]
      <A 'PPID'>            /* CPNAME */
      <A 'FLUX_JET.RCP'>   /* CPVAL */
    >
  >
> .
```


F.29 DJ Offset Calibration – Remote Command

DJ Offset Calibration is a script command used during machine setup to calibrate jet valve start/stop timing to the actual dispensed line. The remote command uses the **DJ Unassisted Offset** script routine which does not require operator interaction.

The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related DJ Offset Calibration.

Table F.29-1 DJ Offset Calibration – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|---|------|------------------------|--|
| Remote Command String = "DJ OFFSET CALIBRATION" Remote control command may include the valve name and number in the command parameters. (SECS/GEM S2F41 format) No parameters will default to Valve 1. | | 6538 | Remote control command to start DJ Offset Calibration. |
| | | 6539 | |
| | | 6540 | |
| | | 6541 | |
| | | 6574 | |
| | | 6575 | |
| | | 6576 | |
| | 3749 | | ce_DJOffsetCalibrationPass |
| | 3773 | | ce_DJOffsetCalibrationFail |

The remote command can include the valve name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters) No parameters in the command message will default to Valve 1.

Table F.29-2 DJ Offset Calibration – Equipment Constants

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|---------------------------|------|--------------|-----------|------|--|
| c_DJOffsetInitialDotXY_V1 | 6538 | A40 | EC | 3749 | DJ Offset initial dot XY location Valve 1. |
| c_DJOffsetCalEndPtXY_V1 | 6579 | A40 | EC | 3749 | DJ Offset XY end pt location for Valve 1. |
| c_DJOffsetHeadSpeed_V1 | 6539 | A40 | EC | 3749 | DJ Offset dispense speed Valve 1. |
| c_DJOffsetDispenseGap_V1 | 6540 | A40 | EC | 3749 | DJ Offset dispense gap Valve 1. |
| c_DJOffset_V1 | 6541 | A40 | EC | 3749 | DJ Offset value for Valve 1. |
| c_DJOffsetInitialDotXY_V2 | 6574 | A40 | EC | 3749 | DJ Offset initial dot XY location valve 2. |
| c_DJOffsetHeadSpeed_V2 | 6575 | A40 | EC | 3749 | DJ Offset dispense speed valve 2 |
| c_DJOffsetDispenseGap_V2 | 6576 | A40 | EC | 3749 | DJ Offset dispense gap valve 2. |
| c_DJOffset_V2 | 6573 | A40 | EC | 3749 | DJ Offset value for valve 2. |
| c_DJOffsetUseDotFinder | 6577 | I4 | EC | --- | DJ Offset calibration Use Dot Finder option. |
| c_DJOffsetRunUnassisted | 6578 | Boolean | EC | --- | DJ Offset calibration Run Unassisted option. |

Usage Scenario

The SECS/GEM host starts the DJ Offset Calibration setup process by sending the remote command DJ OFFSET CALIBRATION to the dispensing tool. After the offset process is finished, collection event 3749 is triggered to notify the host.

The DJ Offset Calibration must be done manually the first time to setup parameters for initial dot location, dispense speed, dispense gap, and dot finder calibration. After the initial setup is completed, the following options must be checked to run this feature without operator interaction:

- Use Dot Finder
- Run calibration at last taught position with no further operator interaction




Figure F.29-1 DJ Line Offset Calibration

SECS/GEM Scripts for Testing DJ OFFSET CALIBRATION Remote Command

DJOFFSETCALIB_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>    /* RPTID */
      <L
        <U2 6541> /* Variable ID Valve 1 */
        <U2 6573> /* Variable ID valve 2 */
      >
    >
  >
> .
```

DJOFFSETCALIB_LNK_REPS_TO_EVT: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3749>   /* CEID */
      <L
        <U2 102> /* RPTID */
      >
    >
  >
> .
```

DJOFFSETCALIB_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3749> /* CEID */
  >
> .
```

SECS/GEM Scripts for Testing DJ OFFSET CALIBRATION Remote Command (continued)

DJOFFSETCALIB_NO_PARM: S2F41 W

```
<L [2]
  <A 'DJ OFFSET CALIBRATION'>    /* RCMD */
  <L
  >
> .
```

DJOFFSETCALIB_VALVE_1: S2F41 W

```
<L [2]
  <A 'DJ OFFSET CALIBRATION'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>    /* COMMAND PARAMETER NAME*/
      <U2 1>        /* COMMAND PARAMETER VALUE*/
    >
  >
> .
```

DJOFFSETCALIB_VALVE_2: S2F41 W

```
<L [2]
  <A 'DJ OFFSET CALIBRATION'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>    /* COMMAND PARAMETER NAME*/
      <U2 2>        /* COMMAND PARAMETER VALUE*/
    >
  >
> .
```

F.30 Move Home – Remote Command

Move Home is a script command used during machine setup to move the dispense head to the home location. The SECS/GEM host can start this process with a remote command sent to the client machine. The following table describes the SECS/GEM remote command and variables related Move Home command.

Table F.30-1 Move Home – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|--|
| Remote Command String = "MOVE HOME" | | --- | Remote control command to start Move Home. |
| | 3743 | | ce_MoveHomeLocationPass |
| | 3769 | | ce_MoveHomeLocationFail |

Usage Scenario

The SECS/GEM host moves the dispense head by sending the remote command **MOVE HOME** to the dispensing tool. After the move is finished, collection event **3743** is triggered to notify the host.

SECS/GEM Scripts for Testing Move Home Remote Command

MOVEHOME_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>     /* RPTID */
      <L
        <U4 27>    /* GEM CLOCK   Test collection event */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing Move Home Remote Command (continued)

MOVEHOME_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 3743> /* CEID */
      <L
        <U2 102> /* RPTID */
      >
    >
  >
>.
```

MOVEHOME_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3743> /* CEID */
  >
>.
```

MOVEHOME: S2F41 W

```
<L [2]
  <A 'MOVE HOME'> /* RCMD */
  <L
  >
>.
```

F.31 Move To Center – Remote Command

Move to Center is a script command used during machine setup to move the dispense head to the center of the machine while servicing the purge and scale. The SECS/GEM host can start this process with a remote command sent to the client machine. The following table describes the SECS/GEM remote command and variables related Move to Center command.

Table F.31-1 Move to Center – Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---|------|-----------------------------------|---|
| Remote Command String = "MOVE TO CENTER" | | --- | Remote control command to start Move To Center. |
| | 3752 | | ce_MoveCenterLocationPass |
| | 3776 | | ce_MoveCenterLocationFail |

Usage Scenario

The SECS/GEM host moves the dispense head by sending the remote command **MOVE TO CENTER** to the dispensing tool. After the move is finished, collection event **3752** is triggered to notify the host.

SECS/GEM Scripts for Testing MOVE TO CENTER Remote Command

MOVECENTER_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 102> /* RPTID */
      <L
        <U4 27> /* GEM CLOCK   Test collection event */
      >
    >
  >
> .
```


SECS/GEM Scripts for Testing MOVE TO CENTER Remote Command (continued)

MOVECENTER_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 3752> /* CEID */
      <L
        <U2 102> /* RPTID */
      >
    >
  >
>.
```

MOVECENTER_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3752> /* CEID */
  >
>.
```

MOVECENTER: S2F41 W

```
<L [2]
  <A 'MOVE TO CENTER'> /* RCMD */
  <L
  >
>.
```

F.32 Move To Front – Remote Command

Move to Front is a script command used during machine setup to move the dispense head to the front of the machine to service the valve. The SECS/GEM host can start this process with a remote command sent to the client machine. The following table describes the SECS/GEM remote command and variables related Move to Front command.

Table F.32-1 Move to Front – Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|--|------|-----------------------------------|--|
| Remote Command String = "MOVE TO FRONT" | | --- | Remote control command to start Move To Front. |
| | 3753 | | ce_MoveFrontLocationPass |
| | 3777 | | ce_MoveFrontLocationFail |

Usage Scenario

The SECS/GEM host moves the dispense head by sending the remote command **MOVE TO FRONT** to the dispensing tool. After the move is finished, collection event **3753** is triggered to notify the host.

SECS/GEM Scripts for Testing MOVE TO FRONT Remote Command

MOVEFRONT_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 102> /* RPTID */
      <L
        <U4 27> /* GEM CLOCK   Test collection event */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing MOVE TO FRONT Remote Command (continued)

MOVEFRONT_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 3753> /* CEID */
      <L
        <U2 102> /* RPTID */
      >
    >
  >
>.
```

MOVEFRONT_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3753> /* CEID */
  >
>.
```

MOVEFRONT: S2F41 W

```
<L [2]
  <A 'MOVE TO FRONT'> /* REMOTE COMMAND */
  <L
  >
>.
```

F.33 Load Board – Remote Command

Load Board is a script command used to load boards onto the conveyor. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Load Board.

Table F.33-1 Load Board – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|---|
| Remote Command String = "LOAD BOARD 1" or "LOAD BOARD 2" | | --- | Remote control command to load board on conveyor 1 or conveyor 2. |
| | 3750 | | ce_LoadBoardConv1Pass |
| | 3751 | | ce_LoadBoardConv2Pass |
| | 3774 | | ce_LoadBoardConv1Fail |
| | 3775 | | ce_LoadBoardConv2Fail |

Usage Scenario

The SECS/GEM host starts the Load Board process by sending the remote command **Load Board 1** or **Load Board 2** to the dispensing tool. After the offsets process is finished, collection event **3750** or **3751** is triggered to notify the host.

SECS/GEM Scripts for Testing Load Board Remote Command

LOADBOARD_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>      /* RPTID */
      <L
        <U2 6107>    /* VID Number of Conveyors TEST ONLY*/
      >
    >
  >
> .
```

LOADBOARD_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          * DATAID */
  <L
    <L [2]
      <U2 3750>    /* CEID */
      <L
        <U2 102>   /* RPTID */
      >
    >
  <L [2]
    <U2 3751>    /* CEID */
    <L
      <U2 102>   /* RPTID */
    >
  >
> .
```

SECS/GEM Scripts for Testing Load Board Remote Command

LOADBOARD_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3750>          /* CEID */
    <U4 3751>          /* CEID */
  >
> .
```

LOADBOARD1: S2F41 W

```
<L [2]
  <A 'LOAD BOARD 1'>  /* REMOTE COMMAND */
  <L
  >
> .
```

LOADBOARD2: S2F41 W

```
<L [2]
  <A 'LOAD BOARD 2'>  /* REMOTE COMMAND */
  <L
  >
> .
```

F.34 Vacuum On/Off – Remote Command

Vacuum On and Vacuum Off are script commands used control purge vacuum. The SECS/GEM host can start this process with a remote command sent to the client machine. The following table describes the SECS/GEM remote command and variables related Vacuum On and Vacuum Off commands.

Table F.34-1 Vacuum On/Off – Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---|------|-----------------------------------|--|
| Remote Command String = "VACUUM ON" or "VACUUM OFF" | | --- | Remote control command to turn purge vacuum on or off. |
| | 3756 | | ce_VacuumOnPass |
| | 3757 | | ce_VacuumOffPass |
| | 3778 | | ce_VacuumOnFail |
| | 3779 | | ce_VacuumOffFail |

Usage Scenario

The SECS/GEM host sends the remote command **VACUUM ON** or **VACUUM OFF** to the dispensing tool. Collection event **3756 or 3757** is triggered to notify the host.

SECS/GEM Scripts for Testing Vacuum On and Vacuum Off Remote Commands

VACUUMON_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>     /* RPTID */
      <L
        <U4 27>    /* GEM CLOCK   Test collection event */
      >
    >
  >
>.
```

VACUUMON_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3756>    /* CEID */
      <L
        <U2 102>   /* RPTID */
      >
    >
  >
>.
```

VACUUMON_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3756>     /* CEID */
  >
>.
```


SECS/GEM Scripts for Testing Vacuum On and Vacuum Off Remote Commands (continued)

VACUUMON: S2F41 W

```
<L [2]
  <A 'VACUUM ON'>    /* RCMD */
  <L
  >
> .
```

```
////////////////////////////////////
//  VACUUM OFF REMOTE COMMAND TEST
////////////////////////////////////
```

VACUUMOFF_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>             /* DATAID */
  <L
    <L [2]
      <U2 102>       /* RPTID */
      <L
        <A 'Vacuum Off Test'> /* VID */
      >
    >
  >
> .
```

VACUUMOFF_LNK_REPS_TO_EVENTS: S2F35 W

```
<L [2]
  <U2 0>             /* DATAID */
  <L
    <L [2]
      <U2 3757>      /* CEID */
      <L
        <U2 102>    /* RPTID */
      >
    >
  >
> .
```

SECS/GEM Scripts for Testing Vacuum On and Vacuum Off Remote Commands (continued)

VACUUMOFF_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3757> /* CEID */
  >
> .
```

VACUUMOFF: S2F41 W

```
<L [2]
  <A 'VACUUM OFF'> /* RCMD */
  <L
  >
> .
```

F.35 Preliminary Needle To Camera Offsets – Remote Command

Preliminary Needle to Camera XY Offsets is a script command used during machine setup to locate the Needle/Jet relative to the camera. The SECS/GEM host can start this process with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and variables related Preliminary Needle to Camera XY Offsets.

Table F.35-1 Preliminary Needle to Camera Offsets – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|---|------|------------------------|---|
| Remote Command String = “ PRELIM NEEDLE TO CAMERA” | | | Remote control command to start Preliminary Needle To Camera Offsets process. |
| | 3745 | | ce_PrelimNeedleToCameraPass |
| | 3771 | | ce_PrelimNeedleToCameraFail |

The remote command can include the valve name and number parameters:

(SECS/GEM S2F41 format, Remote Command with Parameters)

No parameters in the command message will default to Valve 1.

Table F.35-2 Preliminary Needle to Camera Offsets – Equipment Constants

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|--|-------|--------------|-----------|------|--|
| c_PrelimNeedleLocation_V1 | 6362 | A40 | EC | 3745 | Preliminary Needle to Camera Location Valve 1. |
| c_PrelimNeedleLocation_V2 Valve 2 variable is not defined in the current GCP file. | ----- | A40 | EC | 3745 | Preliminary Needle to Camera Location Valve 2. |

Usage Scenario

The SECS/GEM host starts the needle offset setup process by sending the remote command “**PRELIM NEEDLE TO CAMERA**” to the dispensing tool. After the offsets process is finished, collection event **3745** is triggered to notify the host.

SECS/GEM Scripts for Testing Preliminary Needle to Camera Offset Remote Command

PRELIMNDLTOCAM_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>      /* RPTID */
      <L
        <U2 6362>   /* VID PRELIM NDL CAMERA VALVE 1 */
      >
    >
  >
> .
```

PRELIMNDLTOCAM_LINK_REPS_TO_EVT: S2F35 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 3745>     /* CEID HEIGHT SENSE XY OFFSETS */
      <L
        <U2 102>    /* RPTID */
      >
    >
  >
> .
```

Preliminary Needle To Camera Offsets – Remote Command (continued)

PRELIMNDLTOCAM_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3745>          /* Prelim needle camera */
  >
> .
```

PRELIMNDLTOCAM_NO_PARM: S2F41 W

```
<L [2]
  <A 'PRELIM NEEDLE TO CAMERA'>  /* RCMD */
  <L
  >
> .
```

PRELIMNDLTOCAM_VALVE_1: S2F41 W

```
<L [2]
  <A 'PRELIM NEEDLE TO CAMERA'>  /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>          /* COMMAND PARAMETER NAME */
      <U2 1>              /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

PRELIMNDLTOCAM_VALVE_2: S2F41 W

```
<L [2]
  <A 'PRELIM NEEDLE TO CAMERA'>  /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>          /* COMMAND PARAMETER NAME */
      <U2 2>              /* COMMAND PARAMETER VALUE */
    >
  >
> .
```

F.36 Control Dot Weight – Remote Command

Control Dot Weight option controls the jet valve dispense dot weight using the electronic fluid pressure control. The SECS/GEM host can turn this feature on or off with a remote command sent to the client machine. The following tables describe the SECS/GEM remote command and collection events related Control Dot Weight.

Table F.36-1 Control Dot Weight – Remote Command

| Remote Command | CEID | Related Data Variables | Description |
|--|------|------------------------|--|
| Remote Command String = “ CONTROL DOT WEIGHT” Remote control command will include the enable value and the optional valve name and number in the command parameters. (SECS/GEM S2F41 format) No valve parameter defaults to Valve 1. | | | Remote command to enable/disable Control Dot Weight fluid parameter. |
| | 3798 | | ce_ControlDotWeightON |
| | 3799 | | ce_ControlDotWeightOFF |

The remote command includes an argument to turn the fluid Control Dot Weight parameter on and off and an optional valve name and number to select the valve. No valve parameter will set Valve 1 by default. (SECS/GEM S2F41 format, Remote Command with Parameters)

Usage Scenario

The SECS/GEM host sends the remote command “CONTROL DOT WEIGHT” with parameters 1 to enable and 0 to disable the feature. Confirmation collection events are generated after the fluid file parameter is set.

Table F.36-2 Control Dot Weight – Collection Events

| CEID | Description |
|------|------------------------|
| 3798 | ce_ControlDotWeightON |
| 3799 | ce_ControlDotWeightOFF |

SECS/GEM Scripts for Testing Control Dot Weight

```
////////////////////////////////////
// REMOTE COMMAND CONTROL DOT WEIGHT
////////////////////////////////////
CONTROL_DOT_WEIGHT_ON: S2F41 W
  <L [2]
    <A 'CONTROL DOT WEIGHT'>    /* RCMD */
    <L
      <L [2]
        <A 'ENABLED'>          /* NAME */
        <BOOLEAN 0X1>          /* VALUE */
      >
      <L [2]
        <A 'VALVE'>             /* COMMAND PARAMETER NAME */
        <U2 1>                  /* COMMAND PARAMETER VALUE */
      >
    >
  > .
CONTROL_DOT_WEIGHT_OFF: S2F41 W
  <L [2]
    <A 'CONTROL DOT WEIGHT'>    /* RCMD */
    <L
      <L [2]
        <A 'ENABLED'>          /* NAME */
        <BOOLEAN 0X0>          /* VALUE */
      >
      <L [2]
        <A 'VALVE'>             /* COMMAND PARAMETER NAME */
        <U2 1>                  /* COMMAND PARAMETER VALUE */
      >
    >
  > .
```

SECS/GEM Scripts for Testing Control Dot Weight (continued)

CNT_DOT_WT_ON_NVP: S2F41 W

```
<L [2]
  <A 'CONTROL DOT WEIGHT'>    /* RCMD */
  <L
    <L [2]
      <A 'ENABLED'>          /* NAME */
      <BOOLEAN 0X1>          /* VALUE */
    >
  >
> .
```

CNT_DOT_WT_OFF_NVP: S2F41 W

```
<L [2]
  <A 'CONTROL DOT WEIGHT'>    /* RCMD */
  <L
    <L [2]
      <A 'ENABLED'>          /* NAME */
      <BOOLEAN 0X0>          /* VALUE */
    >
  >
> .
```

CONTROL_DOT_WT_DEFINE_REPORTS: S2F33 W

```
<L [2]
  <U2 0>          /* DATAID */
  <L
    <L [2]
      <U2 102>     /* RPTID */
      <L
        <U4 39>    /* SECS GEM TIME */
      >
    >
  >
> .
```


SECS/GEM Scripts for Testing Control Dot Weight (continued)

CONTROL_DOT_WT_LNK_REPS_TO_EVT: S2F35 W

```
<L [2]
  <U2 0>      /* DATAID */
  <L
    <L [2]
      <U2 3798> /* CEID */
      <L
        <U2 102> /* RPTID */
      >
    >
  <L [2]
    <U2 3799> /* CEID */
    <L
      <U2 102> /* RPTID */
    >
  >
>.
```

CONTROL_DOT_WT_ENABLE_CE_: S2F37 W

```
<L
  <BOOLEAN 0x1>
  <L
    <U4 3798> /* CEID */
    <U4 3799> /* CEID */
  >
>.
```

F.37 Auto Setup – Remote commands

Locate Service Station

Script Instruction

LOCATE SERVICE STATION

Host Command

REMOTE_LOCATESERVICESTATION: S2F41 W

```
<L [2]
  <A 'LOCATE SERVICE STATON'>
  <L
  >
> .
```

Collection event 3742 is issued when task is complete.

Needle Z Offsets

Script Instruction

Needle Z Offsets

Host Command

REMOTE_NDL_Z_OFFSET: S2F41 W

```
<L [2]
  <A 'NEEDLE Z OFFSETS'>
  <L
  >
>
```

Collection event 3738 is issued when task is complete.

Teach Scale

Script Instruction

Teach Scale

Host Command

TEACH_SCALE: S2F41 W

```
<L [2]
  <A 'TEACH SCALE '>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>        /* OPTIONAL COMMAND PARAMETER NAME */
      <U2 1>              /* 1 = Valve 1, 2 = Valve 2 */
    >
    <L [2]
      <A SCALE'>         /* OPTIONAL COMMAND PARAMETER NAME */
      <U2 1>              /* 1 = Scale 1, 2 = Scale 2 */
    >
  >
> .
```

Collection event 3737 is issued when task is complete.

If optional command parameters are not used, scale and valve will default to 1.

Setup Required Before Running

Scale Locations must be taught using “FASVO” (Fiducial Assisted Scripted Valve Offsets).

Needle XY Offsets

Script Instruction

Needle XY Offsets

Host Command

NEEDLEXYOFF: S2F41 W

```
<L [2]
  <A 'NEEDLE XY OFFSETS'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>             /* OPTIONAL COMMAND PARAMETER NAME */
      <U2 1>                  /* 1 = Valve 1, 2 = Valve 2 */
    >
  >
> .
```

If optional command parameter is not used, valve will default to 1.

Collection event 3736 is issued when task is complete.

Setup Required Before Running

This procedure requires prior setup to automatically find the dots dispensed. This is accomplished during “Service Station” setup.

DJ Offset Calibration

Script Instruction

DJ Offset Calibration

Host Command

DJOFFSETCALIB_VALVE_1: S2F41 W

```
<L [2]
  <A 'DJ OFFSET CALIBRATION'>    /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'>    /* OPTIONAL COMMAND PARAMETER NAME*/
      <U2 1>          /* 1 = Valve 1, 2 = Valve 2 */
    >
  >
> .
```

Collection event 3749 is issued when task is complete.

If optional command parameter is not used, valve will default to 1.

Setup Required Before Running

The DJ Offset Calibration must be performed manually the first time to setup parameters for initial dot location, dispense speed, dispense gap, and dot finder calibration.

Note: dispense location, speed, and gap can be configured by the SECS/GEM host.

Flowrate (dot weight)

Script Instruction

Flowrate

Host Command

REMOTE_FLOW_RATE_CALIB: S2F41 W

```
<L [2]
  <A 'FLOWRATECALIB'> /* REMOTE COMMAND */
  <L
    <L [2]
      <A 'VALVE'> /* OPTIONAL COMMAND PARAMETER NAME */
      <U2 1> /* 1 = Valve 1, 2 = Valve 2 */
    >
  >
> .
```

If optional command parameter is not used, valve will default to 1.

Collection event 3730 (for Valve 1) or 3731 (for valve 2) is issued when task is complete.

DV 640 contains completion status (0 = PASS).

F.38 Abort – Remote Command

Abort is a remote command used to abort the production run of the Fluidmove application.

SECS/GEM host can start this process with a remote command sent to the client machine. The following table describes the SECS/GEM remote command and variables related to Abort command.

Table F.38-1 Abort - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---------------------------------|------|-----------------------------------|--|
| Remote Command String = "ABORT" | None | None | Remote control command to abort production run of the Fluidmove application. This command is valid if the Fluidmove program is running production. |

SECS/GEM Script for ABORT Application Remote Command

ABORTAPP_CMD: S2F41 W

```
<L [2]
  <A 'ABORT'>    /* RCMD */
  <L
  >
  > .
```

F.39 Local – Remote Command

Local is a remote command to change SECS/GEM control state to “Local” mode.

SECS/GEM host sends this remote command to the client machine. The following table describes the SECS/GEM remote command and variables related to Local command.

Table F.39-1 Local - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---------------------------------|------|-----------------------------------|---|
| Remote Command String = “LOCAL” | None | None | Remote control command to change SECS/GEM control state to “Local” mode. This command is valid anytime SECS/GEM is enabled. |

SECS/GEM Script for LOCAL Remote Command

LOCAL_CMD: S2F41 W

<L [2]

<A 'LOCAL'> /* RCMD */

<L

>

> .

F.40 Pause – Remote Command

Pause is a remote command to pause production mode.

SECS/GEM host sends this remote command to the client machine. The following table describes the SECS/GEM remote command and variables related to Pause command.

Table F.40-1 Pause - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---------------------------------|------|-----------------------------------|---|
| Remote Command String = "PAUSE" | None | None | Remote control command to pause a Fluidmove program. This command is valid if in the tool is in remote mode and the program is running. |

SECS/GEM Script for PAUSE Remote Command

PAUSE_CMD: S2F41 W

<L [2]

<A 'PAUSE'> /* RCMD */

<L

>

> .

F.41 Remote – Remote Command

Remote is a remote command to change SECS/GEM control state to “Remote” mode.

SECS/GEM host sends this remote command to the client machine. The following table describes the SECS/GEM remote command and variables related to Remote command.

Table F.41-1 Remote - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|----------------------------------|------|-----------------------------------|--|
| Remote Command String = “REMOTE” | None | None | Remote control command to change SECS/GEM control state to “Remote” mode. This command is valid anytime SECS/GEM is enabled. |

SECS/GEM Script for REMOTE Remote Command:

```
REMOTE_CMD: S2F41 W
  <L [2]
    <A 'REMOTE'>    /* RCMD */
  <L
  >
  > .
```

F.42 Resume – Remote Command

Resume is a remote command to resume the production run after a pause command.

SECS/GEM host sends this remote command to the client machine. The following table describes the SECS/GEM remote command and variables related to Resume command.

Table F.42-1 Resume - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|----------------------------------|------|-----------------------------------|---|
| Remote Command String = "RESUME" | None | None | Remote control command to resume production running after a pause command. This command is valid if in remote mode and the program is paused. |

SECS/GEM Script for RESUME Remote Command

RESUME_CMD: S2F41 W

<L [2]

<A 'RESUME'> /* RCMD */

<L

>

> .

F.43 Start – Remote Command

Start is a remote command to start a program in production mode.

SECS/GEM host sends this remote command to the client machine. The following table describes the SECS/GEM remote command and variables related to Start command.

Table F.43-1 Start - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|---------------------------------|------|-----------------------------------|---|
| Remote Command String = "START" | None | None | Remote control command to start a program in production mode. This command is valid if remote mode is active, the programming window is active, the program is not running, and production is not blocked by RFID validation. |

SECS/GEM Script for START Remote Command

START_CMD: S2F41 W

<L [2]

<A 'START'> /* RCMD */

<L

>

> .

F.44 Stop – Remote Command

Stop is a remote command to stop program execution.

SECS/GEM host sends this remote command to the client machine. The following table describes the SECS/GEM remote command and variables related to Stop command.

Table F.44-1 Stop - Remote Command

| Remote Command | CEID | Related Data and Status Variables | Description |
|--------------------------------|------|-----------------------------------|--|
| Remote Command String = "STOP" | None | None | Remote control command to stop program execution. This command is valid when remote mode is active, Production window is active, and a program is running. |

SECS/GEM Script for STOP Remote Command

```
STOP_CMD: S2F41 W
  <L [2]
    <A 'STOP'>    /* RCMD */
  <L
  >
  > .
```

F.45 Auto Setup Variables

The following SECS/GEM variables pertain to “auto setup” of the Asymtek tool.

Table F.45-1 Auto Setup - Remote Command

| Variable Name | ID | SECS Type | Storage Type | Class | Related CEIDS | Description |
|-------------------------|------|-----------|--------------|-------|---------------|---|
| HSAtTactileZ | 524 | FLT | FLT | DV | 3732 | Captured Z value when height sensor trips on tactile surface during needle to height sensor offsets. NOTE: This value is now in user units. |
| NdIAAtTactileZ_V1 | 525 | FLT | FLT | DV | 3733 | Captured Z value when Valve 1 needle (nozzle) touches tactile during needle to height sensor offsets. NOTE: This value is now in user units. |
| HSAtScaleLidZ | 526 | FLT | FLT | DV | 3734 | Captured Z value when height sensor detects scale lid. “ScaleNumber” vid 522 denotes which scale. NOTE: This value is now in user units. |
| c_ServiceStationFidXY_1 | 6526 | A[40] | FLT,FLT | EC | 3638 3742 | XY location of service station fiducial 1 (left pin). |
| c_ServiceStationFidXY_2 | 6527 | A[40] | FLT,FLT | EC | 3638 3742 | XY location of service station fiducial 2 (right pin). |

Table F.45-2 Auto Setup – Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|---|
| ce_HSAtTactileZ | 3732 | 524 | Collection event when height sensor Z value is captured during needle to height sensor offsets. Note: this CE can occur multiple times during a single offset session if multiple reps are configured. |
| ce_NdIAAtTactileZ_V1 | 3733 | 525 | Collection event when Valve 1 needle (nozzle) Z value is captured during needle to height sensor offsets. Note: this CE can occur multiple times during a single offset session if multiple reps are configured. |
| ce_HSAtScaleLidZ | 3734 | 526 | Collection event when height sensor Z value is captured on scale lid during “teach scale location”. “ScaleNumber” vid denotes which scale. |

F.46 Controlled Process Heat (CpH) Air Flow Variables

The following status variables reflect the current air flow for the specified lane and station.

“-1” indicates air flow is not available. Units are specified by variable c_AirflowUnits (see below).

NOTE: These status variables are valid only if CpH is enabled (see ECID 6523 - c_CpH_Enabled).

Table F.46-1 CPH Air Flow - Status Variables

| Status Variable Name | ID | SECS Type | Storage Type | Description |
|--------------------------|------|-----------|--------------|---|
| AF_L1S1 | 1269 | F8 | FLT | Current air flow for Lane 1 Station 1. |
| AF_L1S2 | 1270 | F8 | FLT | Current air flow for Lane 1 Station 2. |
| AF_L1S3 | 1271 | F8 | FLT | Current air flow for Lane 1 Station 3. |
| AF_L2S1 | 1272 | F8 | FLT | Current air flow for Lane 2 Station 1. |
| AF_L2S2 | 1273 | F8 | FLT | Current air flow for Lane 2 Station 2. |
| AF_L2S3 | 1274 | F8 | FLT | Current air flow for Lane 2 Station 3. |
| AF_L1S1_Limits_Enabled | 1275 | A[4] | ASCII | Air flow limits enabled for Lane 1 station 1. Value will be “ON” or “OFF”. |
| AF_L1S1_UpperLimitOffset | 1276 | F8 | FLT | Upper limit air flow offset for Lane 1 station 1. |
| AF_L1S1_LowerLimitOffset | 1277 | F8 | FLT | Lower limit air flow offset for Lane 1 station 1. |
| AF_L1S2_Limits_Enabled | 1278 | A[4] | ASCII | Air flow limits enabled for Lane 1 station 2. Value will be “ON” or “OFF”. |
| AF_L1S2_UpperLimitOffset | 1279 | F8 | FLT | Upper limit air flow offset for Lane 1 station 2. |
| AF_L1S2_LowerLimitOffset | 1280 | F8 | FLT | Lower limit air flow offset for Lane 1 station 2. |
| AF_L1S3_Limits_Enabled | 1281 | A[4] | ASCII | Air flow limits enabled for Lane 1 station 3. Value will be “ON” or “OFF”. |
| AF_L1S3_UpperLimitOffset | 1282 | F8 | FLT | Upper limit air flow offset for Lane 1 station 3. |
| AF_L1S3_LowerLimitOffset | 1283 | F8 | FLT | Lower limit air flow offset for Lane 1 station 3. |

Table F.46-1 CPH Air Flow - Status Variables (continued)

| Status Variable Name | ID | SECS Type | Storage Type | Description |
|--------------------------|------|-----------|--------------|---|
| AF_L2S1_Limits_Enabled | 1284 | A[4] | ASCII | Air flow limits enabled for Lane 2 station 1. Value will be "ON" or "OFF". |
| AF_L2S1_UpperLimitOffset | 1285 | F8 | FLT | Upper limit air flow offset for Lane 2 station 1. |
| AF_L2S1_LowerLimitOffset | 1286 | F8 | FLT | Lower limit air flow offset for Lane 2 station 1. |
| AF_L2S2_Limits_Enabled | 1287 | A[4] | ASCII | Air flow limits enabled for Lane 2 station 2. Value will be "ON" or "OFF". |
| AF_L2S2_UpperLimitOffset | 1288 | F8 | FLT | Upper limit air flow offset for Lane 2 station 2. |
| AF_L2S2_LowerLimitOffset | 1289 | F8 | FLT | Lower limit air flow offset for Lane 2 station 2. |
| AF_L2S3_Limits_Enabled | 1290 | A[4] | ASCII | Air flow limits enabled for Lane 2 station 3. Value will be "ON" or "OFF". |
| AF_L2S3_UpperLimitOffset | 1291 | F8 | FLT | Upper limit air flow offset for Lane 2 station 3. |
| AF_L2S3_LowerLimitOffset | 1292 | F8 | FLT | Lower limit air flow offset for Lane 2 station 3. |
| AF_L1S1_SetPoint | 1293 | F8 | FLT | Air flow set point for Lane 1 Station 1. |
| AF_L1S2_SetPoint | 1294 | F8 | FLT | Air flow set point for Lane 1 Station 2. |
| AF_L1S3_SetPoint | 1295 | F8 | FLT | Air flow set point for Lane 1 Station 3. |
| AF_L2S1_SetPoint | 1296 | F8 | FLT | Air flow set point for Lane 2 Station 1. |
| AF_L2S2_SetPoint | 1297 | F8 | FLT | Air flow set point for Lane 2 Station 2. |
| AF_L2S3_SetPoint | 1298 | F8 | FLT | Air flow set point for Lane 2 Station 3. |

Table F.46-2 CPH Air Flow - Related Configuration Variables

| Data Variable Name | ID | SECS Type | Storage Type | FmConfig.ini Entry | Description |
|--------------------|------|-----------|--------------|---------------------------|-----------------------------|
| | | | | [Airflow Manager] | |
| c_AirflowUnits | 6520 | I4 | INT | Units = | 0 = scfm 1 = slpm |
| | | | | [Heater Manager] | |
| c_CpH_Enabled | 6523 | A[4] | ASCII | Controlled Process Heat = | Value will be "ON" or "OFF" |

Table F.46-3 Heater/Air Flow States Status Variables

| Status Variable Name | ID | SECS Type | Storage Type | Description |
|------------------------|------|-----------|--------------|--|
| AF_L1S1_StandbyEnabled | 1300 | A[4] | ASCII | Standby state enabled for Lane 1 Station 1. Value will be "ON" or "OFF" |
| AF_L1S1_StandbyTime | 1301 | I4 | INT | Standby time for Lane 1 Station 1 |
| AF_L1S1_StandbyTemp | 1302 | F8 | FLT | Standby temperature for Lane 1 Station 1 |
| AF_L1S1_StandbyAF | 1303 | F8 | FLT | Standby air flow for Lane 1 Station 1 |
| AF_L1S1_RampEnabled | 1304 | A[4] | ASCII | Ramp state enabled for Lane 1 Station 1. Value will be "ON" or "OFF" |
| AF_L1S1_RampTime | 1305 | I4 | INT | Ramp time for Lane 1 Station 1 |
| AF_L1S1_RampTemp | 1306 | F8 | FLT | Ramp temperature for Lane 1 Station 1 |
| AF_L1S1_RampAF | 1307 | F8 | FLT | Ramp air flow for Lane 1 Station 1 |
| AF_L1S1_NonProdEnabled | 1308 | A[4] | ASCII | Non-Production state enabled for Lane 1 Station 1. Value will be "ON" or "OFF" |
| AF_L1S1_NonProdTemp | 1309 | F8 | FLT | Non-Production temperature for Lane 1 Station 1 |
| AF_L1S1_NonProdAF | 1310 | F8 | FLT | Non-Production air flow for Lane 1 Station 1 |
| AF_L1S2_StandbyEnabled | 1311 | A[4] | ASCII | Standby state enabled for Lane 1 Station 2. Value will be "ON" or "OFF" |
| AF_L1S2_StandbyTime | 1312 | I4 | INT | Standby time for Lane 1 Station 2 |
| AF_L1S2_StandbyTemp | 1313 | F8 | FLT | Standby temperature for Lane 1 Station 2 |
| AF_L1S2_StandbyAF | 1314 | F8 | FLT | Standby air flow for Lane 1 Station 2 |
| AF_L1S2_RampEnabled | 1315 | A[4] | ASCII | Ramp state enabled for Lane 1 Station 2. Value will be "ON" or "OFF" |
| AF_L1S2_RampTime | 1316 | I4 | INT | Ramp time for Lane 1 Station 2 |
| AF_L1S2_RampTemp | 1317 | F8 | FLT | Ramp temperature for Lane 1 Station 2 |
| AF_L1S2_RampAF | 1318 | F8 | FLT | Ramp air flow for Lane 1 Station 2 |
| AF_L1S2_NonProdEnabled | 1319 | A[4] | ASCII | Non-Production state enabled for Lane 1 Station 2. Value will be "ON" or "OFF" |
| AF_L1S2_NonProdTemp | 1320 | F8 | FLT | Non-Production temperature for Lane 1 Station 2 |
| AF_L1S2_NonProdAF | 1321 | F8 | FLT | Non-Production air flow for Lane 1 Station 2 |

Table F.46-3 Heater/Air Flow States Status Variables (continued)

| Status Variable Name | ID | SECS Type | Storage Type | Description |
|------------------------|------|-----------|--------------|--|
| AF_L1S3_StandbyEnabled | 1322 | A[4] | ASCII | Standby state enabled for Lane 1 Station 3. Value will be "ON" or "OFF" |
| AF_L1S3_StandbyTime | 1323 | I4 | INT | Standby time for Lane 1 Station 3 |
| AF_L1S3_StandbyTemp | 1324 | F8 | FLT | Standby temperature for Lane 1 Station 3 |
| AF_L1S3_StandbyAF | 1325 | F8 | FLT | Standby air flow for Lane 1 Station 3 |
| AF_L1S3_RampEnabled | 1326 | A[4] | ASCII | Ramp state enabled for Lane 1 Station 3. Value will be "ON" or "OFF" |
| AF_L1S3_RampTime | 1327 | I4 | INT | Ramp time for Lane 1 Station 3 |
| AF_L1S3_RampTemp | 1328 | F8 | FLT | Ramp temperature for Lane 1 Station 3 |
| AF_L1S3_RampAF | 1329 | F8 | FLT | Ramp air flow for Lane 1 Station 3 |
| AF_L1S3_NonProdEnabled | 1330 | A[4] | ASCII | Non-Production state enabled for Lane 1 Station 3. Value will be "ON" or "OFF" |
| AF_L1S3_NonProdTemp | 1331 | F8 | FLT | Non-Production temperature for Lane 1 Station 3 |
| AF_L1S3_NonProdAF | 1332 | F8 | FLT | Non-Production air flow for Lane 1 Station 3 |
| AF_L2S1_StandbyEnabled | 1333 | A[4] | ASCII | Standby state enabled for Lane 2 Station 1. Value will be "ON" or "OFF" |
| AF_L2S1_StandbyTime | 1334 | I4 | INT | Standby time for Lane 2 Station 1 |
| AF_L2S1_StandbyTemp | 1335 | F8 | FLT | Standby temperature for Lane 2 Station 1 |
| AF_L2S1_StandbyAF | 1336 | F8 | FLT | Standby air flow for Lane 2 Station 1 |
| AF_L2S1_RampEnabled | 1337 | A[4] | ASCII | Ramp state enabled for Lane 2 Station 1. Value will be "ON" or "OFF" |
| AF_L2S1_RampTime | 1338 | I4 | INT | Ramp time for Lane 2 Station 1 |
| AF_L2S1_RampTemp | 1339 | F8 | FLT | Ramp temperature for Lane 2 Station 1 |
| AF_L2S1_RampAF | 1340 | F8 | FLT | Ramp air flow for Lane 2 Station 1 |
| AF_L2S1_NonProdEnabled | 1342 | A[4] | ASCII | Non-Production state enabled for Lane 2 Station 1. Value will be "ON" or "OFF" |
| AF_L2S1_NonProdTemp | 1342 | F8 | FLT | Non-Production temperature for Lane 2 Station 1 |
| AF_L2S1_NonProdAF | 1343 | F8 | FLT | Non-Production air flow for Lane 2 Station 1 |

Table F.46-3 Heater/Air Flow States Status Variables (continued)

| Status Variable Name | ID | SECS Type | Storage Type | Description |
|------------------------|------|-----------|--------------|--|
| AF_L2S2_StandbyEnabled | 1344 | A[4] | ASCII | Standby state enabled for Lane 2 Station 2. Value will be "ON" or "OFF" |
| AF_L2S2_StandbyTime | 1345 | I4 | INT | Standby time for Lane 2 Station 2 |
| AF_L2S2_StandbyTemp | 1346 | F8 | FLT | Standby temperature for Lane 2 Station 2 |
| AF_L2S2_StandbyAF | 1347 | F8 | FLT | Standby air flow for Lane 2 Station 2 |
| AF_L2S2_RampEnabled | 1348 | A[4] | ASCII | Ramp state enabled for Lane 2 Station 2. Value will be "ON" or "OFF" |
| AF_L2S2_RampTime | 1349 | I4 | INT | Ramp time for Lane 2 Station 2 |
| AF_L2S2_RampTemp | 1350 | F8 | FLT | Ramp temperature for Lane 2 Station 2 |
| AF_L2S2_RampAF | 1351 | F8 | FLT | Ramp air flow for Lane 2 Station 2 |
| AF_L2S2_NonProdEnabled | 1352 | A[4] | ASCII | Non-Production state enabled for Lane 2 Station 2. Value will be "ON" or "OFF" |
| AF_L2S2_NonProdTemp | 1353 | F8 | FLT | Non-Production temperature for Lane 2 Station 2 |
| AF_L2S2_NonProdAF | 1354 | F8 | FLT | Non-Production air flow for Lane 2 Station 2 |
| AF_L2S3_StandbyEnabled | 1355 | A[4] | ASCII | Standby state enabled for Lane 2 Station 3. Value will be "ON" or "OFF" |
| AF_L2S3_StandbyTime | 1356 | I4 | INT | Standby time for Lane 2 Station 3 |
| AF_L2S3_StandbyTemp | 1357 | F8 | FLT | Standby temperature for Lane 2 Station 3 |
| AF_L2S3_StandbyAF | 1358 | F8 | FLT | Standby air flow for Lane 2 Station 3 |
| AF_L2S3_RampEnabled | 1359 | A[4] | ASCII | Ramp state enabled for Lane 2 Station 3. Value will be "ON" or "OFF" |
| AF_L2S3_RampTime | 1360 | I4 | INT | Ramp time for Lane 2 Station 3 |
| AF_L2S3_RampTemp | 1361 | F8 | FLT | Ramp temperature for Lane 2 Station 3 |
| AF_L2S3_RampAF | 1362 | F8 | FLT | Ramp air flow for Lane 2 Station 3 |
| AF_L2S3_NonProdEnabled | 1363 | A[4] | ASCII | Non-Production state enabled for Lane 2 Station 3. Value will be "ON" or "OFF" |
| AF_L2S3_NonProdTemp | 1364 | F8 | FLT | Non-Production temperature for Lane 2 Station 3 |
| AF_L2S3_NonProdAF | 1365 | F8 | FLT | Non-Production air flow for Lane 2 Station 3 |

F.47 Multiple Flow Rates

The tool will report a list of intermediate flow rate values when “Multiple Flow Rate Calibration” is selected in the fluid file and a flow rate is run.

Table F.47-1 Multiple Flow Rates - Data Variables

| Variable Name | ID | SECS Type | Storage Type | Class | Related CEIDs | Description |
|-------------------|-----|------------|--------------|-------|---------------|---|
| MultiFlowrates_V1 | 560 | FLT[0..50] | FLT LIST | DV | 4014 | List of “intermediate” flow rates when “Multiple Flow Rate Calibration” is run for Valve 1. |
| MultiFlowrates_V2 | 561 | FLT[0..50] | FLT LIST | DV | 4015 | List of “intermediate” flow rates when “Multiple Flow Rate Calibration” is run for valve 2. |

Table F.47-2 Multiple Flow Rates - Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|--|
| ce_MultiFlowrates_V1 | 4014 | 560 | Collection event triggered when “Multiple Flow Rate Calibration” has been selected in the fluid file and a flow rate is run for Valve 1. |
| ce_MultiFlowrates_V2 | 4015 | 561 | Collection event triggered when “Multiple Flow Rate Calibration” has been selected in the fluid file and a flow rate is run for valve 2. |

Description

Report intermediate flow rate values to the SECS/GEM host when “Multiple Flow Rate Calibration” is active in the fluid file and a flow rate is performed. This example shows four multiple flow rate calibrations selected:

The screenshot displays the 'Fluid Manager' application window. The 'General' tab is selected, showing 'Fluid Name: Generic Fluid'. Below this, there are tabs for 'Purge Parameters', 'Flow Rate Parameters', 'Weight Verification', 'Pot Life/Low Fluid Check', and 'Attach Script Files'. The 'Flow Rate Parameters' tab is active. In this tab, the 'Enable Flow Rate Maintenance' checkbox is unchecked. The 'Flow Rate Calibration every:' section has 'On Timer' set to 1200 secs and 'On Run Count' set to 0. The 'Reset Flow Rate Timer when Run Production Window is exited' checkbox is checked. The 'Enable Multiple Flow Rate Calibration' checkbox is checked and highlighted with a red oval, with the value '4' entered in the adjacent field. Below this, the 'Number of Dispenses to Average' is set to 2. The 'Skip First Shot In Flow Rate Calibration' and 'Purge during Flow Rate Calibration' checkboxes are unchecked. The 'Dispense Duration' is set to 5 secs and the 'Time Delay between Dispenses' is set to 0.25 secs. The 'Block Production Run on Failure' checkbox is unchecked. The 'Dispensed Weight Bias' is set to 0 %. The 'Valid Flowrate Range' is set to 5 to 100 mg/sec.

Figure F.47-1 Fluid Manager – Enable Multiple Flow Rate Calibration

After all flow rate calibrations have been run, the tool will display the results on the screen and report the results to the SECS/GEM host in a floating point list.

The following SECS/GEM message detail was produced by creating a report containing variable 560 (MultiFlowrates_V1) and linked to collection event 4014 (ce_MultiFlowrates_V1).

```

08/01/17 08:24:29 (8) Received Primary Message...
08/01/17 08:24:29 <S6F11 W
08/01/17 08:24:29 <L[3/1]
08/01/17 08:24:29 <U4[1/1] 30>
08/01/17 08:24:29 <U4[1/1] 4014> ce_MultiFlowrates_V1

08/01/17 08:24:29 <L[1/1]
08/01/17 08:24:29 <L[2/1]
08/01/17 08:24:29 <U4[1/1] 438>
08/01/17 08:24:29 <L[1/1]
08/01/17 08:24:29 <F8[4/1] 4.198123e+001 3.316357e+001 2.657014e+001 MultiFlowrates_V1
08/01/17 08:24:29 4.027362e+001>
08/01/17 08:24:29 >
08/01/17 08:24:29 >
08/01/17 08:24:29 >
08/01/17 08:24:29 >
08/01/17 08:24:29 >
08/01/17 08:24:29 >
08/01/17 08:24:29 >

```

This matches the data displayed on the screen:




Figure F.47-2 Multiple Flow Rate Calibration

A separate collection “FlowRate1Updated” (4012) will be triggered when the flow rate dialog is exited with “OK” (canceling the dialog will not save the flow rate and a collection event will not be triggered).

In this example, the multiple flow rate variable (MultiFlowrates_V1 VID 560) and the updated flow rate value (FlowRate1 VID 400) were linked to the flow rate updated collection event (FlowRate1Updated CEID 4012):

```
08/01/17 08:41:57 (8) Received Primary Message...
08/01/17 08:41:57 <S6F11 W
08/01/17 08:41:57 <L[3/1]
08/01/17 08:41:57 <U4[1/1] 34>
08/01/17 08:41:57 <U4[1/1] 4012> FlowRate1Updated
08/01/17 08:41:57 <L[2/1]
08/01/17 08:41:57 <L[2/1]
08/01/17 08:41:57 <U4[1/1] 440>
08/01/17 08:41:57 <L[1/1]
08/01/17 08:41:57 <F8[1/1] 4.027362e+001>
08/01/17 08:41:57 >
08/01/17 08:41:57 >
08/01/17 08:41:57 <L[2/1]
08/01/17 08:41:57 <U4[1/1] 438>
08/01/17 08:41:57 <L[1/1]
08/01/17 08:41:57 <F8[4/1] 4.198123e+001 3.316357e+001 2.657014e+001
08/01/17 08:41:57 4.027362e+001>
08/01/17 08:41:57 >
08/01/17 08:41:57 >
08/01/17 08:41:57 >
08/01/17 08:41:57 >
08/01/17 08:41:57 >
```

The updated flow rate matches the flow rate displayed in the dialog:




Figure F.47-3 Fluidmove Message – Flow Rate Results

Note: Although the above example linked the “multiple flow rate” variable to the “flow rate updated” collection event, this is not recommended. It is better to link the multiple flow rate variables only to the multiple flow rate collection events (4014 / 4015). The “flow rate updated” collection event will be triggered whenever the flow rate is updated, not necessarily after running multiple flow rates. Linking multiple flow rates to this collection event may produce misleading results as old data will be reported with a new value.

F.48 Carrier Sequence Number

Two data variables have been added to track carrier sequence number in each lane of a dual lane conveyor system.

The variables are initially set when a carrier arrives at the dispense station of a given lane indicated by collection events “BoardAtDispenseLoc1” (2001) and “BoardAtDispenseLoc2 (2003)”. They are valid until dispensing is complete on the same carrier indicated by “DispensingDone1” (2002) and “DispensingDone2” (2004).

Table F.48-1 Carrier Sequence Number – Data Variables

| Variable Name | ID | SECS Type | Storage Type | Class | Related CEIDs | Description |
|---------------------|-----|-----------|--------------|-------|----------------------|---|
| CarrierSeqAtDisp_L1 | 571 | I4 | INT | DV | 2001 2002 8404 | Carrier sequence number of carrier on Lane 1. |
| CarrierSeqAtDisp_L2 | 572 | I4 | INT | DV | 2003 2004 8406 | Carrier sequence number of carrier on Lane 1. |

Note: CarrierSeqAtDisp_L1 is valid only when collection events pertaining to Lane 1 are received. CarrierSeqAtDisp_L2 is valid only when collection events pertaining to Lane 2 are received.

F.49 Lane Number

LaneNumber reflects the lane number associated with the data collected during certain collection events. It is not valid for all collection events as the lane number may refer to data currently being collected on a specific lane when a collection event for the opposite lane occurs.

See Related CEIDs in the table below for the valid collection events LaneNumber is valid for.

Table F.49-1 Lane Number – Data Variables

| Variable Name | ID | SECS Type | Storage Type | Class | Related CEIDs | Description |
|---------------|-----|-----------|--------------|-------|--|---|
| LaneNumber | 521 | I4 | INT | DV | 2001 2002 2003 2004 8000 8400 | Lane number specifying what lane report data applies to when certain collection events are triggered. |

Note 1: Workpiece fiducials are not lane dependent and if LANENUMBER is reported during workpiece fiducial location collection events, it will always reflect Lane 1. “Pattern” fiducials are lane dependent and LANENUMBER will reflect the lane in which the pattern fiducial locations are reported.

Note 2: LaneNumber will be updated to lane “2” only when there are “USE CONVEYOR 2:” conveyor block instructions in the FMW program. It is possible for a program to be written for both lanes without the use of these blocks (which is not recommended), in which case “LaneNumber” will never change from lane “1” to lane “2”.

F.50 Carrier Load/Unload Time Stamps

Carrier load / unload data variables are valid only when the “Related CEIDs” occur listed in the table below.

Table F.50-1 Carrier Load/Unload Time Stamps – Data Variables

| Variable Name | ID | SECS Type | Storage Type | Class | Related CEIDs | Description |
|-------------------------|------|-----------|--------------|-------|---------------|--|
| CarrierLoadTime_L1 | 428 | A[0..100] | ASCII | DV | 8403 | Time stamp when carrier on Lane 1 was loaded. |
| CarrierUnloadTime_L1 | 429 | A[0..100] | ASCII | DV | 8403 8404 | Time stamp when carrier on Lane 1 was unloaded. Note: unloading occurs after dispensing is completed (after CEID 2002 -DispensingDone1) |
| ce_CarrierLoadTime_L1 | 8403 | - | - | CEID | - | Collection event when carrier on Lane 1 is loaded. |
| ce_CarrierUnloadTime_L1 | 8404 | - | - | CEID | - | Collection event when carrier on Lane 1 is unloaded. |
| CarrierLoadTime_L2 | 469 | A[0..100] | ASCII | DV | 8405 | Time stamp when carrier on Lane 2 was loaded. |
| CarrierUnloadTime_L2 | 470 | A[0..100] | ASCII | DV | 8405 8406 | Time stamp when carrier on Lane 2 was unloaded. Note: unloading occurs after dispensing is completed (after CEID 2004 –DispensingDone2) |
| ce_CarrierLoadTime_L2 | 8405 | - | - | CEID | - | Collection event when carrier on Lane 2 is loaded. |
| ce_CarrierUnloadTime_L2 | 8406 | - | - | CEID | - | Collection event when carrier on Lane 2 is unloaded. |

F.51 Lookup Camera (LUC) Model Teach/Find

Table F.51-1 Lookup Camera Model Teach/Find – Collected Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|---|
| ce_LucImageFound | 8002 | 7710 7711 520 | Collection event that is triggered after running the script instruction “LUC MODEL FIND” or the program instruction “LUC MODEL FIND” and the model for the LUC is successfully found. |
| ce_LucImageNotFound | 8003 | 7710 7711 520 | Collection event that is triggered after running the script instruction “LUC MODEL FIND” or the program instruction “LUC MODEL FIND” and the model for the LUC is not found. |
| ce_LucImageTaught | 8004 | 520 | Collection event that is triggered when an image is taught using the script instruction “LUC MODEL TEACH”. |

Table F.51-2 Lookup Camera Model Teach/Find – Related Data Variables

| Variable Name | ID | Storage Type | SECS Type | CEID | Description |
|---------------|------|--------------|-----------|----------------------|--|
| LucImageXY | 7710 | A[40] | DV | 8002 8003 | XY location of LUC model if found and expected location if model not found. |
| LucImageScore | 7711 | I2 | DV | 8002 8003 | Score of LUC model if found or not found. |
| ImageFilename | 520 | A[100] | DV | 8002 8003 8004 | Name of image file saved after related collection event is triggered. Name contains entire path and name of image. The name will reflect the current date and time to make each file name unique. |

F.52 Pressure Controlled CPJ (DWCA) Variables

Control Dot Weight – Remote Command

This is the remote command for changing pressure control from ON to OFF or vice versa.

This command will alter the contents of the fluid file currently loaded.

The command will be rejected if not in remote mode or if a program is running.

When changing pressure states, the dot weight computed from the previous state will still be in effect. I.e., the pressure controlled dot weight and the non-pressure controlled dot weight is not stored separately and will not automatically change to match the pressure setting when pressure control is turned on or off. Therefore, when changing states, the appropriate CPJ or DWCA setup routine must be executed:

When changing from the non-pressure controlled state to the pressure controlled state, DWCA “setup” should be run using the remote command “DJ9K DOT WEIGHT PRESSURE SETUP”. When changing from the pressure controlled state to the non-pressure controlled state, CPJ should be run using the remote command “FLOWRATECALIB”.

DJ9K Dot Weight Pressure Setup – Remote Command

Use this command to initiate the dot weight pressure “setup” routine. To run this routine, pressure control must be enabled, a program must be running and the tool must be in remote mode.

Table F.52-1 Dot Weight Pressure Setup – Rejection HCAK

| Rejection HCAK | Reason |
|----------------|---------------------------------|
| 0x01 | Valve is not a Jet |
| 0x02 | Not in valid Fluidmove Window |
| 0x40 | Not in remote mode |
| 0x41 | Programming is running |
| 0x45 | Pressure Control is not enabled |

Dot Weight Pressure Setup Data Variables and Collection Events

Dot Weight Pressure Setup can be run remotely or manually from the Fluid Manager. When run remotely, setup variables such as desired dot weight and min and max pressure are initialized directly from the currently loaded Fluid File. When run manually from the Fluid Manager, these variables reflect the values entered by an operator in the user interface, which may or may not be the same values stored in the Fluid File.

The three “coordinate” pairs that define the calibration curve are:

DWCA_MinPressure, DWCA_DotWeightAtMinPressure

DWCA_PressureAtFinalDotWeight, DWCA_FinalDotWeight

DWCA_MaxPressure, DWCA_DotWeightAtMaxPressure

Intermediate “failed” attempts when determining a final dot weight/pressure are stored in DWCA_IntermediatePressure and DWCA_IntermediateDotWeight.

Table F.52-2 Dot Weight Pressure Setup – Data Variables

| Data Variable Name | ID | SECS Type | Class | Related Collection Events | Description |
|-------------------------------|-----|-----------|-------|---------------------------|--|
| DWCA_MaxPressure | 641 | FLT | DV | 5040 5042 5043 | Maximum pressure used when determining calibration curve |
| DWCA_DotWeightAtMaxPressure | 642 | FLT | DV | 5042 5043 | Dot weight measured at maximum pressure |
| DWCA_MinPressure | 643 | FLT | DV | 5040 5041 5043 | Minimum pressure used when determining calibration curve |
| DWCA_DotWeightAtMinPressure | 644 | FLT | DV | 5041 5043 | Dot weight measured at minimum pressure |
| DWCA_DesiredDotWeight | 645 | FLT | DV | 5040 5043 | Desired dot weight during setup routine |
| DWCA_FinalDotWeight | 646 | FLT | DV | 5043 | Final dot weight when setup completes successfully |
| DWCA_PressureAtFinalDotWeight | 647 | FLT | DV | 5043 | Final pressure at dot weight when setup completes successfully |
| DWCA_DeviationMaxPC | 648 | FLT | DV | 5040 5043 | Maximum dot weight deviation (percentage) |

Table F.52-2 Dot Weight Pressure Setup – Data Variables (continued)

| Data Variable Name | ID | SECS Type | Class | Related Collection Events | Description |
|----------------------------|-----|-----------|-------|---------------------------|---|
| DWCA_IntermediateDotWeight | 649 | FLT | DV | 5044 | Out of tolerance dot weight measured. Tool will retry unless retries exhausted. |
| DWCA_IntermediatePressure | 650 | FLT | DV | 5044 | Pressure when dot weight failed. Tool will retry unless retries exhausted. |

Table F.52-3 Dot Weight Pressure Setup – Related Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|------------------------------|------|--|---|
| ce_DWCA_SetupStarted | 5040 | 641 643 645 648 | Initial collection event signaling start of DWCA setup (DJ9K Dot Weight Pressure Setup). |
| ce_DWCA_MinPressureCompleted | 5041 | 643 644 | Intermediate collection event when dot weight at minimum pressure has been completed. |
| ce_DWCA_MaxPressureCompleted | 5042 | 641 642 | Intermediate collection event when dot weight at maximum pressure has been completed. |
| ce_DWCA_SetupCompleted | 5043 | 641 642 643 644 645 646 647 648 | Final collection event when final dot weight and pressure has been computed and DWCA setup has completed successfully. |
| ce_DWCA_IntermediateValues | 5044 | 649 650 | Intermediate collection event when a fluid pressure / dot weight has failed calibration and the routine is adjusting pressure. The tool will retry unless retries exhausted. |
| ce_DWCA_SetupFailed | 5045 | - | Collection event if setup failed or was aborted by user or tool error. This collection event signals that the DWCA setup routine (DJ9K Dot Weight Pressure Setup) has completed unsuccessfully. |

FlowRateCalib - Remote Command (existing command)

Use this command to run CPJ. If pressure control is not enabled, CPJ without pressure control will be executed. If pressure control is enabled, CPJ with pressure control (DWCA) will be executed.

CPJ with Pressure Control Data Variables and Collection Events

Table F.52-4 CPJ with Pressure Control – Data Variables

| Data Variable Name | ID | SECS Type | Class | Related Collection Events | Description |
|-------------------------------|-----|-----------|-------|---------------------------|--|
| DWCA_DesiredDotWeight | 645 | FLT | DV | 5046 | Desired dot weight during CPJ routine |
| DWCA_FinalDotWeight | 646 | FLT | DV | 5047 | Final dot weight when CPJ completes successfully |
| DWCA_PressureAtFinalDotWeight | 647 | FLT | DV | 5047 | Final pressure at dot weight when CPJ completes successfully |
| DWCA_DeviationMaxPC | 648 | FLT | DV | 5046 | Maximum dot weight deviation (percentage) |
| DWCA_IntermediateDotWeight | 649 | FLT | DV | 5044 | Out of tolerance dot weight measured before reiteration |
| DWCA_IntermediatePressure | 650 | FLT | DV | 5044 | Pressure when out of tolerance dot weight failed |
| DWCA_StartingPressure | 651 | FLT | DV | 5046 | Beginning pressure when CPJ is started |
| DWCA_StartingDotWeight | 652 | FLT | DV | 5046 | Beginning dot weight when CPJ is started |

Table F.52-5 CPJ with Pressure Control – Related Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------|------|--|---|
| ce_DWCA_CPJStarted | 5046 | 645 648 651 652 | Initial collection event signaling start of DWCA CPJ (FLOWRATECALIB). |
| ce_DWCA_CPJCompleted | 5047 | 645 646 647 648 651 652 | Final collection event when final dot weight and pressure has completed. This collection event signals that the DWCA CPJ routine has completed successfully. |
| ce_DWCA_IntermediateValues | 5044 | 649 650 | Intermediate collection event when a fluid pressure / dot weight has failed calibration and the routine is adjusting pressure and retrying. |
| ce_DWCA_CPJFailed | 5048 | - | Collection event if CPJ failed or was aborted by user or tool error. This collection event signals that the DWCA CPJ routine (FLOWRATECALIB) has completed unsuccessfully. |

F.53 Setup “Offset” Data

Table F.53-1 Setup Offset – Data Variables

| Variable Name | ID | SECS Type | Storage Type | Related CEID | Description |
|-------------------|-----|-----------|------------------|--------------|--|
| HSAtPurgeLidZ | 528 | DV | F8 FLT | 3748 | Reported when the height sensor measures the Z value of the purge cup lid. The value reported is the Z height when the sensor is tripped in user units. |
| HSAtScaleLidZ* | 526 | DV | F8 FLT | 3734 | Reported when the height sensor measures the Z value of the Scale 1 cover. The value reported is the Z height when the sensor is tripped in user units. |
| HSAtScale2LidZ | 531 | DV | F8 FLT | 3801 | Reported when the height sensor measures the Z value of the scale 2 cover. The value reported is the Z height when the sensor is tripped in user units. |
| HSAtTactileZ* | 524 | DV | F8 FLT | 3732 | Reported during Needle Z Offsets. The value reported is the Z Position when the height sensor measures the height of the tactile in user units. |
| NdlAtTactileZ_V1* | 525 | DV | F8 FLT | 3733 | Reported during Needle Z Offsets. The value reported is the Z position when the needle (nozzle) touches the tactile (2 nd touch / slow speed) in user units. |
| SubstrateCornerTL | 529 | DV | A[40] FLT,FLT | 3800 | The top left (TL) corner location of the substrate in user units. Reported during Needle to Camera XY Offsets when the corners of the substrate are used to determine the locations of the four dispense dots. |
| SubstrateCornerBR | 530 | DV | A[40] FLT,FLT | 3800 | The bottom right (BR) corner location of the substrate in user units. Reported during Needle to Camera XY Offsets when the corners of the substrate are used to determine the locations of the four dispense dots. |
| TactileCenter | 532 | DV | A[40] FLT,FLT | 3802 | Reported during Needle Z Offsets. The value reported is the center of the tactile in user units. |

F.54 Image Capture

Table F.54-1 Image Capture – Equipment Constants

| Equipment Constant Variable Name | ID | SECS Type | Description |
|----------------------------------|------|-----------|--|
| c_ImageCaptureWpFidsFound | 6584 | A[4] | “ON” enables image capturing of “Found” Workpiece fiducials. “OFF” disables image capturing. |
| c_ImageCaptureWpFidsNotFound | 6585 | A[4] | “ON” enables image capturing of “Not Found” Workpiece fiducials. “OFF” disables image capturing. |
| c_ImageCapturePattFidsFound | 6586 | A[4] | “ON” enables image capturing of “Found” Pattern fiducials. “OFF” disables image capturing. |
| c_ImageCapturePattFidsNotFound | 6587 | A[4] | “ON” enables image capturing of “Not Found” Pattern fiducials. “OFF” disables image capturing. |
| c_ImageCaptureServiceStationPins | 6588 | A[4] | “ON” enables image capturing of Service Station Pins. “OFF” disables image capturing. |
| c_ImageCaptureLUCModelTeachFind | 6589 | A[4] | “ON” enables image capturing of “LUC MODEL” teach and find program and script instructions. “OFF” disables image capturing. |
| c_ImageCaptureXYOffsetDots | 6597 | A[4] | “ON” enables image capturing of the 4 dots found when performing “XY Needle to Camera Offsets”. “OFF” disables image capturing. |
| c_ImageCaptureLmoWpFids | 6598 | A[4] | “ON” enables image capturing of Local Machine Offsets Workpiece fiducials. “OFF” disables image capturing. |
| c_ImageCaptureFilenamePrefix | 6599 | A[50] | Specifies an ASCII string that will be prefixed to the image capture filename. |

Table F.54-2 Image Capture – Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------|------|------------------------|---|
| ce_WpFoundImageSaved | 8027 | 520 | Collection event when a program Workpiece fiducial is found and saved as an image |
| ce_WpNotFoundImageSaved | 8028 | 520 | Collection event when a program Workpiece fiducial is NOT found and saved as an image |
| ce_PattFoundImageSaved | 8029 | 520 523 | Collection event when a program Pattern fiducial is found and saved as an image |

Table F.54-2 Image Capture – Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------------------|------|------------------------|--|
| ce_PattNotFoundImageSaved | 8030 | 520 523 | Collection event when a program Pattern fiducial is NOT found and saved as an image |
| ce_SSIPin1ImageSaved | 8009 | 520 | Collection event when the Service Station Pin 1 is found (or not found) and saved as an image |
| ce_SSIPin2ImageSaved | 8010 | 520 | Collection event when the Service Station Pin 2 is found (or not found) and saved as an image |
| ce_LUCModelFindImageSaved | 8023 | 520 | Collection event when the Lookup Camera LUC MODEL FIND program or script instruction is executed and the image is saved |
| ce_LUCModelTeachImageSaved | 8024 | 520 | Collection event when the Lookup Camera LUC MODEL TEACH script instruction is executed and the image is saved |
| ce_XYDot1ImageSaved | 8011 | 520 | Collection event when Needle to Camera XY offset is executed and the first dot is found (or not found) and saved as an image |
| ce_XYDot2ImageSaved | 8012 | 520 | Collection event when Needle to Camera XY offset is executed and the second dot is found (or not found) and saved as an image |
| ce_XYDot3ImageSaved | 8013 | 520 | Collection event when Needle to Camera XY offset is executed and the third dot is found (or not found) and saved as an image |
| ce_XYDot4ImageSaved | 8014 | 520 | Collection event when Needle to Camera XY offset is executed and the fourth dot is found (or not found) and saved as an image |
| ce_LmoWpFid1ImageSaved | 8025 | 520 | Collection event when the Local Machine Offset Workpiece is re-aligned and the first fiducial is found (or not found) and saved as an image |
| ce_LmoWpFid2ImageSaved | 8026 | 520 | Collection event when the Local Machine Offset Workpiece is re-aligned and the second fiducial is found (or not found) and saved as an image |
| ce_ImageSaveInstructionImageSaved | 8031 | 520 | Collection event when the “IMAGE SAVE” instruction is executed and the image is saved |
| ce_ImageSaveManualImageSaved | 8032 | 520 | Collection event when an image is manually saved from the video window |

Table F.54-3 Image Capture – Data Variables

| Data Variable Name | ID | SECS Type | Description |
|--------------------|-----|-----------|--|
| ImageFilename | 520 | A[100] | Name and path of image file |
| RunningPatternName | 523 | A[50] | Name of pattern when a pattern image is saved. |

F.55 Additional Offset Variables

Table F.55-1 Additional Offset Variables – Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|------------------------|---|
| ce_SSPin1Found | 8005 | 553 534 | Collection event when the Service Station Pin 1 is found |
| ce_SSPin1NotFound | 8006 | - | Collection event when the Service Station Pin 1 is not found |
| ce_SSPin2Found | 8007 | 553 554 | Collection event when the Service Station Pin 2 is found |
| ce_SSPin2NotFound | 8008 | - | Collection event when the Service Station Pin 2 is not found |
| ce_XYDot1Found | 8015 | 535 536 | Collection event when the Needle to Camera XY Offset Dot 1 is found |
| ce_XYDot1NotFound | 8016 | - | Collection event when the Needle to Camera XY Offset Dot 1 is not found |
| ce_XYDot2Found | 8017 | 535 536 | Collection event when the Needle to Camera XY Offset Dot 2 is found |
| ce_XYDot2NotFound | 8018 | - | Collection event when the Needle to Camera XY Offset Dot 2 is not found |
| ce_XYDot3Found | 8019 | 535 536 | Collection event when the Needle to Camera XY Offset Dot 3 is found |
| ce_XYDot3NotFound | 8020 | - | Collection event when the Needle to Camera XY Offset Dot 3 is not found |
| ce_XYDot4Found | 8021 | 535 536 | Collection event when the Needle to Camera XY Offset Dot 4 is found |
| ce_XYDot4NotFound | 8022 | - | Collection event when the Needle to Camera XY Offset Dot 4 is not found |

Table F.55-2 Additional Offset Variables – Data Variables

| Data Variable Name | ID | SECS Type | Description |
|--------------------|-----|------------------|--|
| SSPinXY | 533 | A[40] FLT,FLT | XY location of Service Station Pin found |
| SSPinScore | 534 | I2 | Score of found Service Station fiducial |
| XYDotOffsetXY | 535 | A[40] FLT,FLT | XY location of Needle to Camera XY Offset Dot found |
| XYDotOffsetScore | 536 | INT | Score of Needle to Camera XY Offset Dot fiducial found |

F.56 Prompted Setup, Flowrate and Purge Collection Events

GEM variables and collection events have been added to notify the SECS/GEM host when a scripted prompted setup file has started and completed and when a purge or flow rate has been performed. Some existing collection events have been expanded and are now triggered whenever a purge or flowrate is performed (previously some were only triggered in response to a remote request to purge or to perform a flowrate).

Table F.56-1 Prompted Setup, Flowrate and Purge - Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|---------------------------------|------|------------------------|--|
| ce_PromptedSetupStarted | 4001 | 573 | Scripted prompted setup has started either manually by the operator or remotely from a SECS/GEM host. |
| ce_PromptedSetupCompleted | 4002 | 573 | Scripted prompted setup has finished and all tasks have been successfully completed. |
| ce_PromptedSetupIncomplete | 4022 | 573 | Scripted prompted setup has finished but all tasks were not successfully completed. |
| ce_PromptedSetupScriptLoaded | 4023 | 573 | A scripted prompted setup file has been loaded and is ready to run. |
| ce_PurgePass | 3740 | --- | A purge has successfully completed using Valve 1. |
| ce_PurgePass_V2 | 3806 | --- | A purge has successfully completed using Valve 2. |
| ce_PurgeFail | 3766 | --- | A purge was started but did not successfully complete using Valve 1. |
| ce_PurgeFail_V2 | 3807 | --- | A purge was started but did not successfully complete using Valve 2. |
| ce_FlowRateCalibComplete_V1Pass | 3730 | --- | A flowrate has successfully completed using Valve 1. This collection event will also occur when an operator selects OK when running flowrate manually. |
| ce_FlowRateCalibComplete_V2Pass | 3731 | --- | A flowrate has successfully completed using Valve 2. This collection event will also occur when an operator selects OK when running flowrate manually. |
| ce_FlowRateCalibComplete_V1Fail | 3784 | --- | A flowrate was performed but did not successfully complete using Valve 1. This collection event will also occur when an operator selects CANCEL when running flowrate manually. |
| ce_FlowRateCalibComplete_V2Fail | 3785 | --- | A flowrate was performed but did not successfully complete using Valve 2. This collection event will also occur when an operator selects CANCEL when running flowrate manually. |

Table F.56-2 Prompted Setup, Flowrate and Purge – New Data Variable

| Variable Name | ID | Storage Type | Related CEID | Description |
|-----------------------------|-----|--------------|------------------------------|--|
| PromptedSetupScriptFilename | 573 | A[100] | 4001 4002 4022 4073 | Name of currently loaded prompted setup script file. |

F.57 DJ Cycle Count

Table F.57-1 DJ Cycle Count - Equipment Constants

| Variable Name | ID | Storage Type | Class | Related CEID | Description |
|-------------------|------|---------------------------|-------|--------------|---|
| c_DJCycleCount_V1 | 6502 | A[30] *See Description | EC | None | Running total of DJ shots for Valve 1. *The machine format of this variable is floating point that has been converted to a SECS/GEM string variable to prevent rounding and truncation errors that would occur if uploaded as a float. To reset this value from the SC, EC 6502 should be set to the ASCII string "0". |
| c_DJCycleCount_V2 | 6503 | A[30] *See Description | EC | None | Running total of DJ shots for valve 2. *The machine format of this variable is floating point that has been converted to a SECS/GEM string variable to prevent rounding and truncation errors that would occur if uploaded as a float. To reset this value from the SC, EC 6503 should be set to the ASCII string "0". |

F.58 Low Fluid Collection Events

Table F.58-1 Low Fluid – Collection Events

| Collection Event Name | CEID | Class | Description |
|-----------------------|------|-------|---|
| ce_LowFluid_V1 | 3696 | CEID | Collection event triggered when low fluid is detected on Valve 1. |
| ce_LowFluid_V2 | 3697 | CEID | Collection event triggered when low fluid is detected on valve 2. |

F.59 Height Sense

Table F.59-1 Height Sense –Data Variables and Collection Events

| Variable Name | ID | Storage Type | Class | Related CEID | Description |
|---------------------------|------|--------------|-------|--------------|---|
| HeightSenseOriginConv1 | 7701 | F8 | EC | 8401 | Height Sense on Conveyor 1 |
| ce_HeightSenseOriginConv1 | 8401 | -- | CEID | -- | Collection event is triggered when Height Sense is changed. |
| HeightSenseOriginConv2 | 7702 | F8 | EC | 8402 | Height Sense on Conveyor 2 |
| ce_HeightSenseOriginConv2 | 8402 | -- | CEID | -- | Collection event is triggered when Height Sense is changed. |

F.60 Electronic Pressure

Table F.60-1 Electronic Pressure –Data Variables and Collection Events

| Variable Name | ID | Storage Type | Class | Related CEID | Description |
|----------------------------|------|--------------|-------|------------------------------|--|
| VALVEPRESSUREV1 | 421 | F8 | DV | 3703 | Electronic controlled valve pressure 1. |
| ce_VavlePressureValve_V1 | 3703 | -- | CEID | -- | Collection event is triggered when valve pressure is checked. |
| FLUIDPRESSUREV1 | 422 | F8 | DV | 3704 | Electronic controlled fluid pressure 1. |
| ce_FluidPressureValve_V1 | 3704 | -- | CEID | -- | Collection event is triggered when fluid pressure is checked. |
| COOLINGPRESSUREV1 | 423 | F8 | DV | 3705 | Electronic controlled cooling pressure 1. |
| ce_CoolingPressureValve_V1 | 3705 | -- | CEID | -- | Collection event is triggered when cooling pressure is checked. |
| VALVEPRESSUREV2 | 424 | F8 | DV | 3706 | Electronic controlled valve pressure 2. |
| ce_VavlePressureValve_V2 | 3706 | -- | CEID | -- | Collection event is triggered when valve pressure is checked. |
| FLUIDPRESSUREV2 | 425 | F8 | DV | 3707 | Electronic controlled fluid pressure 2. |
| ce_FluidPressureValve_V2 | 3707 | -- | CEID | -- | Collection event is triggered when fluid pressure is checked. |
| COOLINGPRESSUREV2 | 426 | F8 | DV | 3708 | Electronic controlled cooling pressure 2. |
| ce_CoolingPressureValve_V2 | 3708 | -- | CEID | -- | Collection event is triggered when cooling pressure is checked. |
| LaneNumber | 521 | I4 | DV | 8000 8801 8802 8400 | Lane number (1 or 2) where event has occurred. |
| ScaleNumber | 522 | I4 | DV | TBD | Scale number (1 or 2) where dispense related operation has occurred. |

F.61 Scale Number

Table F.61-1 Scale Number – Data Variables

| Variable Name | ID | Storage Type | Class | Related CEID | Description |
|---------------|-----|--------------|-------|--------------|--|
| ScaleNumber | 522 | I4 | DV | TBD | Scale number (1 or 2) where dispense related operation has occurred. |

F.62 Program Fiducial ON/OFF Control

Turning fiducials ON or OFF is controlled solely by the SECS/GEM host. There will be no user interface other than the configuration editor.

There are two levels of control: Workpiece fiducials may be turned ON or OFF.

Patterns enabled for SECS/GEM control may have their fiducials turned ON or OFF. Turning fiducial finding ON or OFF by individual pattern name or by lane number will not be supported.

Vision “pipelining” must be turned off. If “pipelining” is active, the SECS/GEM host will not have the capability to turn ON or OFF fiducials. This should not be a concern as pipelining should not be used when running with dual lanes.

When fiducial finding is turned OFF, the workpiece and/or pattern(s) will not be translated or rotated – the parts will be dispensed on in the same location and orientation in which they were taught.

The SECS/GEM host will have the ability to change fiducial finding from ON to OFF and vice versa between carriers while production is running. The change will not take effect until the carrier(s) currently being processed have finished and the next carrier(s) have arrived at the dispense station.

Pattern Fiducials

Patterns with fiducials that will be turned ON or OFF by the SECS/GEM host must have SECS/GEM control of fiducial finding enabled. All enabled patterns will be controlled by a single equipment constant.

If SECS/GEM control is not enabled, the pattern will ignore SECS/GEM host control and will always find fiducials. This allows individual selection of those patterns that should always find fiducials and those that should be controlled by the SECS/GEM host.

SECS/GEM Control

When a pattern is created, a dialog requesting the name of the pattern and the number of fiducials is presented.

If SECS/GEM is enabled on the tool, a checkbox will appear to enable SECS/GEM control of fiducial finding. This checkbox is accessible only if a selection other than “None” is chosen for the number/type of fiducials.

By default, this box will not be checked.

- Check this box to allow the SECS/GEM host to control fiducial finding.
- Do not check this box if the pattern should always find fiducials and should not be controlled by the SECS/GEM host.




Figure F.62-1 Create Pattern – Allow SECS/GEM Control of Fiducial Search

To alter control of an existing pattern or to change the control after a pattern has been created, open the desired pattern in the Programming Window. Select **Edit>Edit SECS/GEM Fid Control**. Note that this selection is available only if a pattern that uses fiducials is currently being displayed.




Figure F.62-2 Edit SECS/GEM Fid Control

A dialog will be displayed reflecting the current state of this pattern and to allow SECS/GEM control to be changed.




Figure F.62-3 Multiple Flow Rate Calibration

SECS/GEM Variables

Fiducial finding control is achieved through equipment constants. The SECS/GEM host does not have to be in remote mode.

Table F.62-1 Program Fiducial ON/OFF Control – Equipment Constants

| Equipment Constant | Data Type | ID | Description |
|------------------------|-----------------------|------|--|
| ec_WorkpieceFindFids | A[4] “ON” or “OFF” | 6590 | If set to “ON”, workpiece fiducials will be found (normal operating mode). If set to “OFF”, workpiece fiducials will be skipped. |
| ec_PatternFindFidsLane | A[4] “ON” or “OFF” | 6591 | If set to “ON”, ALL pattern fiducials will be found (normal operating mode). If set to “OFF”, patterns flagged for SECS/GEM control will skip fiducial finding. |

Log File

To turn on logging, select “SECS/GEM Host Configuration Change” under the “SECS/GEM” button in the event manager. This selection is normally turned on by default. The log file will indicate when one of the equipment constants has changed or when the workpiece or pattern fiducials are being skipped. These entries will appear when one of the equipment constants are changed:

```
2008-06-30,17:05:58.953,SECS/GEM Host Configuration Change,VID=6590,Old Value=ON,New Value=OFF
2008-07-01,18:04:52.732,SECS/GEM Host Configuration Change,VID=6591,Old Value=ON,New Value=OFF
```

These entries will appear only if finding fiducials has been turned off:

```
2008-07-01,18:05:02.105,SECS/GEM Host Configuration Change,Pattern Find Fiducials=OFF
2008-07-01,18:05:02.105,SECS/GEM Host Configuration Change,Workpiece Find Fiducials=OFF
```

Dual Lanes

For pattern fiducials, the SECS/GEM host will not be able to selectively turn fiducial finding on or off by lane number. When turned on, both lanes will find fiducials. When turned off, neither lane will attempt to find fiducials.

For processing fiducials on just the first board of each lane during recipe validation, the SECS/GEM host should enable workpiece and pattern fiducial finding until collection events are received from each lane indicating the first board has been processed. Fiducial finding can then be turned off for subsequent boards.

Configuration Editor

With normal operation, the SECS/GEM host will control turning fiducials ON or OFF. However, if the SECS/GEM host is not available and has left the tool in an undesirable state (ie, has turned fiducials OFF but this state is no longer desired), the workpiece and pattern control variables can be changed manually via the configuration editor.

1. In the left window, select the Configuration Group “Gem Manager”.
2. In the right window, “Find Pattern Fids” controls pattern fiducial finding. Set this parameter to “ON” to allow pattern fiducials to be found (normal running state) or “OFF” to turn off fiducial finding for those patterns with SECS/GEM control enabled.
3. “Find Workpiece Fids” in the right window controls workpiece fiducial finding. Set this parameter to “ON” to allow workpiece fiducials to be found (normal running state) or “OFF” to turn off workpiece fiducial finding.




Figure F.62-4 Editing Configuration Files

File Versioning Note

When opening existing Fluidmove programs that have been created with a previous version of FmXP, a message will appear:




Figure F.62-5 Fluidmove – File Versioning Error Message

This prompt is displayed because the SECS/GEM control information is being added to the program. This message will appear only once if the program is saved and will not appear when creating new programs.

F.63 Scale Overflow

Equipment Constants

The following equipment constants will affect scale overflow detection as described. Variables ending in _S1 refer to Scale 1 and variables ending in _S2 refer to scale 2.

The SECS/GEM host should monitor c_OverflowCurrentCupWeightMG_S1/S2 for the current total weight in the cup.

c_OverflowAccumulatedTotalMG_S1/S2 and c_OverflowPreTareMG_S1/S2 are for internal use and individually are only part of the total cup weight.

Read carefully the affect that changing each equipment constant will have on overflow detection. It is recommended that the SECS/GEM host should not alter the weight variables.

c_OverflowProtectionEnabled_S1/S2

- Enables or disables the overflow protection feature.
- Set variable to ASCII string “ON” to enable the feature or “OFF” to disable the feature.

c_OverflowMaxCapacityMG_S1/S2

- Contains the maximum scale overflow capacity for the scale.

c_OverflowWarningPercentage_S1/S2

- Contains the percentage of the maximum scale overflow capacity of the scale when the operator is warned to change the cup.
- Note that 1.0 = 100%, 0.5 = 50%, 0.25 = 25%, ...

c_OverflowCurrentCupWeightMG_S1/S2

- Contains the current total weight in cup in milligrams.
- This equipment constant contains the total of the accumulated weight plus the pre-tared weight.
- Zeroing this value will also zero c_OverflowAccumulatedTotalMG_S1/S2 and c_OverflowPreTareMG_S1/S2.
- Normally this equipment constant should not be changed by the SECS/GEM host. The equipment will keep track of the weight in the cup.
- If this value is changed by the host, it is recommended that only a zero is written to this equipment constant to clear the total weight in the scale cup. A non-zero value will have the following affect on the accumulated and tare value equipment constants:

c_OverflowAccumulatedTotalMG_S1/S2 will be set to the value of c_OverflowCurrentCupWeightMG_S1/S2.

c_OverflowPreTareMG_S1/S2 will be zeroed out.

c_OverflowAccumulatedTotalMG_S1/S2

- Contains the current accumulated weight of scale in milligrams.
- This is NOT the total weight in the cup. Total weight in the cup is the total of this variable (accumulated weight) plus pre-tared weight.
- It is recommended that the SECS/GEM host does not change this variable and if changed will indirectly affect the total weight.
- If this value is changed, c_OverflowCurrentCupWeightMG_S1/S2 will also be changed to the new value plus the existing pre-tare value.

c_OverflowPreTareMG_S1/S2

- Contains the current “pre-tare” weight in milligrams.
- This is NOT the total weight in the cup. Total weight in the cup is the total of accumulated weight plus this value (pre-tared weight).
- It is recommended that the SECS/GEM host does not change this variable and if changed will indirectly affect the total weight.
- If this value is changed, c_OverflowCurrentCupWeightMG_S1/S2 will also be changed to the new value plus the existing accumulated value.

c_OverflowLastWeightReadingStable_S1/S2

- Indicates if the last weight reading returned from the scale was “stable”
- This equipment constant is for internal use and it is recommended that the SECS/GEM host does not change this value

In general, $c_OverflowCurrentCupWeightMG_S1/S2$ (total weight) = $c_OverflowAccumulatedTotalMG_S1/S2$ (accumulated weight) + $c_OverflowPreTareMG_S1/S2$ (pre-tare weight).

Table F.63-1 Scale Overflow – Equipment Constants

| Variable Name | ECID | SECS Type | Storage Type | FmConfig.ini Entry |
|--------------------------------|------|-----------|--------------|---------------------------------------|
| | | | | [Scale Manager] |
| c_OverflowProtectionEnabled_S1 | 6703 | A[4] | ASCII | Overflow Protection Enabled = |
| c_OverflowProtectionEnabled_S2 | 6704 | A[4] | ASCII | Scale 2 Overflow Protection Enabled = |
| c_OverflowMaxCapacityMG_S1 | 6705 | A[30] | FLT | Max Capacity (mg) = |
| c_OverflowMaxCapacityMG_S2 | 6706 | A[30] | FLT | Scale 2 Max Capacity (mg) = |
| c_OverflowWarningPercentage_S1 | 6707 | A[30] | FLT | Warning Percentage = |

Table F.63-1 Scale Overflow – Equipment Constants (continued)

| Constant Name | ECID | SECS Type | Storage Type | FmConfig.ini Entry |
|--------------------------------------|------|-----------|--------------|--------------------------------------|
| c_OverflowWarningPercentage_S2 | 6708 | A[30] | FLT | Scale 2 Warning Percentage = |
| c_OverflowCurrentCupWeightMG_S1 | 6709 | A[30] | FLT | Current Cup Weight (mg) = |
| c_OverflowCurrentCupWeightMG_S2 | 6710 | A[30] | FLT | Scale 2 Current Cup Weight (mg) = |
| c_OverflowAccumulatedTotalMG_S1 | 6711 | A[30] | FLT | Accumulated Total (mg) = |
| c_OverflowAccumulatedTotalMG_S2 | 6712 | A[30] | FLT | Scale 2 Accumulated Total (mg) = |
| c_OverflowPreTareMG_S1 | 6713 | A[30] | FLT | Pre-Tare Total (mg) = |
| c_OverflowPreTareMG_S2 | 6714 | A[30] | FLT | Scale 2 Pre-Tare Total (mg) = |
| c_OverflowLastWeightReadingStable_S1 | 6715 | A[4] | ASCII | Last Weight Reading Stable = |
| c_OverflowLastWeightReadingStable_S2 | 6716 | A[4] | ASCII | Scale 2 Last Weight Reading Stable = |

Collection Events

Table F.63-2 Scale Overflow – Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-----------------------|------|--|--|
| ce_ScaleOverflow_S1 | 4024 | 6703 6705 6707 6709 6711 6713 6715 | The operator has been notified that Scale 1 has met or exceeded maximum weight capacity. |
| ce_ScaleOverflow_S2 | 4027 | 6704 6706 6708 6710 6712 6714 6716 | The operator has been notified that scale 2 has met or exceeded maximum weight capacity. |

Table F.63-2 Scale Overflow – Collection Events (Continued)

| Collection Event Name | CEID | Related Data Variables | Description |
|----------------------------|------|--|--|
| ce_ScaleOverflowWarning_S1 | 4025 | 6703 6705 6707 6709 6711 6713 6715 | The operator has been notified that Scale 1 has reached the warning level weight capacity. |
| ce_ScaleOverflowWarning_S2 | 4028 | 6704 6706 6708 6710 6712 6714 6716 | The operator has been notified that scale 2 has reached the warning level weight capacity. |
| ce_ScaleOverflowReset_S1 | 4026 | 6703 6705 6707 6709 6711 6713 6715 | Scale 1 overflow parameters have been reset. This collection event will occur when an operator has manually reset the overflow parameters from the scale configuration menu or has indicated that the cup has been replaced in response to a warning or overflow message. |
| ce_ScaleOverflowReset_S2 | 4029 | 6704 6706 6708 6710 6712 6714 6716 | Scale 2 overflow parameters have been reset. This collection event will occur when an operator has manually reset the overflow parameters from the scale configuration menu or has indicated that the cup has been replaced in response to a warning or overflow message. |

F.64 Electronic Pressure LMO

Each E/P device (valve, cooling and fluid) contains two offsets. A “setting” offset that is added before writing a value to the E/P controller and a “reading” offset that is applied to the value read from the E/P controller before making computations or displaying the value.

When the SECS/GEM host changes an LMO value, the change will be logged into the Asymtek log file:

2008-12-16,10:13:02.671,SECS/GEM Host Configuration Change,Pressure Offset Change,VID=1800,Old Value=3.000000,New Value=5.000000

When modifying the offsets, the SECS/GEM host must ensure the values are downloaded in the same units as indicated as the “units” status variable described below.

Note that currently the E/P hardware supports only Valve 1.

Equipment Constants

Table F.64-1 Electronic Pressure LMO - Equipment Constants

| Constant Name | ECID | SECS Type | Storage Type | Description |
|------------------------------------|------|-----------|--------------|---|
| ec_ValvePressSetLmoOffsetUsr_V1 | 1800 | F8 | FLT | Electronic Valve Pressure setting LMO for Valve 1 |
| ec_CoolingPressSetLmoOffsetUsr_V1 | 1801 | F8 | FLT | Electronic Cooling Pressure setting LMO for Valve 1 |
| ec_FluidPressSetLmoOffsetUsr_V1 | 1802 | F8 | FLT | Electronic Fluid Pressure setting LMO for Valve 1 |
| ec_ValvePressReadLmoOffsetUsr_V1 | 1803 | F8 | FLT | Electronic Valve Pressure reading LMO for Valve 1 |
| ec_CoolingPressReadLmoOffsetUsr_V1 | 1804 | F8 | FLT | Electronic Cooling Pressure reading LMO for Valve 1 |
| ec_FluidPressReadLmoOffsetUsr_V1 | 1805 | F8 | FLT | Electronic Fluid Pressure reading LMO for Valve 1 |
| ec_ValvePressSetLmoOffsetUsr_V2 | 1806 | F8 | FLT | Electronic Valve Pressure setting LMO for valve 2 |
| ec_CoolingPressSetLmoOffsetUsr_V2 | 1807 | F8 | FLT | Electronic Cooling Pressure setting LMO for valve 2 |
| ec_FluidPressSetLmoOffsetUsr_V2 | 1808 | F8 | FLT | Electronic Fluid Pressure setting LMO for valve 2 |
| ec_ValvePressReadLmoOffsetUsr_V2 | 1809 | F8 | FLT | Electronic Valve Pressure reading LMO for valve 2 |
| ec_CoolingPressReadLmoOffsetUsr_V2 | 1810 | F8 | FLT | Electronic Cooling Pressure reading LMO for valve 2 |
| ec_FluidPressReadLmoOffsetUsr_V2 | 1811 | F8 | FLT | Electronic Fluid Pressure reading LMO for valve 2 |

Status Variables

The following status variables indicate what units the LMO offsets are stored in (“psi” or “kPa”). These variables are for internal use and cannot be modified.

Table F.64-2 Electronic Pressure LMO – Status Variables

| Status Variable Name | ID | SECS Type | Description |
|------------------------------|------|-----------|--|
| sv_PressLmoOffsetUserUnit_V1 | 1830 | A[10] | Units that E/P LMO offsets are stored in for Valve 1: “kPa” or “psi” |
| sv_PressLmoOffsetUserUnit_V2 | 1831 | A[10] | Units that E/P LMO offsets are stored in for valve 2: “kPa” or “psi” |

When an E/P LMO offset is changed by the operator via the user interface, a collection event will occur and the associated data variables will contain the old and new values.

Collection Events

Table F.64-3 Electronic Pressure LMO – Collection Events

| Collection Event Name | CEID | Related Data Variables | Description |
|-------------------------------|------|------------------------|--|
| ce_PressureOffsetChanged | 8033 | 450 575 574 | Collection event when operator changes an E/P LMO offset value. |
| ce_PressureOffsetUnitsChanged | 8034 | 450 453 451 | Collection event when the internal units of E/P LMO offset changes. This value will change when “Air Pressure” units are changed from the main configuration dialog and after the LMO offset dialog is visited and exited. |

Table F.64-4 Electronic Pressure LMO – Data Variables

| Variable Name | ID | SECS Type | Related CEID | Description |
|---------------------|-----|-----------|--------------|--|
| ParameterChangedVid | 450 | I4 | 8033 8034 | The VID of the E/P LMO offset or unit that is being changed. |
| OldParameterDouble | 575 | F8 | 8033 | The current “old” E/P LMO offset before changed. |
| NewParameterDouble | 574 | F8 | 8033 | The new E/P LMO offset after changed. |
| OldParameterString | 453 | A[100] | 8034 | The current “old” units of E/P LMO offsets before changed. |
| NewParameterString | 451 | A[100] | 8034 | The new units of E/P LMO offsets after changed. |

F.65 Operator ID

NOTE: there is currently no Fluidmove interface for Operator ID.

Table F.65-1 Operator ID – Status Variables

| Status Variable Name | ID | Storage Type | SECS Type | Related CEID | Description |
|----------------------|-----|--------------|-----------|--------------|--|
| OperatorLoginID | 340 | A[100] | SV | 3640 3641 | Operator log in ID. Collection event 3640 will be triggered when an operator logs in. Collection event 3641 will be triggered when an operator logs out. |

F.66 Additional Configuration Parameter Variables

Table F.66-1 Additional Configuration Parameter Variables

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|---------------------------|-------|--------------|-------|--------------|---|
| Model | | | | | |
| Software | 1561 | A[20] | SV | None | Fluidmove software FmXP |
| OperatingSystem | 1560 | A[20] | SV | None | Computer operating system XP |
| SoftwareRev | 1562 | A[20] | SV | None | Dispenser/Heater Module software version |
| Setup Language | | | | | |
| c_UILanguage | 1566 | I4 | SV | None | User interface language |
| Setup Units | | | | | |
| p_Units | 11601 | A[30] | DV | 3672 | System units (inch, mm, mach) |
| c_ElectronicPressureUnits | 6570 | A[10] | EC | None | Pressure units |
| c_AirflowUnits | 6520 | I4 | EC | None | Airflow units |
| Change Operator Level | | | | | |
| c_OperatorLevel | 6600 | I4 | EC | None | (Production = 1, System = 2, Service = 3) |
| c_StartinProdOplevel | 6011 | A4 | EC | None | Startup operator level |
| c_ChangeOperatorLevel | 6005 | A[4] | EC | None | Set operator level when idle |
| c_ProgramIdleTimeLimit | 6717 | I4 | EC | None | Program idle time limit operator level |
| Machine Offsets | | | | | |
| c_HeightSensorType | 6033 | A[30] | EC | None | Sensor Type |
| c_NSZBeamInput | 6215 | I4 | EC | None | Sensor I/O bit |
| c_TactileSensorInput | 6213 | I4 | EC | None | Sensor I/O bit |
| c_SuckbackPeriod | 6228 | A[30] | EC | None | Reverse period |
| C_SuckbackLength | 6229 | A[30] | EC | None | Reverse time |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|---|------|--------------|-------|--------------|---|
| c_MachineSetupMode | 6000 | A[20] | EC | None | Scripted valve offset |
| c_ScriptedVOFileName | 6001 | A[60] | EC | None | Script file name |
| c_CameraAssistedScripts | 6002 | A[4] | EC | None | Camera assisted mode |
| c_UseSeviceStationData | 6601 | A[4] | EC | None | Service station mode |
| Setup Scripts Options | | | | | |
| c_UseScript | 6255 | A[4] | EC | None | Use setup script |
| c_Valve1PromptedSetupScriptFile | 6259 | A[60] | EC | None | Prompted setup filename |
| c_Valve1ChangeSyringeScriptFile | 6260 | A[60] | EC | None | Change syringe script filename |
| c_Valve1LowFluidScriptFile | 6261 | A[60] | EC | None | Low fluid script filename |
| Setup Runtime Preferences – Start Production | | | | | |
| c_HomeZAxisatProd | 6020 | A[4] | EC | None | Home Z at production start |
| c_HomeAllAxesatProd | 6021 | A[4] | EC | None | Home all axis at production start |
| c_MoveToSystemLocation | 6030 | A[4] | EC | None | Move to system location at production start |
| c_CheckForDisabledInstructions | 6701 | A[4] | EC | None | Check for disabled instructions |
| Setup Runtime Preferences – Purge | | | | | |
| c_PurgeBeforeEachRun_V1 | 6602 | A[4] | EC | None | Purge before each board |
| c_PurgeAfterEachRun_V1 | 6603 | A[4] | EC | None | Purge after each board |
| Setup Runtime Preferences – Production | | | | | |
| c_EnableRunSetupForProduction | 6025 | A[4] | EC | None | Enable run setup/production |
| c_LotContolEnabled | 6604 | A[4] | EC | None | Enable lot control for production |
| c_CheckSystemAirPressure | 6026 | A[4] | EC | None | Check system air pressure |
| c_CheckAirPressEveryInstruction | 6605 | I4 | EC | None | Check air every instruction |
| c_ConveyorEmptyTimeLimit | 6606 | I4 | EC | None | Alert if conveyor empty after time limit |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|---|-------|--------------|-------|--------------|------------------------------------|
| c_EnableToolingVacuum_1 | 6607 | A[4] | EC | None | Enable tooling vacuum 1 |
| c_ToolingVacuumInput_1 | 6608 | I4 | EC | None | Tooling vacuum I/O input 1 |
| c_EnableToolingVacuum_2 | 6609 | A[4] | EC | None | Enable tooling vacuum 2 |
| c_ToolingVacuumInput_2 | 6610 | I4 | EC | None | Tooling vacuum I/O input 2 |
| p_MoveToFirstFidLocation | 11610 | A[4] | DV | 3672 | Post run park location |
| p_MoveToSystemLocation | 11611 | A[4] | DV | 3672 | Post run park location |
| p_SystemLocationName | 11612 | A[100] | DV | 3672 | System location name |
| Setup Runtime Preferences – E10 Equipment States | | | | | |
| c_E10StatesEnabled | 6611 | A[4] | EC | None | Enable E10 States |
| Setup Runtime Preferences – Beacon Control General Error | | | | | |
| c_GenErrStateEnabledBeacon | 6612 | A4 | EC | None | Enable beacon general error |
| c_GenErrStateEnabledAudAlarm | 6613 | A4 | EC | None | Enable beacon audible alarm |
| c_GenErrStateOutputBit | 6614 | I4 | EC | None | Beacon state I/O output |
| c_GenErrStateOutputLevel | 6615 | A[40] | EC | None | Gen error state output level |
| Setup Runtime Preferences – Beacon Control Vision Error | | | | | |
| c_VisionErrStateEnabledBeacon | 6616 | A4 | EC | None | Enable beacon vision error |
| c_VisionErrStateEnabledAudAlarm | 6617 | A4 | EC | None | Enable beacon vision audible alarm |
| c_VisionErrStateOutputBit | 6618 | I4 | EC | None | Vision error I/O output bit |
| c_VisionErrOutputLevel | 6619 | A[40] | EC | None | Vision error output level |
| Setup Runtime Preferences – Beacon Control Heater Error | | | | | |
| c_HeaterErrStateEnabledBeacon | 6620 | I4 | EC | None | Enable beacon heater error |
| c_HeaterErrStateEnabledAudAlarm | 6621 | A4 | EC | None | Enable beacon heater audible alarm |
| c_HeaterErrStateOutputBit | 6622 | I4 | EC | None | Heater error state I/O output bit |
| c_HeaterErrStateOutputLevel | 6623 | A[40] | EC | None | Heater error state output level |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|--|------|--------------|-------|--------------|--|
| Setup Runtime Preferences – Beacon Control Production Run | | | | | |
| c_ProdRunStateEnabledBeacon | 6624 | I4 | EC | None | Enable beacon production run program states |
| c_ProdRunStateEnabledAudAlarm | 6625 | A4 | EC | None | Enable beacon audible alarm prod run prog states |
| c_ProdRunStateOutputBit | 6626 | I4 | EC | None | Prod run state I/O output bit |
| c_ProdRunStateOutputLevel | 6627 | A[40] | EC | None | Prod run state output level |
| Setup Runtime Preferences – Beacon Control Programming Run | | | | | |
| c_ProgRunStateEnabledBeacon | 6628 | A4 | EC | None | Enable beacon programming run states |
| c_ProgRunStateEnabledAudAlarm | 6629 | A4 | EC | None | Enable beacon audible alarm programming run states |
| c_ProgRunStateOutputBit | 6630 | I4 | EC | None | Programming run state I/O output bit |
| c_ProgRunStateOutputLevel | 6631 | A[40] | EC | None | Programming run state output level |
| Setup Runtime Preferences – Beacon Control Run from SECS/GEM | | | | | |
| c_SECSGEMRunStateEnabledBeacon | 6632 | A4 | EC | None | Enable beacon run state SECS/GEM |
| c_SECSGEMRunStateEnabledAudAlarm | 6633 | A4 | EC | None | Enable beacon audible alarm SECS/GEM |
| c_SECSGEMRunStateOutputBit | 6634 | I4 | EC | None | SECS/GEM run beacon output bit |
| c_SECSGEMRunStateOutputLevel | 6635 | A[40] | EC | None | SECS/GEM run beacon output level |
| Setup Runtime Preferences – Beacon Control Dry Run | | | | | |
| c_DryRunStateEnabledBeacon | 6636 | A4 | EC | None | Enable beacon dry run state |
| c_DryRunStateEnabledAudAlarm | 6637 | A4 | EC | None | Enable beacon dry run audible alarm |
| c_DryRunStateOutputBit | 6638 | I4 | EC | None | Dry run beacon output bit |
| c_DryRunStateOutputLevel | 6639 | A[40] | EC | None | Dry run beacon output level |
| Setup Runtime Preferences – Beacon Control Low Fluid Critical | | | | | |
| c_LowFluidStateEnabledBeacon | 6640 | A4 | EC | None | Enable beacon low fluid |
| c_LowFluidStateEnabledAudAlarm | 6641 | A4 | EC | None | Enabled beacon audible alarm low fluid |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|--|------|--------------|-------|--------------|--|
| c_LowFluidOutputBit | 6642 | I4 | EC | None | Beacon low fluid I/O output bit |
| c_LowFluidAuxOutputBit | 6643 | I4 | EC | None | Beacon low fluid I/O aux output bit |
| c_LowFluidOutputLevel | 6644 | A[40] | EC | None | Beacon low fluid output level |
| Setup Runtime Preferences – Beacon Control Low Fluid Warning | | | | | |
| c_LowFluidBoardCntDwnStateEnabledBeacon | 6645 | A4 | EC | None | Enabled beacon audible alarm low fluid warning |
| c_LowFluidBoardCntDwnStateEnabledAudAlarm | 6646 | A4 | EC | None | Beacon low fluid warning I/O output bit |
| c_LowFluidBoardCntDwnOutputBit | 6647 | I4 | EC | None | Beacon low fluid warning I/O aux output bit |
| c_LowFluidBoardCntDwnOutputLevel | 6648 | A[40] | EC | None | Beacon low fluid warning output level |
| Setup Runtime Preferences – Beacon Control Pot Life Low | | | | | |
| c_PotLifeLowStateEnabledBeacon | 6649 | A4 | EC | None | Enable beacon pot life low state |
| c_PotLifeLowStateEnabledAudAlarm | 6650 | A4 | EC | None | Enable beacon pot life low audible alarm |
| c_PotLifeLowOutputBit | 6651 | I4 | EC | None | Beacon pot life low I/O output bit |
| c_PotLifeLowOutputLevel | 6652 | A[40] | EC | None | Beacon pot life low output level |
| Setup Runtime Preferences – Beacon Control Pot Life Expired | | | | | |
| c_PotLifeExpStateEnabledBeacon | 6653 | I4 | EC | None | Enable beacon pot life expired state |
| c_PotLifeExpStateEnabledAudAlarm | 6654 | I4 | EC | None | Enable beacon pot life expired audible alarm |
| c_PotLifeExpOutputBit | 6655 | I4 | EC | None | Beacon pot life expired I/O output bit |
| c_PotLifeExpOutputLevel | 6656 | A[40] | EC | None | Beacon pot life expired output level |
| Setup Runtime Preferences – Beacon Control Fluidmove Idle State | | | | | |
| c_FMIIdleStateEnabledBeacon | 6657 | A4 | EC | None | Enable beacon idle state |
| c_FMIIdleStateEnabledAudAlarm | 6658 | I4 | EC | None | Enable beacon idle audible alarm |
| c_FMIIdleOutputBit | 6659 | I4 | EC | None | Beacon idle state output bit |
| c_FMIIdleOutputLevel | 6660 | A[40] | EC | None | Beacon idle state output level |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|--|-------|--------------|-------|--------------|---|
| Setup Runtime Preferences – Library Pattern | | | | | |
| LibraryPatternFilename | 1546 | A[100] | SV | None | Library pattern filename |
| LibraryPatternPath | 1547 | A[30] | SV | None | Library pattern path |
| c_AskBeforeUpdatingPatternLibrary | 6718 | A[4] | EC | None | Prompt before updating pattern library |
| Setup Runtime Preferences – Low Pressure Detect | | | | | |
| c_LowAirThreshold | 6661 | I4 | EC | None | Low pressure detect threshold |
| Setup Runtime Preferences – Flowmeter | | | | | |
| c_FlowmeterEnabled | 6662 | A[4] | EC | None | Flowmeter enabled |
| Setup Height Sensor | | | | | |
| c_HeightSensorType | 6033 | A[30] | EC | None | Height sensor type |
| c_ME LaserRangeFinderMode | 6663 | A[4] | EC | None | Enable ME range finder mode |
| c_HeightSenseMode | 6664 | I4 | EC | None | Height sense mode |
| p_BatchHeightSenseCommands | 11625 | A[4] | DV | 3672 | Use batch height sense |
| c_ME LaserHSDownSpeed | 6665 | A[30] | EC | None | ME laser down speed |
| c_ME LaserHSUpSpeed | 6666 | A[30] | EC | None | ME laser up speed |
| c_ME LaserHSAccel | 6667 | A[30] | EC | None | ME laser acceleration |
| c_ME LaserHSMaxDist | 6668 | A[30] | EC | None | ME laser max search distance |
| c_ME LaserHSMaxDistRunTime | 6669 | A[30] | EC | None | ME laser max search distance at runtime |
| c_ME LaserHSRetractDist | 6670 | A[30] | EC | None | ME laser retract distance |
| c_RetractBeforeHeightSense | 6671 | A[4] | EC | None | Enable retract before HS |
| Setup Purge Station | | | | | |
| c_PurgeLocName_V1 | 6297 | A[30] | EC | None | Purge location name Valve 1 |
| c_MonitorPurgeCupOverflowTime | 6672 | A[4] | EC | None | Enable monitor purge cup overflow time |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|----------------------------|-------|--------------|-------|--------------|---|
| c_OverflowTimeLimit | 6571 | I4 | EC | None | Purge cup overflow time limit (minutes) |
| c_ElapsedPurgeTime | 6572 | A[30] | EC | None | Overflow time |
| fc_PurgeDuration | 11201 | A[30] | DV | 3651 | Purge duration |
| c_TimedPurge | 6094 | A[4] | EC | None | Enable timed purge |
| Setup Scale | | | | | |
| c_Enabled | 6101 | A[4] | EC | None | Enable Scale 1 |
| c_ScaleType | 6100 | A[20] | EC | None | SART-WZ |
| c_ReadDelay | 6102 | A[30] | EC | None | Scale read delay |
| c_StabilityTimeout | 6104 | A[30] | EC | None | Scale stability timeout |
| c_CheckScaleCup | 6105 | A[4] | EC | None | Check for missing scale cup |
| c_ScaleLocName_V1 | 6298 | A[4] | EC | None | Scale location Valve 1 |
| c_ScaleCalibWeight | 6673 | A[30] | EC | None | Scale calibration weight |
| Setup Vision | | | | | |
| c_VisionSystem | 6139 | A[30] | EC | None | Vision system type |
| c_VideoMixer | 6140 | A[30] | EC | None | Video mixer type |
| c_DfltGraphicslevel | 6152 | I4 | EC | None | Graphics level |
| c_LightType | 6271 | A[30] | EC | None | Light controller type |
| c_Turnlightoffonexit | 6272 | A[4] | EC | None | Turn light off on exit |
| Setup Vision - Reticles | | | | | |
| c_ReticleCircle1Enable | 6719 | A[4] | EC | None | Enable reticle circle 1 |
| c_ReticleCircle1Diameter | 6720 | A[30] | EC | None | Reticle circle 1 diameter |
| c_ReticleCircle2Enable | 6721 | A[4] | EC | None | Enable reticle circle 2 |
| c_ReticleCircle2Diameter | 6722 | A[30] | EC | None | Reticle circle 2 diameter |
| c_ReticleAdditionalCircles | 6723 | I4 | EC | None | Reticle additional circles |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|----------------------------------|------|--------------|-------|--------------|---|
| c_ReticleRectangleEnable | 6724 | A[4] | EC | None | Enable reticle rectangle |
| c_ReticleRectangleXSize | 6725 | A[30] | EC | None | Reticle rectangle X size |
| c_ReticleRectangleYSize | 6726 | A[30] | EC | None | Reticle rectangle Y size |
| c_ReticleGraduationsIEnable | 6727 | A[4] | EC | None | Reticle graduations enable |
| c_ReticleGraduationsSpacing | 6728 | A[30] | EC | None | Reticle graduations spacing |
| c_ReticleColor | 6729 | I4 | EC | None | Reticle color: Black = 0 White = 1 Red = 2 |
| Setup Vision - General | | | | | |
| c_DfltMotionAntibacklash | 6145 | A[4] | EC | None | Use anti-backlash move |
| Setup Vision - Tolerances | | | | | |
| c_ErrDetfidloctol | 6180 | A[30] | EC | None | Fid location tolerance |
| c_ErrDetdiagdisttol | 6181 | A[30] | EC | None | Diagonal distance tolerance |
| c_DfltCForthogonality | 6178 | A[30] | EC | None | Orthogonality tolerance |
| Setup Vision – Skip Mark Options | | | | | |
| c_DfltMarkPausemode | 6154 | A[4] | EC | None | Pause after search |
| Setup Vision – Fiducial Options | | | | | |
| c_ErrDetfidskipmode | 6183 | A[4] | EC | None | Fid skip if not found |
| c_DfltPausemode | 6153 | A[4] | EC | None | Fid pause after search |
| c_UseFidZPosition | 6191 | A[4] | EC | None | Enable Z positioning |
| c_ApplyCameraRotationCorrection | 6730 | A[4] | EC | None | Apply camera rotation |
| c_FidDripControlEnabled | 6731 | A[4] | EC | None | Enable FID drip control |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|-------------------------------------|-------|--------------|-------|--------------|---|
| Setup Vision – New Program Defaults | | | | | |
| c_DfltImagesettlingtime | 6750 | I4 | EC | None | Post move settling time |
| p_BatchFids | 11614 | A[4] | DV | 3672 | Find fids at program start |
| c_DfltUsePipeline | 6146 | A[4] | EC | None | Use pipeline vision |
| Setup Workpiece Alignment | | | | | |
| c_LearnWorkpieceAngle | 6674 | A[4] | EC | None | Learn WP angle first |
| c_WorkpieceNumberOfFids | 6675 | I4 | EC | None | Number of fiducials |
| c_VerifyWkpcOrgNoFids | 6676 | A[4] | EC | None | Verify WP origin when opening program with no fids. |
| Setup Conveyor 1 | | | | | |
| c_ConveyorControlType_C1 | 6114 | A[20] | EC | None | Conveyor 1 control type |
| c_ConveyorMode_C1 | 6117 | I4 | EC | None | Disabled = 0, Run Continuous = 1, Pass Through = 2 |
| c_StartupFileName_C1 | 6134 | A[60] | EC | None | Conveyor startup filename |
| c_StyleType_C1 | 6116 | A[100] | EC | None | Conveyor style |
| c_BeltSpeed_C1 | 6127 | A[30] | EC | None | Belt speed |
| c_BeltAccel_C1 | 6128 | A[30] | EC | None | Belt acceleration |
| c_LongMove_C1 | 6129 | A[30] | EC | None | Long move |
| c_ShortMove_C1 | 6130 | A[30] | EC | None | Short move |
| c_Retries_C1 | 6131 | A[30] | EC | None | Retries |
| c_BackMove_C1 | 6132 | A[30] | EC | None | Back move |
| c_TwinConveyorWait_C1 | 6126 | I4 | EC | None | Wait for 2 nd board time(dual conveyor) |
| c_ConfirmACWMove | 6113 | A[4] | EC | None | Confirm move to taught width |
| c_ConveyorWidthSpeed | 6754 | A[30] | EC | None | Conveyor width speed |
| c_ConveyorWidthAccel | 6755 | A[30] | EC | None | Conveyor width accel |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|--|------|--------------|-------|--------------|---|
| Setup Conveyor 2 | | | | | |
| c_ConveyorControlType_C2 | 6743 | A[20] | EC | None | Conveyor 2 control type |
| c_ConveyorMode_C2 | 6744 | I4 | EC | None | Disabled = 0, Run Continuous = 1, Pass Through = 2 |
| c_StartupFileName_C2 | 6745 | A[60] | EC | None | Conveyor startup filename |
| c_StyleType_C2 | 6746 | A[100] | EC | None | Conveyor style |
| c_BeltSpeed_C2 | 6747 | A[30] | EC | None | Belt speed |
| c_BeltAccel_C2 | 6748 | A[30] | EC | None | Belt acceleration |
| c_LongMove_C2 | 6749 | A[30] | EC | None | Long move |
| c_ShortMove_C2 | 6750 | A[30] | EC | None | Short move |
| c_Retries_C2 | 6752 | A[30] | EC | None | Retries |
| c_BackMove_C2 | 6751 | A[30] | EC | None | Back move |
| c_TwinConveyorWait_C2 | 6753 | I4 | EC | None | Wait for 2 nd board time(dual conveyor) |
| c_ConfirmACWMove2 | 6679 | A[4] | EC | None | Confirm move to taught width 2 |
| c_ConveyorWidthSpeed | 6754 | A[30] | EC | None | Conveyor width speed |
| c_ConveyorWidthAccel | 6755 | A[30] | EC | None | Conveyor width accel |
| Conveyor Configuration – FmConvey.ini | | | | | |
| ClearPinsMove | 1567 | F8 | SV | None | Clear pins move distance |
| S2RequestDelayMove | 1568 | F8 | SV | None | Station 2 request delay move |
| S3RequestDelayMove | 1569 | F8 | SV | None | Station 3 request delay move |
| ClearDownPinDelay | 1570 | F8 | SV | None | Clear down pin delay |
| S3OutFirst | 1571 | F8 | SV | None | Station 3 out first |
| Automatic Conveyor Width | | | | | |
| c_AutoConveyorWidthEnable | 6677 | A[4] | EC | None | Enable automatic conveyor width |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|---------------------------------|------|--------------|-------|--------------|---------------------------------------|
| c_AutoConveyorWidthEnable2 | 6678 | A[4] | EC | None | Enable automatic conveyor width 2 |
| c_ConfirmACWMove | 6113 | A[4] | EC | None | Confirm move to taught width |
| c_ConfirmACWMove2 | 6679 | A[4] | EC | None | Confirm move to taught width 2 |
| c_AutoConveyorWidthClearance | 6756 | A[30] | EC | None | Automatic conveyor width clearance |
| c_AutoConveyorWidthClearance2 | 6757 | A[30] | EC | None | Automatic conveyor width clearance 2 |
| c_ConveyorWidthSpeed | 6754 | A[30] | EC | None | Conveyor width speed |
| c_ConveyorWidthAccel | 6755 | A[30] | EC | None | Conveyor width accel |
| Heater Configuration | | | | | |
| c_ControlType_H1 | 6018 | A[20] | EC | None | Heater 1 control type |
| c_CpH_Enabled | 6523 | A[4] | EC | None | Enable control process heat |
| c_AutoPurgeEnabled | 6680 | A[4] | EC | None | Auto purge during wait |
| c_EnableSkipWhileWaitingforTemp | 6015 | A[4] | EC | None | Enable skip during wait for temp |
| c_EnabledPurgeBeforeResume | 6014 | A[4] | EC | None | Enable purge before resume |
| c_TurnheatersoffwhenFmntexits | 6016 | A[4] | EC | None | Turn heaters off when Fluidmove exits |
| c_PreHeatTimerEnabled | 6681 | A[4] | EC | None | Enable pre heat timer |
| c_DefaultPreHeatTime | 6683 | A[4] | EC | None | Default pre heat time |
| c_WarnHeaterFileChange | 6684 | A[4] | EC | None | Warn if heater file changed |
| Setup Dispenser | | | | | |
| c_MotionControllerType | 6057 | A[20] | EC | None | Motion controller type |
| c_ScaleFMWPerUnit | 1552 | A[30] | EC | None | FMW units/encoder step |
| FirmwareRev | 1553 | F8 | SV | None | Firmware revision |
| FirmwareBuild | 1554 | A[40] | SV | None | Firmware build |
| c_RunRecoveryEnabled | 6685 | A[4] | EC | None | Run recovery enabled |
| c_RecoveryPromptPosition | 6686 | I4 | EC | None | Recovery instruction position |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|--|------|--------------|-------|--------------|---|
| c_SkipDryRunRecovery | 6687 | A[4] | EC | None | Skip dry run recovery |
| c_WarnIfRecoverySkipped | 6688 | A[4] | EC | None | Warn if recovery skipped |
| c_DoHSRunRecovery | 6689 | A[4] | EC | None | Do height sense in run recovery |
| c_ErrorMapEnabled | 6088 | A[4] | EC | None | Enable correction map |
| c_StartupFileName | 6084 | A[60] | EC | None | Dispenser startup filename |
| Setup Dispenser – Keep Out Zones | | | | | |
| UseKeepoutZones | 7808 | Boolean | EC | None | Enable keep out zones |
| Setup Module Skip | | | | | |
| c_ModuleReaderEnabled | 6690 | A[4] | EC | None | Enable module skipping |
| c_ModuleAutoMode | 1555 | A[4] | EC | None | Automatic mode |
| c_ModuleOutgoingFlowControl | 1556 | I4 | SV | None | Flow control number |
| c_ModuleNumberOfRetries | 1558 | I4 | SV | None | # of read/write retries |
| c_ModuleTeachWindowMode | 1559 | I4 | SV | None | Module teach window mode |
| Setup Event Logging | | | | | |
| c_SuppressLogFile | 6732 | A[4] | EC | None | Suppress log file creation |
| c_CheckDiskSpaceProd | 6691 | A[4] | EC | None | Check disk space for log file during production |
| Setup Trace/Debug Logging | | | | | |
| TrcEnableAllLogs | 7817 | Boolean | EC | None | Enable all trace logs |
| DbgEnableAllLogs | 7816 | Boolean | EC | None | Enable all debug logs |
| DbgSuppressFileCreation (same for trace log) | 7815 | Boolean | EC | None | Suppress file creation |
| DbgWriteToFile | 7812 | Boolean | EC | None | Debug write to file |
| DbgBufferedWrite | 7814 | Boolean | EC | None | Debug buffered write |
| DbgWriteToDbgWindow | 7813 | Boolean | EC | None | Write to debug window |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|--|------|--------------|-------|--------------|---|
| c_CheckDiskSpaceInterval | 6739 | I4 | EC | None | Check disk space board interval |
| c_MinDiskSpaceNeeded | 6740 | I4 | EC | None | Min disk space need to start Fluidmove |
| c_DiskSpaceTooLow | 6741 | I4 | EC | None | Disk space limit - too low to write log files |
| DbgSuppressFileCreation (same for debug log) | 7815 | Boolean | EC | None | Suppress file creation |
| TrcWriteToFile | 7809 | Boolean | EC | None | Trace write to file |
| TrcBufferedWrite | 7811 | Boolean | EC | None | Trace buffered write |
| TrcWriteToDbgWindow | 7810 | Boolean | EC | None | Trace write to debug window |
| c_OutputToFile | 6742 | A[4] | EC | None | Run to file |
| Setup Logging – Automatic file deletion | | | | | |
| c_AutoDeleteLogFiles | 6733 | A[4] | EC | None | Automatic log file delete |
| c_AutoDeleteTrcFiles | 6734 | A[4] | EC | None | Auto delete trace files |
| c_AutoDeleteDbgFiles | 6735 | A[4] | EC | None | Auto delete debug files |
| c_AutoDeleteFilesDaysAfterCreation | 6736 | I4 | EC | None | Auto delete files # days after creation |
| c_AutoDeleteFreqDays | 6737 | I4 | EC | None | Auto delete files every X days |
| c_AutoDeleteFilesUserConfirm | 6738 | A[4] | EC | None | Confirm auto delete files |
| SECS/GEM Configuration | | | | | |
| GemLinkState | 68 | U1 | SV | None | Gem link state |
| GemControlState | 28 | U1 | SV | None | Gem control state |
| GemSpoolState | 53 | U1 | SV | None | Gem spool state |
| GemEstabCommDelay Name = ESTABLISHCOMMUNICATIONSTIMEOUT | 6 | U20 | EC | None | Gem communication timeout |
| DeviceID | 115 | A[12] | SV | None | Gem device id |
| GemInstallVersion | 1563 | A[20] | SV | None | Gem installed version |

Table F.66-1 Additional Configuration Parameter Variables (Continued)

| Variable Name | ID | Storage Type | Class | Related CEID | Description/Default |
|-------------------|------|--------------|-------|--------------|----------------------|
| GemGCPFileVersion | 1564 | A[20] | SV | None | Gem GCP file version |
| GemDriverVersion | 1565 | A[20] | SV | None | Gem driver version |

Glossary

| | |
|--|--|
| TestAlarm | An alarm is related to any abnormal situation on the Equipment that may endanger people, Equipment, or material being processed. GEM allows the Host to be notified when alarm conditions are detected and cleared. |
| ALID | Equipment Alarm ID |
| CEID | Collection Event ID |
| Collection Event | A collection event is a detectable occurrence significant to the Equipment that is considered to be significant to the Host. GEM allows the Host to be notified when a collection event occurs. This allows the Host to track the Equipment's activity. |
| Data Values | Also known as Discrete Data. Meant to be temporary or ephemeral statuses that disappear after an event is complete. Sometimes known as 'DVs' (Data Values), 'DVVALs' (Discrete Data Values). |
| Data Variable (DV) | Data variables may only be valid upon the occurrence of a particular event. The Host may gather data variable values from the GEM Equipment. |
| Equipment | An intelligent system which communicates with a Host and complies with the GEM standard. In this manual it refers to an Asymtek dispensing system. |
| Equipment Constant (EC) | Equipment Constants are settable by the Host. The Host may gather Equipment constant values from the GEM Equipment. The Host may also set Equipment constant values on the GEM Equipment to control the Equipment's behavior. |
| Fluidmove | The Fluidmove [®] for Windows NT [®] or Fluidmove [®] for Windows XP [®] software application which controls GEM. |
| GCD | GWGEM Configuration Data (an ASCII file compiled for GWGEM). |
| GEM | Generic Equipment Model. The GEM (E30) standard defines the generic behavior of semiconductor Equipment as viewed through a communications link in terms of SECS-II messages communicated over that link. The GEM standard impacts Equipment control and Equipment-to-Host communications. |
| High-Speed SECS Message Services (HSMS) | <p>HSMS (E37) is a high-speed replacement and an alternative to SECS-I for applications where higher speed communication is needed or where simple point-to-point technology is insufficient.</p> <p>HSMS defines a communication interface via TCP/IP suitable for the exchange of (SECS-II) messages between computers in a semiconductor factory.</p> |
| Host | The computer which is connected to, and communicates with, the Equipment via the SECS interface. The GEM standard defines a set of messages the Host must use when interacting with the Equipment. The Equipment communicates with one Host, but the Host may communicate with multiple Equipment units. |

| | |
|-----------------------------|--|
| HSMS-GS | High Speed Message Service-General Session. This standard defines TCP/IP network communication used by GEM for Host/Equipment communication. It is intended to be applied for complex systems containing multiple independently accessible subsystems and uses an extended state machine. |
| HSMS-SS | High Speed Message Service-Single Session. This standard defines TCP/IP network communication used by GEM for Host/Equipment communication. It replaces the SECS-I standard. |
| ID | Identifier or Identification. |
| Operator | The person who physically has access to the Equipment's material port(s) and control panel. This is the person who is operating the dispensing system. |
| PP | Process Program |
| Recipe | A file containing a set of instructions for the Equipment. |
| Report | A set of variables predefined by the Equipment or defined by the Host. The Host uses reports to gather status variable, data variable, and Equipment constant values. The Host may request a report explicitly or attach a set of reports to a collection event. |
| SECS | SEMI Equipment Communications Standard. <u>SECS I (E4):</u> SEMI Equipment Communications Standard 1 Message Transfer. Defines RS-232 serial communication used by GEM for Host/Equipment communication. <u>SECS II (E5):</u> SEMI Equipment Communications Standard 2 Message Content. A standard for communications between intelligent Equipment and a Host. The standard defines the communication protocol interface (SECS-I) and the messages exchanged (SECS-II). |
| Message | All GEM Equipment and Host communication is accomplished using SECS-II messages. Each unique SECS-II message is identified by its stream number (S) and function number (F). The SECS-II standard defines a large set of SECS-II messages determining each one's purpose, content, and usage. The GEM standard defines how to use a subset of these SECS-II messages yet allows other SECS-II messages to be used in addition to this subset. |
| SEMI | Semiconductor Equipment and Materials International (SEMI) is a global trade association that represents the semiconductor and flat panel display equipment and materials industries. SEMI maintains and publishes standards that relate to Equipment automation and software. |
| Status Variable (SV) | Status Variable. Status variables may include any parameters that can be sampled in time such as temperature or quantity of a consumable. The Host may gather status variable values from the GEM Equipment. |
| UFPP | Unformatted Process Program |
| VID | Variable Identifier. A unique string representing the name of a variable. |